

Oracle® Database

Move to Oracle Cloud Using Zero Downtime Migration



Release 26 (26.1)

G27612-01

April 2026

ORACLE®

Oracle Database Move to Oracle Cloud Using Zero Downtime Migration, Release 26 (26.1)

G27612-01

Copyright © 2019, 2026, Oracle and/or its affiliates.

Primary Authors: Roopam Jain, Virginia Beecher

Contributors: Ricardo Alonso Gonzalez Acuna, Prakash Jashnani, Jean-Francois Verrier, Sam Ravindhran, Soo Huey Wong, Kamalesh Ramasamy, Annie Chen, Vikash Gunreddy, Gabriel Labrada, Nitin Vira, Adrian Esquivel, Aman Kumar, Daniel Nuño, Pramod Shetty, Jose Luis Velazquez, Ayush Hemnani, Harsh Vishwakarma, Jose Moya, Manik Bhosle, Ricardo Tamez Durandean

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface

Audience

Documentation Accessibility

Related Documents

Conventions

1 Introduction to Zero Downtime Migration

- 1.1 About Zero Downtime Migration
- 1.2 Physical Migrations with Zero Downtime Migration
 - 1.2.1 Physical Online Migration
 - 1.2.2 Physical Offline Migration
 - 1.2.3 Supported Physical Migration Paths
 - 1.2.4 Data Transfer Media Supported for Physical Migrations
 - 1.2.5 Direct Data Transfer Support
 - 1.2.6 Supported Database Architectures for Physical Migration
 - 1.2.7 Oracle Database Edition Support
 - 1.2.8 Target Placeholder Database Environment
- 1.3 Logical Migrations with Zero Downtime Migration
 - 1.3.1 Logical Online Migration
 - 1.3.2 Logical Offline Migration
 - 1.3.3 Supported Logical Migration Targets
 - 1.3.4 Initial Load Methods Supported for Logical Migrations
 - 1.3.5 What Is Migrated During Initial Load
 - 1.3.6 Data Replication
- 1.4 Hybrid Migrations with Zero Downtime Migration
- 1.5 Zero Downtime Migration Requirements and Considerations
 - 1.5.1 Supported Platforms
 - 1.5.2 Supported Database Versions for Migration
 - 1.5.3 Zero Downtime Migration Database Server Access
 - 1.5.4 Zero Downtime Migration Operational Phases
 - 1.5.5 Zero Downtime Migration Security Provisions

2 Setting Up Zero Downtime Migration Software

- 2.1 Prepare a Host for Zero Downtime Migration Software Installation
- 2.2 Install Zero Downtime Migration Software
 - 2.2.1 Customizing Port Numbers
- 2.3 Installing Zero Downtime Migration on VM in Oracle Cloud Infrastructure
 - To install Zero Downtime Migration on Oracle Linux 8 VM in OCI
- 2.4 Installing Zero Downtime Migration on Red Hat Enterprise Linux 8 in an Oracle Cloud Infrastructure Instance
 - To install Zero Downtime Migration on Red Hat Enterprise Linux 8
- 2.5 Installing Zero Downtime Migration on Red Hat Enterprise Linux 9 in an Oracle Cloud Infrastructure Instance
 - To install Zero Downtime Migration on Red Hat Enterprise Linux 9

3 Configuring Required Connections

- 3.1 Logical Migration without SSH Access
- 3.2 Physical and Logical Migration with SSH Access
 - 3.2.1 Migrating with Database User Privileges
 - 3.2.2 Migrating with SUDO User Privilege
- 3.3 Zero Downtime Migration Port Requirements
- 3.4 Configuring Database Connectivity for Online Physical Migration
 - 3.4.1 SQL*Net Connectivity Using SCAN

4 Preparing for a Physical Database Migration

- 4.1 Prerequisites for Online Physical Migration
- 4.2 Preparing the Source and Target Databases
- 4.3 Source Database Prerequisites
- 4.4 Target Database Prerequisites
- 4.5 Setting Up the Transparent Data Encryption Keystore
- 4.6 Using Supported Data Transfer Media
- 4.7 Setting Physical Migration Parameters
- 4.8 Using an Existing RMAN Backup as a Data Source
- 4.9 Using Direct Data Transfer
- 4.10 Using an Existing Standby to Instantiate the Target Database
- 4.11 Preparing for Automatic Application Switchover
- 4.12 Using Oracle Data Guard Broker Role Switchover
- 4.13 Configuring Resiliency to Intermittent Network Failures
- 4.14 Converting a Non-CDB Database to a CDB During Migration
- 4.15 Migrating an On-Premises Database to an On-Premises Exadata Database Machine
- 4.16 Creating an Oracle Cloud Native Disaster Recovery Strategy
- 4.17 Migration and Upgrade of CDB Databases

- 4.18 Migration, Upgrade, and Conversion of a Non-CDB to a PDB Database
- 4.19 Using External Keystores
 - 4.19.1 Migrating Source Database with OKV Keystore Configured as an External Keystore
- 4.20 Migration Using PDB Clone
- 4.21 Setting up the SEPS Wallet

5 Preparing for a Logical Database Migration

- 5.1 Best Practices for a Logical Database Migration
- 5.2 Source Database Prerequisites for Logical Migration
- 5.3 Target Database Prerequisites for Logical Migration
- 5.4 Additional Logical Migration Prerequisites
 - 5.4.1 Additional Connectivity Prerequisites for Oracle GoldenGate Hub
 - 5.4.2 Validating Connections to and from the Oracle GoldenGate Marketplace Instance
 - 5.4.3 Validating Connections to and from an Oracle GoldenGate Docker Deployment
- 5.5 Setting Logical Migration Parameters
- 5.6 Registering a New Region
- 5.7 Configuring the Transfer Medium and Specifying Transfer Nodes
- 5.8 Selecting Objects for Migration
 - 5.8.1 Migrating Objects with Different Oracle GoldenGate Support Modes
- 5.9 Migrating METADATA
- 5.10 Setting Advanced Data Pump Parameters
 - 5.10.1 Default Data Pump Parameter Settings for Zero Downtime Migration
 - 5.10.2 Automatic Tablespace Creation
 - 5.10.3 Automatic Tablespace Remap
 - 5.10.4 Metadata Remapping
 - 5.10.5 Data Pump Error Handling
- 5.11 Migrating Schemas in Parallel Using Batches
- 5.12 Migrating from Amazon Web Services RDS Oracle to Oracle Cloud
 - 5.12.1 Setting Amazon as the Source Environment
 - 5.12.2 Configure Secure Connections
 - 5.12.3 Setup the Source Oracle on Amazon RDS for Oracle GoldenGate
 - 5.12.4 Configuring the Data Transfer Method
 - 5.12.4.1 Setting Up Database Link Transfer Method
 - 5.12.4.2 Setting Up S3 Bucket Data Transfer Medium
- 5.13 Migrating to Oracle Autonomous AI Database on Exadata Cloud@Customer
- 5.14 Migrating to Co-Managed Database Server with NFS Data Transfer Medium
- 5.15 Migrating to Autonomous Database Server with File Storage Service as the Data Transfer Medium
- 5.16 Migrating to non-Autonomous Database with File Storage Service as the Data Transfer Medium
- 5.17 Logical Migration from an Autonomous AI Database
- 5.18 Configuring Per-PDB Extract Using Oracle GoldenGate 21c

6 Performing a Hybrid Offline Migration

- 6.1 Overview
- 6.2 Pre-requisites
- 6.3 Source Database Requirements
- 6.4 Target Database Requirements
- 6.5 Encryption Requirements
- 6.6 Intermediate Storage Requirements
- 6.7 Connectivity Requirements
- 6.8 Preparing for a Hybrid Offline Migration
- 6.9 Migrating the Database
- 6.10 Troubleshooting

7 Performing Migration Using the Instant Deploy Feature

8 Customizing a Migration Job

- 8.1 About Custom Plug-ins with User Actions
- 8.2 Parameters Supplied for Custom Plug-ins with Shell Script User Actions
- 8.3 Variables Supplied for Custom Plug-ins with SQL Based User Actions
- 8.4 User Action Scripts
- 8.5 User Action for Oracle Autonomous AI Database Target and Amazon Web Services RDS Source
- 8.6 Registering User Actions
- 8.7 Creating an Action Template
- 8.8 Associating an Action Template with a Migration Job
- 8.9 Querying Action Plug-ins
- 8.10 Updating Action Plug-ins
- 8.11 Modifying User Action Scripts
- 8.12 Modifying an Action Template
- 8.13 Chained User Action Output
- 8.14 Customizing Job to Setup Standby

9 Migrating Your Database with Zero Downtime Migration

- 9.1 Evaluate the Migration Job
 - 9.1.1 Using the ZDMCLI MIGRATE DATABASE -eval Option
 - 9.1.2 Zero Downtime Migration Schema Analysis with Cloud Premigration Advisor Tool
 - 9.1.3 Configuring Migrations for Remote CPAT Invocation
- 9.2 Migrate the Database

- 9.3 Post-Migration Tasks
- 9.4 Query Migration Job Status
- 9.5 List Migration Job Phases
- 9.6 Pause a Migration Job
- 9.7 Resume a Migration Job
- 9.8 Suspend and Resume a Migration Job
- 9.9 Rerun a Migration Job
- 9.10 Terminate a Running Migration Job
- 9.11 Modify Oracle GoldenGate Processes During a Migration Job
- 9.12 Handling Application Switchover in a Logical Migration
- 9.13 Zero Downtime Migration Centralized Fleet Migration Management

10 Managing the Zero Downtime Migration Service

- 10.1 Starting and Stopping the Zero Downtime Migration Service
- 10.2 Checking Zero Downtime Migration Service Status
- 10.3 Updating Zero Downtime Migration Software
- 10.4 Uninstalling Zero Downtime Migration Software
- 10.5 Performing a Silent Update or Deinstallation
- 10.6 Viewing the Cloud Premigration Advisor Tool Version
- 10.7 Updating the Cloud Premigration Advisor Tool

11 Troubleshooting Zero Downtime Migration

- 11.1 Handling Migration Job Failures

A Database Server Connectivity Using a Bastion Host

B Zero Downtime Migration Encryption Requirements

C Providing Passwords Non-Interactively Using a Wallet

D Zero Downtime Migration Process Phases

E Zero Downtime Migration Physical Migration Response File Parameters Reference

- E.1 BACKUP_PATH
- E.2 DATA_TRANSFER_MEDIUM
- E.3 DATAPATCH_WITH_ONE_INSTANCE_RUNNING

E.4 HOST
E.5 MAX_DATAPATCH_DURATION_MINS
E.6 MIGRATION_METHOD
E.7 NONCDBTOPDB_CONVERSION
E.8 NONCDBTOPDB_SWITCHOVER
E.9 OPC_CONTAINER
E.10 FLASHBACK_ON
E.11 PLATFORM_TYPE
E.12 SHUTDOWN_SRC
E.13 SKIP_FALLBACK
E.14 SKIP_SRC_SERVICE_RETENTION
E.15 SRC_BASTION_HOST_IP
E.16 SRC_BASTION_IDENTITY_FILE
E.17 SRC_BASTION_PORT
E.18 SRC_BASTION_USER
E.19 SRC_CONFIG_LOCATION
E.20 SRC_DB_LISTENER_HOST
E.21 SRC_DB_LISTENER_PORT
E.22 SRC_DB_HOSTNAME
E.23 SRC_DB_PORT
E.24 SRC_HOST_IP
E.25 SRC_HTTP_PROXY_PORT
E.26 SRC_HTTP_PROXY_URL
E.27 SRC_OSS_PROXY_HOST
E.28 SRC_OSS_PROXY_PORT
E.29 SRC_RMAN_CHANNELS
E.30 SRC_SSH_RETRY_TIMEOUT
E.31 SRC_TIMEZONE
E.32 SRC_ZDLRA_WALLET_LOC
E.33 TGT_BASTION_HOST_IP
E.34 TGT_BASTION_IDENTITY_FILE
E.35 TGT_BASTION_PORT
E.36 TGT_BASTION_USER
E.37 TGT_CONFIG_LOCATION
E.38 TGT_DATAACFS
E.39 TGT_DATADG
E.40 TGT_DB_UNIQUE_NAME
E.41 TGT_DB_HOSTNAME
E.42 TGT_DB_PORT
E.43 TGT_HOST_IP
E.44 TGT_HTTP_PROXY_PORT
E.45 TGT_HTTP_PROXY_URL

E.46 TGT_OSS_PROXY_HOST
E.47 TGT_OSS_PROXY_PORT
E.48 TGT_RECOACFS
E.49 TGT_RECODG
E.50 TGT_REDOACFS
E.51 TGT_REDODG
E.52 TGT_RETAIN_DB_UNIQUE_NAME
E.53 TGT_RMAN_CHANNELS
E.54 TGT_SKIP_DATAPATCH
E.55 TGT_SSH_RETRY_TIMEOUT
E.56 TGT_SSH_TUNNEL_PORT
E.57 TGT_ZDLRA_WALLET_LOC
E.58 TGT_STBY_NODE
E.59 TGT_STBY_DB_UNIQUE_NAME
E.60 TGT_STBY_AUTH
E.61 TGT_STBY_SUDO_USER
E.62 TGT_STBY_IDENTITY_FILE
E.63 TGT_STBY_SUDO_PATH
E.64 TGT_STBY_ZDLRA_WALLET_LOC
E.65 ZDM_TGT_STBY_CASCADING
E.66 ZDM_UPGRADE_TARGET_HOME
E.67 ZDM_PRE_UPGRADE_TARGET_HOME
E.68 ZDLRA_CRED_ALIAS
E.69 ZDM_BACKUP_DIFFERENTIAL_SRC_MONITORING_INTERVAL
E.70 ZDM_BACKUP_FULL_SRC_MONITORING_INTERVAL
E.71 ZDM_BACKUP_INCREMENTAL_SRC_MONITORING_INTERVAL
E.72 ZDM_BACKUP_RETENTION_WINDOW
E.73 ZDM_BACKUP_TAG
E.74 ZDM_CLONE_TGT_MONITORING_INTERVAL
E.75 ZDM_CURL_LOCATION
E.76 ZDM_LOG_OSS_PAR_URL
E.77 ZDM_PDB_CLONE_METHOD
E.78 ZDM_ODA_USERNAME
E.79 ZDM_WALLET_ODA_PASSWORD
E.80 ZDM_OPC_RETRY_COUNT
E.81 ZDM_OPC_RETRY_WAIT_TIME
E.82 ZDM_OSS_RECOVER_TGT_MONITORING_INTERVAL
E.83 ZDM_OSS_RESTORE_TGT_MONITORING_INTERVAL
E.84 ZDM_RMAN_COMPRESSION_ALGORITHM
E.85 ZDM_RMAN_DIRECT_METHOD
E.86 ZDM_RMAN_ENCRYPT_BACKUP
E.87 ZDM_RMAN_SECTION_SIZE

E.88 ZDM_SHARD_ID
 E.89 ZDM_SKIP_DG_CONFIG_CLEANUP
 E.90 ZDM_SKIP_TDE_WALLET_MIGRATION
 E.91 ZDM_SRC_DB_RESTORE_SERVICE_NAME
 E.92 ZDM_SRC_TNS_ADMIN
 E.93 ZDM_SRC_DB_OKV_HOME
 E.94 ZDM_SRC_PDB_NAME
 E.95 ZDM_TGT_PDB_NAME
 E.96 ZDM_TGT_DB_OKV_HOME
 E.97 ZDM_TGT_DBLINK_NAME
 E.98 ZDM_TGT_DBLINK_USERNAME
 E.99 ZDM_TGT_DBLINK_PASSWORD_WALLET
 E.100 ZDM_SRC_DB_OKV_VIRTUAL_WALLET_NAME
 E.101 ZDM_TGT_DB_OKV_VIRTUAL_WALLET_NAME
 E.102 ZDM_PDB_REFRESH_INTERVAL
 E.103 ZDM_SWITCHOVER
 E.104 ZDM_STANDBY_DB_CONNECT_STRING
 E.105 ZDM_UPGRADE_OPTIONS
 E.106 ZDM_USE_DG_BROKER
 E.107 ZDM_USE_EXISTING_BACKUP
 E.108 ZDM_USE_EXISTING_STANDBY
 E.109 ZDM_USE_EXISTING_UNDO_SIZE
 E.110 ZDM_TGT_UPGRADE_TIMEZONE
 E.111 ZDM_APPLY_LAG_MONITORING_INTERVAL
 E.112 ZDM_NONCDBTOPDB_PDB_NAME
 E.113 SRC_DB_PASSWORDFILE_LOC
 E.114 SRC_DB_TDE_WALLET_LOC
 E.115 WALLET_SOURCEADMIN
 E.116 WALLET_OSS
 E.117 WALLET_DV
 E.118 WALLET_TDEKEYSTORE
 E.119 WALLET_TGTTDEKEYSTORE
 E.120 WALLET_BACKUP

F Zero Downtime Migration Logical Migration Response File Parameters Reference

F.1 DATA_TRANSFER_MEDIUM
 F.2 DATAPUMPSETTINGS_CREATEAUTHTOKEN
 F.3 DATAPUMPSETTINGS_DATABASELINKDETAILS_NAME
 F.4 DATAPUMPSETTINGS_DATABASELINKDETAILS_WALLETBUCKET_BUCKETNAME
 F.5 DATAPUMPSETTINGS_DATABASELINKDETAILS_WALLETBUCKET_NAMESPACENAME
 F.6 DATAPUMPSETTINGS_DATABUCKET_BUCKETNAME

F.7 DATAPUMPSETTINGS_DATABUCKET_NAMESPACENAME
 F.8 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_ESTIMATEBYSTATISTICS
 F.9 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_TABLEEXISTSACTION
 F.10 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_USERMETADATA
 F.11 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_IMPORTPARALLELISMDEGREE
 F.12 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXPORTPARALLELISMDEGREE
 F.13 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_DISABLESTATSGATHERING
 F.14 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_ENCRYPTION
 F.15 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXCLUDETYPELIST
 F.16 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_FLASHBACKTIME
 F.17 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_SKIPCURRENT
 F.18 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_NOCLUSTER
 F.19 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_RETAININDEX
 F.20 DATAPUMPSETTINGS_DATAPUMPPARAMETERS_PARTITIONOPTION
 F.21 DATAPUMPSETTINGS_DELETEDUMPSINOSS
 F.22 DATAPUMPSETTINGS_ENABLETRACE
 F.23 DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_NAME
 F.24 DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_PATH
 F.25 DATAPUMPSETTINGS_EXPORTVERSION
 F.26 DATAPUMPSETTINGS_FIXINVALIDOBJECTS
 F.27 DATAPUMPSETTINGS_IGNOREERROR
 F.28 DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_PATH
 F.29 DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_NAME
 F.30 DATAPUMPSETTINGS_JOBMODE
 F.31 DATAPUMPSETTINGS_METADATAFILTERS-LIST_ELEMENT_NUMBER
 F.32 DATAPUMPSETTINGS_METADATAAREMAPS-LIST_ELEMENT_NUMBER
 F.33 DATAPUMPSETTINGS_METADATATRANSFORMS-LIST_ELEMENT_NUMBER
 F.34 DATAPUMPSETTINGS_METADATAAFIRST
 F.35 DATAPUMPSETTINGS_MONITORINTERVALMINUTES
 F.36 DATAPUMPSETTINGS_OMITENCRYPTIONCLAUSE
 F.37 DATAPUMPPARAMETER_<PARAMETER_NAME>
 F.38 DATAPUMPSETTINGS_RETAINDUMPS
 F.39 DATAPUMPSETTINGS_REUSE_DUMPMPREFIX
 F.40 DATAPUMPSETTINGS_SECUREFILELOB
 F.41 DATAPUMPSETTINGS_SCHEMABATCHCOUNT
 F.42 DATAPUMPSETTINGS_SCHEMABATCH-LIST_ELEMENT_NUMBER
 F.43 DATAPUMPSETTINGS_SKIPDEFAULTTRANSFORM
 F.44 DATAPUMPSETTINGS_TEXTINDEX_METHOD
 F.45 DATAPUMPSETTINGS_TRACELEVEL
 F.46 DUMPTRANSFERDETAILS_PUBLICREAD
 F.47 DUMPTRANSFERDETAILS_PARALLELCOUNT
 F.48 DUMPTRANSFERDETAILS_RETRYCOUNT

F.49 DUMPTRANSFERDETAILS_RSYNCAVAILABLE
F.50 DUMPTRANSFERDETAILS_S3BUCKET_ACCESSKEY
F.51 DUMPTRANSFERDETAILS_S3BUCKET_NAME
F.52 DUMPTRANSFERDETAILS_S3BUCKET_REGION
F.53 DUMPTRANSFERDETAILS_SHAREDSTORAGE_NAME
F.54 DUMPTRANSFERDETAILS_SHAREDSTORAGE_HOST
F.55 DUMPTRANSFERDETAILS_SHAREDSTORAGE_PATH
F.56 DUMPTRANSFERDETAILS_SHAREDSTORAGE_DETACHFSSPOST
F.57 DUMPTRANSFERDETAILS_SOURCE_OCIHOME
F.58 DUMPTRANSFERDETAILS_SOURCE_PARTSIZEMB
F.59 DUMPTRANSFERDETAILS_SOURCE_NOSSHUPLOADMETHOD
F.60 DUMPTRANSFERDETAILS_SOURCE_OCIWALLETLOC
F.61 DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_DUMPDIRPATH
F.62 DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_HOST
F.63 DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_SUDOPATH
F.64 DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_USER
F.65 DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_USERKEY
F.66 DUMPTRANSFERDETAILS_SOURCE_USEOCICLI
F.67 DUMPTRANSFERDETAILS_SRCPROXY_HOSTNAME
F.68 DUMPTRANSFERDETAILS_SRCPROXY_PORT
F.69 DUMPTRANSFERDETAILS_SRCPROXY_PROTOCOL
F.70 DUMPTRANSFERDETAILS_TARGET_OCIHOME
F.71 DUMPTRANSFERDETAILS_TARGET_NOSSHUPLOADMETHOD
F.72 DUMPTRANSFERDETAILS_TARGET_OCIWALLETLOC
F.73 DUMPTRANSFERDETAILS_TARGET_PARTSIZEMB
F.74 DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_DUMPDIRPATH
F.75 DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_HOST
F.76 DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_SUDOPATH
F.77 DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_USER
F.78 DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_USERKEY
F.79 DUMPTRANSFERDETAILS_TARGET_USEOCICLI
F.80 DUMPTRANSFERDETAILS_TRANSFERTARGET_DUMPDIRPATH
F.81 DUMPTRANSFERDETAILS_TRANSFERTARGET_HOST
F.82 DUMPTRANSFERDETAILS_TRANSFERTARGET_SUDOPATH
F.83 DUMPTRANSFERDETAILS_TRANSFERTARGET_USER
F.84 DUMPTRANSFERDETAILS_TRANSFERTARGET_USERKEY
F.85 DUMPTRANSFERDETAILS_TGTPROXY_HOSTNAME
F.86 DUMPTRANSFERDETAILS_TGTPROXY_PORT
F.87 DUMPTRANSFERDETAILS_TGTPROXY_PROTOCOL
F.88 EXCLUDEOBJECTS-LIST_ELEMENT_NUMBER
F.89 FIXINVALIDS_ENABLED
F.90 FIXINVALIDS_BYSCHEMA

F.91 FIXINVALIDS_PARALLELCOUNT
 F.92 FIXINVALIDS_RETRYCOUNT
 F.93 GOLDENGATEHUB_ALLOWSELSIGNEDCERTIFICATE
 F.94 GOLDENGATEHUB_ADMINUSERNAME
 F.95 GOLDENGATEHUB_COMPUTEID
 F.96 GOLDENGATEHUB_SOURCEDEPLOYMENTNAME
 F.97 GOLDENGATEHUB_TARGETDEPLOYMENTNAME
 F.98 GOLDENGATEHUB_URL
 F.99 GOLDENGATESETTINGS_ACCEPTABLELAG
 F.100 GOLDENGATESETTINGS_EXTRACT_PERFORMANCEPROFILE
 F.101 GOLDENGATESETTINGS_EXTRACT_WARNLONGTRANS_CHECKINTERVAL
 F.102 GOLDENGATESETTINGS_EXTRACT_WARNLONGTRANS_DURATION
 F.103 GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS
 F.104 GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS
 F.105 GOLDENGATESETTINGS_EXCLUDERELOAD
 F.106 GOLDENGATESETTINGS_SKIPRELOADQUERYADVISOR
 F.107 GOLDENGATESETTINGS_EXTRACT_PARALLELISM
 F.108 GOLDENGATESETTINGS_RELOADUNREPLICATEDOBJECTS
 F.109 GOLDENGATESETTINGS_REPLICAT_MAPPARALLELISM
 F.110 GOLDENGATESETTINGS_REPLICAT_MAXAPPLYPARALLELISM
 F.111 GOLDENGATESETTINGS_REPLICAT_MINAPPLYPARALLELISM
 F.112 GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE
 F.113 GOLDENGATESETTINGS_REPLICATEDDL
 F.114 GOLDENGATESETTINGS_RELOADAQOBJECTS
 F.115 GOLDENGATESETTINGS_REPLICATIONMODE
 F.116 GOLDENGATESETTINGS_REPLICAT_SPLITTRANSRECS
 F.117 GOLDENGATESETTINGS_FEATUREGROUP
 F.118 GOLDENGATESETTINGS_ENABLEPROCEDURALREPLICATION
 F.119 GOLDENGATESETTINGS_ENABLEEVENTBASEDSWITCHOVER
 F.120 GENFIXUP
 F.121 GOLDENGATESETTINGS_USEFLASHBACKQUERY
 F.122 GOLDENGATESETTINGS_USEMIGRATIONMODE
 F.123 IGNOREEXPORTERRORS
 F.124 IGNOREIMPORTERRORS
 F.125 IGNOREPHASEERRORS-n
 F.126 IGNOREERROR
 F.127 INCLUDEOBJECTS-LIST_ELEMENT_NUMBER
 F.128 MIGRATION_METHOD
 F.129 MIGRATE_APEX
 F.130 MIGRATE_AWR
 F.131 MIGRATE_STS
 F.132 OCIAUTHENTICATIONDETAILS_REGIONID

F.133 OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_FINGERPRINT
 F.134 OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_PRIVATEKEYFILE
 F.135 OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_TENANTID
 F.136 OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_USERID
 F.137 OCIPROXY_HOSTNAME
 F.138 OCIPROXY_PORT
 F.139 OCIPROXY_PROTOCOL
 F.140 OCISDKCONFIG_REGISTERREGIONDETAILS_REALM_KEY
 F.141 OCISDKCONFIG_REGISTERREGIONDETAILS_REALM_DOMAINCOMPONENT
 F.142 OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_ID
 F.143 OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_KEY
 F.144 OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_REALMKEY
 F.145 PROFILE
 F.146 RUNCPATREMOTELY
 F.147 RUNFIXUPS
 F.148 REFRESHMVIEWS
 F.149 RELOADOBJECTS-LIST_ELEMENT_NUMBER
 F.150 COPYCPATREPORTTOZDMHOST
 F.151 FORCECPATENUSLOCALE
 F.152 SOURCECONTAINERDATABASE_ADMINUSERNAME
 F.153 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE
 F.154 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP
 F.155 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT
 F.15 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP
 6
 F.157 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME
 F.158 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_HOST
 F.159 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PORT
 F.160 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL
 F.161 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME
 F.162 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT
 F.163 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_SERVICENAME
 F.1 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_TLSDetails_CREDENTIALSLOCATION
 64
 F.16 SOURCECONTAINERDATABASE_CONNECTIONDETAILS_TLSDetails_DISTINGUISHEDNAME
 5
 F.166 SOURCECONTAINERDATABASE_GGADMINUSERNAME
 F.167 SOURCEDATABASE_ADMINUSERNAME
 F.168 SOURCEDATABASE_ALLOWWEMPTABLE
 F.169 SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE
 F.170 SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP
 F.171 SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT
 F.172 SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP

F.173	SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME	F
F.174	SOURCEDATABASE_CONNECTIONDETAILS_HOST	F
F.175	SOURCEDATABASE_CONNECTIONDETAILS_PORT	F
F.176	SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME	F
F.177	SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT	F
F.178	SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL	F
F.179	SOURCEDATABASE_CONNECTIONDETAILS_SERVICENAME	F
F.180	SOURCEDATABASE_CONNECTIONDETAILS_TLSDETAILS_CREDENTIALSLOCATION	F
F.181	SOURCEDATABASE_CONNECTIONDETAILS_TLSDETAILS_DISTINGUISHEDNAME	F
F.182	SOURCEDATABASE_ENVIRONMENT_DBTYPE	F
F.183	SOURCEDATABASE_ENVIRONMENT_NAME	F
F.184	SOURCEDATABASE_GGADMINUSERNAME	F
F.185	SOURCEDATABASE_OCID	F
F.186	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_HOST	F
F.187	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_PORT	F
F.188	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_SERVICENAME	F
F.189	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_TLSDETAILS_DISTINGUISHEDNAME	F
F.19	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_TLSDETAILS_CREDENTIALSLOCATION	F
0		
F.191	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP	F
F.192	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT	F
F.193	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE	F
F.194	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME	F
F.195	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP	F
F.196	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL	F
F.197	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME	F
F.198	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT	F
F.199	STS_SCHEMANAME	F
F.200	STS_SQLSETNAME	F
F.201	STS_SQLSETREPLACE	F
F.202	STS_SQLSETOWNER	F
F.203	TABLESPACEDETAILS_AUTOCREATE	F
F.204	TABLESPACEDETAILS_AUTOREMAP	F
F.205	TABLESPACEDETAILS_EXCLUDE	F
F.206	TABLESPACEDETAILS_EXTENDSIZEMB	F
F.207	TABLESPACEDETAILS_REMAPTARGET	F
F.208	TABLESPACEDETAILS_REMAPTEMPTARGET	F
F.209	TABLESPACEDETAILS_USEBIGFILE	F
F.210	TABLESPACEDETAILS_BLOCKSIZE	F
F.211	TARGETDATABASE_ADMINUSERNAME	F
F.212	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE	F
F.213	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP	F

F.214	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT	F
F.215	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP	F
F.216	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME	F
F.217	TARGETDATABASE_CONNECTIONDETAILS_HOST	F
F.218	TARGETDATABASE_CONNECTIONDETAILS_PORT	F
F.219	TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME	F
F.220	TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT	F
F.221	TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL	F
F.222	TARGETDATABASE_CONNECTIONDETAILS_SERVICENAME	F
F.223	TARGETDATABASE_CONNECTIONDETAILS_TLSDETAILS_CREDENTIALSLOCATION	F
F.224	TARGETDATABASE_CONNECTIONDETAILS_TLSDETAILS_DISTINGUISHEDNAME	F
F.225	TARGETDATABASE_GGADMINUSERNAME	F
F.226	TARGETDATABASE_OCID	F
F.227	TARGETDATABASE_DBTYPE	F
F.228	WALLET_USERACTION	F
F.229	WALLET_AMAZONS3SECRET	F
F.230	WALLET_OCIAUTHTOKEN	F
F.231	WALLET_DATAPUMPENCRYPTION	F
F.232	WALLET_OGGADMIN	F
F.233	WALLET_SOURCECONTAINER	F
F.234	WALLET_SOURCECGGADMIN	F
F.235	WALLET_SOURCEGGADMIN	F
F.236	WALLET_TARGETADMIN	F
F.237	WALLET_TARGETGGADMIN	F
F.238	WALLET_OGGSERVICEADMIN	F

G Zero Downtime Migration Hybrid Migration Response File Parameters Reference

G.1	MIGRATION_METHOD
G.2	DATA_TRANSFER_MEDIUM
G.3	TARGETDATABASE_ADMINUSERNAME
G.4	SOURCEDATABASE_ADMINUSERNAME
G.5	DATAPUMPSETTINGS_DATAPUMPPARAMETERS_IMPORTPARALLELISMDEGREE
G.6	DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXPORTPARALLELISMDEGREE
G.7	DATAPUMPSETTINGS_DATAPUMPPARAMETERS_NOCLUSTER
G.8	DATAPUMPSETTINGS_EXPORTVERSION
G.9	DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_NAME
G.10	DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_PATH
G.11	DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_NAME
G.12	DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_PATH
G.13	DUMPTRANSFERDETAILS_PUBLICREAD
G.14	IGNOREEXPORTERRORS

G.15 IGNOREIMPORTERRORS
 G.16 RMANSETTINGS_SRCCHANNELS
 G.17 RMANSETTINGS_TGTCHANNELS
 G.18 RMANSETTINGS_RETENTIONWINDOW
 G.19 RMANSETTINGS_BACKUPTAG
 G.20 RMANSETTINGS_SECTIONSIZE
 G.21 RMANSETTINGS_COMPRESSIONALGORITHM
 G.22 RMANSETTINGS_PUBLICREAD
 G.23 SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE
 G.24 SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP
 G.25 SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT
 G.26 SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP
 G.27 SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME
 G.28 SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME
 G.29 SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT
 G.30 SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL
 G.31 SOURCEDATABASE_ENVIRONMENT_DBTYPE
 G.32 SOURCEDATABASE_ENVIRONMENT_NAME
 G.33 TARGETDATABASE_CONNECTIONDETAILS_HOST
 G.34 TARGETDATABASE_CONNECTIONDETAILS_PORT
 G.35 TARGETDATABASE_CONNECTIONDETAILS_SERVICENAME
 G.36 SOURCEDATABASE_CONNECTIONDETAILS_HOST
 G.37 SOURCEDATABASE_CONNECTIONDETAILS_PORT
 G.38 SOURCEDATABASE_CONNECTIONDETAILS_SERVICENAME
 G.39 TABLESPACEDETAILS_EXCLUDE
 G.40 TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE
 G.41 TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP
 G.42 TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT
 G.43 TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP
 G.44 TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME
 G.45 TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME
 G.46 TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT
 G.47 TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL
 G.48 TARGETDATABASE_DBTYPE
 G.49 WALLET_DATAPUMPENCRYPTION
 G.50 WALLET_SOURCEADMIN
 G.51 WALLET_TARGETADMIN
 G.52 WALLET_TDEKEYSTORE
 G.53 WALLET_TGTTDEKEYSTORE
 G.54 WALLET_USERACTION

H Zero Downtime Migration ZDMCLI Command Reference

- H.1 ZDMCLI Options
- H.2 abort job
- H.3 add imagetype
- H.4 add useraction
- H.5 migrate database
- H.6 modify imagetype
- H.7 modify job
- H.8 modify useraction
- H.9 query audit
- H.10 query job
- H.11 query useraction
- H.12 resume job
- H.13 suspend job
- H.14 delete job
- H.15 delete useraction
- H.16 delete imagetype

I Setting Up SSH Key Based Authentication

- I.1 Generate SSH Keys Without a Passphrase
- I.2 Set up an SSH Tunnel for Online Physical Migration

Index

Preface

This book provides information about Zero Downtime Migration capabilities, how to set up the Zero Downtime Migration service, how to prepare your source and target databases for migration, and how to use the Zero Downtime Migration tool to quickly and smoothly move your Oracle databases to the Oracle Cloud or any Oracle Exadata Database Machine environment without incurring any significant downtime.

Audience

This book is intended for anyone who wants to learn about what Zero Downtime Migration can do, and for anyone tasked with migrating Oracle databases.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.

Related Documents

See [Zero Downtime Migration](#) on the Oracle Help Center for all published Zero Downtime Migration documentation.

See Zero Downtime Migration Release Notes for the latest information about what's new in this release, known issues, and troubleshooting solutions.

See the README file included with the downloaded Zero Downtime Migration software for additional information about installation.

See Zero Downtime Migration Licensing Information User Manual for information about third party licenses included in the Zero Downtime Migration software kit.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.

Convention	Meaning
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

1

Introduction to Zero Downtime Migration

Learn about how Zero Downtime Migration works, and its requirements and supported configurations.

1.1 About Zero Downtime Migration

Zero Downtime Migration provides a robust, flexible, and resumable migration process. Zero Downtime Migration integrates Oracle Maximum Availability Architecture (MAA) and supports Oracle Database 11g Release 2 (11.2.0.4) and later database releases.

You can perform and manage a database migration of an individual database or perform database migrations at a fleet level. Leveraging technologies such as Oracle Data Guard, Oracle Recovery Manager (RMAN), Oracle GoldenGate, and Oracle Data Pump, Transportable Tablespaces and Pluggable Database (PDB) Cloning, you can migrate databases online or offline.

Using Zero Downtime Migration, you can migrate Oracle databases from a variety of on premises and cloud sources to Oracle Databases into any Oracle-owned infrastructure, including Exadata Database Machine on-premises, Oracle Database Appliance, Exadata Cloud@Customer, Base Database Service, Exadata Database Service on Dedicated Infrastructure and on Exascale. Including Oracle Cloud Database Services at Oracle AI Database@Azure, Oracle AI Database@Google Cloud, and Oracle AI Database@AWS.

The Zero Downtime Migration software is a service with a command line interface that you install and run on a host that you provision. The server where the Zero Downtime Migration software is installed is called the Zero Downtime Migration service host. You can run one or more database migration jobs from the Zero Downtime Migration service host simultaneously.

Starting in release ZDM 26, a new feature, Instant Deploy, offers a no-install option, where ZDM can be deployed directly on the source or the target database server.

Zero Downtime Migration Capabilities

- **Audit capability** - All custom user actions are audited including actions performed by the migration job.
- **Work flow customization** - You can customize the migration work flow (marked by operational phases) with your own scripts, which can be run before or after any phase in the work flow.
- **Job subsystem** - You can perform and manage database migrations at a fleet scale.
- **Job scheduler** - You can schedule your migration job to run at a future point in time.
- **Pause and resume functionality** - You can schedule a job pause, and then resume your migration job if needed, which is useful to conform to a maintenance window, for example.
- **Suspend and resume functionality** - You can suspend a running job and resume it later, which is useful to circumvent any high workload in the database caused by migration activity, for example.
- **Job termination** - You can terminate a running migration job, rather than waiting for it to complete.

- **Job rerun ability** - Your migration job can be re-run (resumed) from a point of failure.
- **Job pre-check** - You can run pre-checks for migration tasks to prevent errors during database migration.
- **Compliance** - Zero Downtime Migration is compliant with Oracle Maximum Availability Architecture best practices and supports Oracle Database 11g Release 2 (11.2.0.4.0) and later.

Zero Downtime Migration Concepts

- **Online** migration methods incur zero or minimal downtime (typically less than 15 minutes) and can leverage either physical or logical migration methods.
- **Offline** migration methods will incur downtime on the source database as part of the migration process. It can leverage either physical, logical, or hybrid migration methods.
- **Physical** migration methods:
 - Use Oracle Data Guard and RMAN, or Pluggable Database (PDB) cloning to perform migrations
 - Allow you to convert a non-multitenant (non-CDB) source database to a multitenant (CDB) target database
 - Allow you to migrate from Oracle Database 11g Release 2 (11.2.0.4) source database to a Oracle Database 12c Release 1 (12.1.0.2) or Oracle Database 19c target database, or from an Oracle Database 19c source database to an Oracle AI Database 26ai target database. This is accomplished leveraging a temporary auxiliary database.
- **Logical** migration methods:
 - Use Oracle Data Pump and, for online migrations, Oracle GoldenGate Microservices
 - Allow you to perform cross-platform migration where the source Oracle Database is running on Oracle Solaris or IBM AIX operating system, and the target is an Oracle Autonomous AI Database or Co-managed Oracle Database on Oracle Linux.
 - Include integration with the Cloud Premigration Advisor Tool (CPAT), which a) warns you about any features used by your database that aren't supported in the target cloud environment, and b) makes suggestions for remedial changes and/or parameters to use for the Data Pump export and import operations
- **Hybrid** migration methods:
 - Use Oracle RMAN Transportable Tablespaces for Data and Data Pump for Metadata for offline migrations.
 - Allows you to perform cross-platform migration where the source Oracle Database is running on Oracle Solaris or IBM AIX operating system.

Table 1-1 ZDM migration methods and their migration technologies and data transfer mechanisms

Migration Method	High Availability	Migration Technology	Data Transfer Mechanisms Supported
Hybrid	Offline Backup-Restore ¹	Oracle RMAN Oracle Data Pump	Shared Storage - NFS
Physical Block copy	Offline Backup-Restore ¹	Oracle RMAN	<ul style="list-style-type: none"> • Oracle Cloud Object Store • Oracle ZDLRA • Shared Storage - NFS

Table 1-1 (Cont.) ZDM migration methods and their migration technologies and data transfer mechanisms

Migration Method	High Availability	Migration Technology	Data Transfer Mechanisms Supported
	Online	Oracle RMAN	<ul style="list-style-type: none"> • Direct Restore from service • Database Link
	Backup-Restore ²	Oracle Data Guard	
	Physical Standby-Switchover		
Logical SQL Unload-Reload	PDB cloning		<ul style="list-style-type: none"> • Oracle Cloud Object Store <ul style="list-style-type: none"> — oci-cli • Shared Storage - NFS • Secure Copy • Database Link • Amazon S3²
	Offline (cold, hot)		
	Online (refreshable clone)		
	Offline	Oracle Data Pump	
	Export-Import		
	Online	Oracle Data Pump	
	Export-Import	Oracle GoldenGate	
	Extract-Replicat		

¹Full Backup is optional for Physical migration only; pre-existing backup can be used. For hybrid migration, all backups are performed all the time, there is no use existing backup feature applicable for hybrid. Backup is optional; pre-existing backup can be used. ZDM supports existing backups, only for NFS and even then ZDM performs incremental backup.

²Migration from AWS only

The migration methods are described in the following topics.

- [Physical Migrations with Zero Downtime Migration](#)
- [Logical Migrations with Zero Downtime Migration](#)

1.2 Physical Migrations with Zero Downtime Migration

Physical migrations with Zero Downtime Migration use the Recovery Manager (RMAN), Oracle Data Guard, and PDB Cloning to perform the data transfer from the source to the target database, and can handle the role switch of the target database to primary database for application connections.

1.2.1 Physical Online Migration

Zero Downtime Migration harnesses Oracle Data Guard to perform an online physical migration.

A Zero Downtime Migration online physical migration does the following:

- Backs up the source database to the specified data transfer medium
- Instantiates a standby database from this backup to the target environment
- Configures Data Guard with Maximum Performance protection mode and asynchronous (ASYNC) redo transport mode
- Synchronizes the source and target databases

- Switches over to the target database as the new primary database with minimum downtime

Upon switchover, the target database becomes the primary database, and the source database becomes the standby.

If there is SQL*Net connectivity from the new primary and the new standby after the switchover, the configuration continues to synchronize data (ship redo) from the new primary to the new standby source database. This configuration makes it possible to perform a rollback with minimal downtime, if you need to switch the primary back to the original source database.

However, if there is no SQL*Net connectivity from the new primary and the new standby after the switchover, there is no data synchronization (ship redo) from the new primary to the new standby on the source database. With this configuration you cannot fall back to the original source database.

Note that any fallback operation must be done manually; Zero Downtime Migration does not handle reverse role switches to fall back to the original source database as the primary database.

① Note

- When migrating to the cloud, TDE is mandatory for Oracle Database 12.2 and later releases.
- The source must have TDE configured. The tablespaces on the source do not need to be encrypted. The tablespaces on the target will be encrypted when using backup/restore or restore from service.
- When the target is on-premises Oracle Exadata Database Machine (`NON_CLOUD`), you can choose to not use TDE and to skip TDE at the source by specifying `ZDM_TDE_MANDATORY=FALSE`. In this case, the target will not use TDE.
- If the source has TDE enabled, then the target will also use TDE.

1.2.2 Physical Offline Migration

Zero Downtime Migration can perform a backup and restore operation to achieve an offline physical migration.

A Zero Downtime Migration offline physical migration does the following:

- Backs up the source database to the specified data transfer medium
- Instantiates a new database from this backup to the target environment

The offline migration method is similar to cloning a database. The target database has no relationship to the source, so there is no data synchronization or fallback capability. No SQL*Net connectivity is needed between the source and target database servers.

Note that for physical migrations, the offline methodology is the only one that supports Oracle Database Standard Edition 2.

1.2.3 Supported Physical Migration Paths

Zero Downtime Migration supports the following physical migration paths.

- On-premises Oracle Database to Oracle Cloud Infrastructure (either virtual machine or bare metal)
- On-premises Oracle Database to Oracle Exadata Database Service on Dedicated Infrastructure
- On-premises Oracle Database to Oracle Exadata Database Service on Cloud@Customer
- On-premises Oracle Database to On-Premises Exadata Database Machine
- On-premises Oracle Database to Oracle Exadata Database Service on Exascale Infrastructure (ExaDB-XS)
- On-premises Oracle Database to Oracle Exadata Database Service on Dedicated Infrastructure (ExaDB-D) on Oracle AI Database@Hyperscaler:
 - Oracle AI Database@Azure
 - Oracle AI Database@Google Cloud
 - Oracle AI Database@AWS

Note

Currently, physical online migration with direct data transfer is the supported workflow.

For more information, see:

- [Physical Online Migration to ExaDB-D on Oracle AI Database @Azure](#)
- [Physical Offline Migration to ExaDB-D on Oracle AI Database@Azure](#)
- [Physical Online Migration to ExaDB-D on Oracle AI Database@Google Cloud](#)
- [Physical Offline Migration to ExaDB-D on Oracle AI Database@Google Cloud](#)
- [Physical Online Migration to Exadata Database Service on Oracle AI Database@AWS](#)
- [Physical Offline Migration to Exadata Database Service on Oracle AI Database@AWS](#)
- Oracle Cloud Infrastructure Classic Database to Oracle Cloud Infrastructure (either virtual machine or bare metal)
- Oracle Cloud Infrastructure Database to a database in the same or another Oracle Cloud Infrastructure region.
For example, you can move a database from the `phoenix` commercial OCI region to the `frankfurt` or `ashburn` region.
- Oracle Database Appliance source database to Oracle Database Appliance target database.

Note

ZDM supports both Oracle Database Appliance Base Database Service and Oracle Database Appliance KVM and you can both as the source or the target databases.

Related Topics

- [Migrate Oracle Databases to ExaDB-D on Oracle AI Database@Google Cloud with Zero Downtime Migration](#)

- [Oracle Zero Downtime Migration - Physical Online Migration to ExaDB-D on Oracle AI Database@Google Cloud](#)
- [Migrate Oracle Databases to ExaDB-D on Oracle AI Database@AWS with Zero Downtime Migration \(ZDM\)](#)
- [Oracle Zero Downtime Migration - Physical Online Migration to Exadata Database Service on Oracle AI Database@AWS](#)

1.2.4 Data Transfer Media Supported for Physical Migrations

The Zero Downtime Migration physical migration process involves creating a backup of the source database and restoring it to the target database. Zero Downtime Migration supports the following backup media, depending on your target environment.

- Oracle Cloud Infrastructure Object Storage
- Zero Data Loss Recovery Appliance
- Database Links for PDB Cloning
- Network File System (NFS)

Note

Oracle ACFS NAS - MAX is fully supported for both physical and logical migration scenarios where NFS is selected as the transfer medium of choice.

1.2.5 Direct Data Transfer Support

Zero Downtime Migration supports direct data transfer during a physical migration to avoid backing up the source database to an intermediate store such as Object Storage or NFS.

Backing up a large database to intermediate storage adds additional overhead because of the additional hop that the data has to be moved to. This intermediate step can be costly in migrations involving very large databases. Recovery Manager (RMAN) allows Zero Downtime Migration to support active database duplication and restore from service.

Active database duplication does not require backups of the source database. It duplicates the live source database to the destination host by copying the database files over the network to the auxiliary instance. RMAN can copy the required files as image copies or backup sets.

With restore from service, RMAN restores database files, over the network, by using the `FROM SERVICE` clause of the `RESTORE` command. During the restore operation RMAN creates backup sets of the files that need to be restored and then transfers these backup sets to the target database over the network.

Restore from service also allows you to transfer data from a Oracle Data Guard standby database, reducing the load on your primary database system.

1.2.6 Supported Database Architectures for Physical Migration

Zero Downtime Migration supports the following database architecture implementations.

- Oracle Database Single-Instance, which can be migrated to a single-instance or Oracle RAC database target
- Oracle RAC One Node, which can be migrated to an Oracle RAC database target

- Oracle RAC, which can be migrated to an Oracle RAC database target

1.2.7 Oracle Database Edition Support

Zero Downtime Migration supports migrations of Standard and Enterprise Edition Oracle databases.

While Standard Edition databases can use Zero Downtime Migration, they must use the offline migration method which is based on a backup and restore methodology that does not use Data Guard.

Enterprise Edition can be migrated using the offline or online method.

1.2.8 Target Placeholder Database Environment

Zero Downtime Migration requires that you configure a placeholder database target environment before beginning the migration process. Zero Downtime Migration uses the provisioned target as a template and recreates the target during the course of migration.

You should configure the target database with the required and desired options of your native environment, because Zero Downtime Migration does not preserve this automatically during the migration.

During the migration process, the Zero Downtime Migration service host restores the source database to this placeholder database target environment by dropping the placeholder database and recreating a database in the target environment with the same `db_name` as that of source database.

Any database parameters for the target database, including SGA parameters, are maintained during the migration, and the migrated database runs with this same configuration.

Once the migration is complete, the target database is accessible using Oracle Database Cloud Service console, and you can manage the database with SRVCTL commands. You can make any modifications to database parameters after the migration.

1.3 Logical Migrations with Zero Downtime Migration

Online and offline logical migrations using Zero Downtime Migration are described in the following topics:

1.3.1 Logical Online Migration

Zero Downtime Migration harnesses Oracle GoldenGate and Oracle Data Pump to perform an online logical migration.

During a logical online migration, the source database remains online for client connections while data is moved to the target database, using a combination of Oracle Data Pump and Oracle GoldenGate replication.

Note that for migrations to OCI targets you can use the [Oracle GoldenGate license](#) from Oracle Cloud Marketplace, which is the Oracle-certified way of deploying the GoldenGate hub in Oracle Cloud Infrastructure.

Note

For migrations to Oracle AI Database@Google Cloud, Oracle AI Database@Azure and Oracle AI Database@AWS, you can use the Oracle GoldenGate for Multicloud Database Migrations container from the Oracle Container registry, which is the Oracle-certified method of deploying the GoldenGate hub in the target Multicloud service. See [Oracle GoldenGate for Multicloud Database Migrations 26ai \(23.26.1.0.0\) Container Image Documentation](#) for more details.

The “Oracle GoldenGate for Oracle – Database Migrations” Oracle Cloud Marketplace offering now contains a downloadable docker image for Zero Downtime Migration to use with on-premises Exadata Cloud@Customer systems. You can review the latest marketplace VM at https://cloudmarketplace.oracle.com/marketplace/en_US/listing/96175416, and the documentation for this functionality can be found at [Migrating to Exadata Cloud@Customer Using Oracle Zero Downtime Migration](#).

The source database can be either a pluggable database (PDB) or a non-multitenant database.

Logical online migration involves two steps:

- Instantiation of target database.
Oracle Data Pump extracts data from the source database and loads it into the target database.
- Real-time data replication between source and target databases.
Zero Downtime Migration completes the migration once both databases are synchronized.

Optionally, you can configure the migration job to pause after replication is set up, and Oracle GoldenGate can continue to replicate data between the source and target databases in real-time until you choose to switch applications over to the target database.

1.3.2 Logical Offline Migration

Zero Downtime Migration can perform an offline logical migration using Oracle Data Pump to extract the data from the source database and load it into a target database.

Offline logical migration means that the source database is not available for clients while data is moved to the target database. When using the offline migration method, you must stop updates to the source database before you start a migration. When the migration is complete, the target database and source database do not require any direct SQL*Net connectivity between them.

1.3.3 Supported Logical Migration Targets

Zero Downtime Migration supports logical database migration to the following target databases.

- Oracle Autonomous Database on Shared Exadata Infrastructure (Data Warehouse or Transaction Processing)
- Oracle Autonomous AI Database on Dedicated Exadata Infrastructure (Data Warehouse or Transaction Processing)
- Oracle Autonomous AI Database on Exadata Cloud@Customer
- Oracle Co-managed Database Systems:

- Oracle Base Database Service (Virtual Machine, Bare Metal)
- Oracle Exadata Database Service on Dedicated Infrastructure
- Oracle Exadata Database Service on Cloud@Customer
- On premises Exadata Database Machine
- Autonomous AI Database on Dedicated Infrastructure and Autonomous AI Database on Cloud@Customer with fractional OCPU allocation, where a fraction of OCPU is allocated per database service, instead of integer OCPU.

You can specify any predefined fractional service alias available; however, for Autonomous Transaction Processing workloads TP* services are preferred over LOW* services because LOW* is meant for low priority batch jobs.

- TP_TLS, TP, LOW_TLS or LOW (for Autonomous Transaction Processing workloads)
- LOW_TLS or LOW (for Autonomous Data Warehouse workloads)

1.3.4 Initial Load Methods Supported for Logical Migrations

Some Zero Downtime Migration logical migration work flows involve placing Oracle Data Pump dump files on storage media for transfer to the target database. Some migration work flows transfer the initial load without using intermediate storage.

Oracle Cloud Object Store

Object Storage is supported as a Data Pump dump file storage medium for logical migrations to all target Autonomous Database or co-managed databases.

To use Object Storage with OCI CLI on co-managed targets, see [Command Line Interface \(CLI\)](#).

Database Link

Autonomous Database Shared Infrastructure and Dedicated Infrastructure (Data Warehouse or Transaction Processing) and co-managed database targets support the use of a database link for data transport.

① Note

Migrating your database using database link for database sized more than few gigabytes (GB) is not recommended.

Network File System (NFS)

For migrations to co-managed target databases, NFS is supported as a data transfer medium. Oracle ACFS 21c NAS - MAX is fully supported for both physical migration scenarios where NFS is selected as the transfer medium of choice. See [Migrating to Co-Managed Database Server with NFS Data Transfer Medium and DUMPTRANSFERDETAILS_PUBLICREAD](#) for more information.

Direct Copy

For migrations to co-managed target databases, Data Pump dumps can be securely transferred directly from the source database to the target using secure copy (SCP) or RSYNC.

Amazon Simple Storage Service (Amazon S3) Bucket

An Amazon S3 bucket is supported as a Data Pump dump file storage medium for migrations of Oracle Database instances from Amazon Web Services RDS Oracle Database.

1.3.5 What Is Migrated During Initial Load

The initial load phases of a migration job moves the contents of all schemas from the source database to schemas of the same name in the target database. You can elect to exclude specific objects and rename objects when you create a migration.

There are some limitations on objects, schemas, roles, and users that can be migrated, because they cannot be exported by Data Pump, such as system-generated schemas that contain Oracle-managed data and metadata.

Objects Excluded by Default in Oracle 12c and Later Releases

By default, objects owned by Oracle-maintained users (`ORACLE_MAINTAINED = Y`), and the `ggadmin` and `c##ggadmin` users, are excluded from migration. In addition, Data Pump ignores schemas listed in the `KU_NOEXP_VIEW` in addition to Oracle-maintained users.

Oracle Database includes the column `ORACLE_MAINTAINED` in several dictionary views to indicate which objects, schemas, roles, and users are maintained by Oracle. You can query these views to discover object types which are Oracle-maintained, and therefore excluded from migration. See *Oracle Database Reference* at <https://docs.oracle.com/en/database/oracle/oracle-database/21/refrn/database-reference.pdf> to find views that contain `ORACLE_MAINTAINED`.

Objects Excluded by Default in Oracle 11gR2

Zero Downtime Migration excludes schemas listed in the `KU_NOEXP_VIEW` view, and the following Oracle-maintained schemas from Oracle 11gR2 migrations.

"ORACLE_OCM","OJVMSYS","XS\$NULL","GSMCATUSER","MDDATA","DIP",
"APEX_PUBLIC_USER","SPATIAL_CSW_ADMIN_USR", "OWBSYS",
"SPATIAL_WFS_ADMIN_USR","GSMUSER","AUDSYS","FLOWS_FILES",
"MDSYS","ORDSYS","WMSYS","EXFSYS","APEX_040200","APPQOSSYS",
"GSMADMIN_INTERNAL","ORDDATA","CTXSYS","ANONYMOUS","XDB",
"ORDPLUGINS","SI_INFORMTN_SCHEMA","OLAPSYS","DBSNMP","SYSKM",
"SYSBACKUP","OUTLN","SYSDG","SYS","SYSTEM","APEX_030200", "GGADMIN",
"LBACSYS", "MGMT_VIEW", "OWBSYS_AUDIT", "DVSYS", "TSMSYS", "MGDSYS"

1.3.6 Data Replication

Replication migrates all data and metadata operations in transactions committed after the initial load until you resume the migration job after the Monitor Replication Lag phase.

During the migration job it is recommended that your database avoid Data Definition Language (DDL) operations to provide the most optimal environment for fast database replication. When DDL is replicated, Oracle GoldenGate Replicat serializes data to ensure that there are no locking issues between DML and DDL on the same objects.

The `DBOPTIONS DEFERREFCONST` option is set by default for Oracle GoldenGate Replicat Non-integrated Parallel Replicat mode of replication. `DEFERREFCONST` allows to migrate constraints and not disable the constraints on the target tables or setting them to `DEFERRED`. When used, `DEFERREFCONST` defers both `DEFERABLE` and `NOT DEFERABLE` constraints. `DEFERREFCONST` applies to every transaction that is processed by Replicat.

By default, Zero Downtime Migration excludes all DDL from GoldenGate replication. However, Zero Downtime Migration lets you override this behavior with a configuration parameter.

The following objects are not supported:

- Changes to external tables
- Oracle GoldenGate Unsupported Types (see [Understanding What's Supported](#))

1.4 Hybrid Migrations with Zero Downtime Migration

Hybrid migrations is a new migration method alongside physical and logical migration. Currently, `XTTS_OFFLINE` with data transfer medium as NFS is supported. This hybrid implementation combines RMAN for incremental backup and restore of tablespaces and Datapump for migration of metadata. Therefore, this migration combines elements of both physical and logical migration.

1.5 Zero Downtime Migration Requirements and Considerations

1.5.1 Supported Platforms

Zero Downtime Migration supports the following platforms for the service host and the migration source and target database servers.

Starting with the Oracle Zero Downtime Migration 26 (26.1) release, you can also leverage the Instant Deploy feature and have ZDM deployed directly at your source or target database server.

Zero Downtime Migration Service Host - Supported Platforms

The Zero Downtime Migration service host can be configured on Oracle Linux 7 (Linux-x86-64), Oracle Linux 8 (64-bit) on x86-64, Red Hat Enterprise Linux 8 (64-bit) on x86-64, and Red Hat Enterprise Linux 9 (64-bit) on x86-64, Oracle Linux 9.

You can deploy the Zero Downtime Migration service on a standalone server on-premises or on a standalone Linux server (compute instance) in the Oracle Cloud.

Note that the Zero Downtime Migration service host can be shared with other applications for other purposes.

Supported Source Environments

- Oracle Cloud Infrastructure co-managed databases or on-premises environments
- Amazon Web Services RDS Oracle Database
- Linux-x86-64 (all migration modes)
- IBM AIX (using logical migration)
- Oracle Solaris on SPARC (64-Bit) (using logical migration)
- Windows (using logical migration)

Note

Support for Windows is through no-SSH method of access.

Supported Target Environments

- Oracle Cloud Infrastructure co-managed databases: Oracle Exadata Database Service on Dedicated Infrastructure, Oracle Exadata Database Service on Cloud@Customer, Oracle Base Database Service (Virtual Machine and Bare Metal).

The target co-managed database can be either a pluggable database or a non-multitenant database.

- Linux-x86-64 is the supported operating system for target database servers.
- As a target environment only, Autonomous Database is supported platform for logical migrations. You can choose a Dedicated Infrastructure (Data Warehouse or Transaction Processing) or Shared (Data Warehouse or Transaction Processing).

An Autonomous Database is a pluggable database in an Autonomous Container Database (ACD) deployed on an Autonomous Exadata Infrastructure (AEI) rack.

You can also migrate to Oracle Autonomous AI Database on Dedicated Exadata Infrastructure and Oracle Autonomous AI Database on Exadata Cloud@Customer with **fractional OCPU allocation**, where a fraction of OCPU is allocated per database service, instead of integer OCPU.

You can specify any predefined fractional service alias available; however, for Autonomous Transaction Processing workloads TP* services are preferred over LOW* services because LOW* is meant for low priority batch jobs.

- TP_TLS, TP, LOW_TLS, or LOW (for Autonomous Transaction Processing workloads)
- LOW_TLS or LOW (for Autonomous Data Warehouse workloads)

- On-premises Oracle Exadata Database Machine
- Migrating using logical migration methods to Oracle Exadata Database Machine or Oracle Database Appliance is supported.

1.5.2 Supported Database Versions for Migration

Zero Downtime Migration supports most Oracle Database versions available on Oracle Cloud Infrastructure, Oracle Exadata Database Service on Cloud@Customer, and Oracle Exadata Database Service on Dedicated Infrastructure.

The following Oracle Database versions can be migrated using Zero Downtime Migration.

- Oracle Database 11g Release 2 (11.2.0.4)
- Oracle Database 12c Release 1 (12.1.0.2)
- Oracle Database 12c Release 2 (12.2.0.1)
- Oracle Database 18c
- Oracle Database 19c
- Oracle Database 21c
- Oracle AI Database 26ai
- All subsequent Oracle Database releases

Note

If you have a source database version below Oracle Database 19c and you want to perform an online migration to Oracle AI Database 26ai, then you need to perform a two-step migration:

1. Migrate to perform Oracle Database 11g Release 2 (11.2.0.4) and higher version to Oracle Database 19c
2. Migrate to Oracle Database 19c and higher version to Oracle AI Database 26ai.

Some restrictions apply to physical migration work flows. See *Preparing the Source and Target Databases*.

1.5.3 Zero Downtime Migration Database Server Access

The Zero Downtime Migration service host needs to access the source and target database servers during a database migration.

To perform the migration, the Zero Downtime Migration service host requires either root user or SSH key-based access to one of the source database servers, and the Zero Downtime Migration service host requires SSH key-based access to one of the target database servers. If you are migrating an Oracle RAC database, providing access to one of the Oracle RAC nodes is adequate. The Zero Downtime Migration service host copies the software needed for migration to the source and target servers and cleans it up at the end of the operation.

An SSH private key is required to establish SSH connections. This generated key must not use a passphrase. You can create and add a new SSH key to your existing deployment using the Oracle Cloud Service Console.

1.5.4 Zero Downtime Migration Operational Phases

The Zero Downtime Migration service defines the migration process in units of operational phases.

Zero Downtime Migration auto computes the migration work flow using defined operational phases based on configured input parameters, such as the target platform, backup medium, and so on. You can customize the work flow by inserting custom plug-ins on each of the operational phases. The Zero Downtime Migration service lets you pause and resume the migration work flow at any chosen operational phase.

Migration work flow-associated phases for a given operation can be listed. Phases that are performed on the source database server are listed with a `_SRC` suffix, and the phases associated with the target database server are listed with a `_TGT` suffix.

See Also

[Zero Downtime Migration Process Phases](#)

1.5.5 Zero Downtime Migration Security Provisions

Zero Downtime Migration permissions and ownership of files and directories, and handling of configurations for security features, are equivalent to those of Oracle Database.

Zero Downtime Migration installs in a location, named `ZDM_HOME`, that is structured similarly to the Oracle home directory, `ORACLE_HOME`, for Oracle Database. The permissions and ownership of files and directories in the `ZDM_HOME` follow the same conventions as that of a database `ORACLE_HOME`.

Zero Downtime Migration also creates a base directory structure for storing Zero Downtime Migration configuration files, logs, and other artifacts, named `ZDM_BASE`, that is similar to an Oracle base directory, `ORACLE_BASE`, that is associated with an Oracle home. The structure, owners, and permissions of directories and files in `ZDM_BASE` are similar to that of an `ORACLE_BASE`.

`ZDM_BASE` and `ORACLE_BASE` do not allow access by group or others.

You do not need to do any additional steps to ensure security the of the Zero Downtime Migration configuration because the Zero Downtime Migration configuration is designed to be secure out of the box.

Zero Downtime Migration is configured to accept JMX connections only from the local host, and to listen on the loopback address for HTTP connections. Zero Downtime Migration operations can only be performed by the operating system user that installed the product.

For physical migrations, SSH connectivity from the Zero Downtime Migration service host to the source database server and the target database server is required. You must provide the SSH key file location as an input for a migration job, and the existence of this file is expected for the duration of the migration job. You must manage the security of the directories and files where these key files are located.

You can modify the communication ports when there is a port conflict with another application. Note that access to these ports are configured only from within the Zero Downtime Migration host. You can change the RMI and HTTP port properties in the file `$ZDM_BASE/crsdata/zdm_service_host/rhp/conf/standalone_config.properties`.

The properties are:

- RMI port - `oracle.jwc.rmi.port=8895`
- HTTP port - `oracle.jwc.http.port=8896`

Restart the Zero Downtime Migration service after changing the properties.

When Zero Downtime Migration operations require passwords, prompts are given for password entry by default. Zero Downtime Migration can also operate non-interactively by entering wallet information in the migration response file settings.

Passwords are encrypted and stored in the Zero Downtime Migration database. Provided passwords are not expected to change for the duration of a migration job.

From an operation perspective, Zero Downtime Migration follows the guidelines in *Oracle AI Database Security Guide* for handling source and target database configurations for migration, such as Oracle Wallets, Transparent Data Encryption, and so on.

2

Setting Up Zero Downtime Migration Software

When you install Zero Downtime Migration software, read this section carefully as there may have been changes since the last time you performed an installation.

The Zero Downtime Migration software kit supports both physical and logical migrations. You only need to install one kit to get all of the functionality.

Always see the Zero Downtime Migration Release Notes for the latest information about known issues. Also, see the README file included with the downloaded Zero Downtime Migration software for any additional information about software installation and updates.

If you already have Zero Downtime Migration software installed on a host, you should always make sure it is the latest available release. Zero Downtime Migration software updates give you the latest features and fixes while retaining existing job information, metadata, and log files. Always check the version and determine if it is the latest by comparing it with what's available on the downloads page.

For information about updating existing software to the latest release, removing the software, and starting and stopping the Zero Downtime Migration service, see [Managing the Zero Downtime Migration Service](#).

2.1 Prepare a Host for Zero Downtime Migration Software Installation

If a host has not had Zero Downtime Migration software installed on it previously, verify that it complies with the requirements and perform any pre-installation tasks, then download and install the software. Once the software is installed, the host is referred to as the Zero Downtime Migration service host.

Provision a host with the following prerequisites and complete the following pre-installation tasks before installing Zero Downtime Migration software on it.

- The Zero Downtime Migration service host should be a dedicated system, but it can be shared for other purposes.

However, if the Zero Downtime Migration service is installed on the same host where RHP server is deployed, see [Running RHP and Zero Downtime Migration Service on the Same Host](#) for more info.

- Zero Downtime Migration software requires a standalone Linux host running on any one of the following platforms:

Oracle Linux 7, Oracle Linux 8, Oracle Linux 9, or Red Hat Enterprise Linux 8.

- The Zero Downtime Migration service host must be able to connect to the source and the target database servers.
- Ensure that the Linux host has 100 GB of free storage space.
- You may use an existing user, or, on the Zero Downtime Migration service host, as root user, create a `zdm` group and add `zdmuser` user to the group.

For example,

```
root> groupadd zdm
root> useradd -g zdm zdmuser
```

- Verify that the `glibc-devel` and `expect` packages are installed.

For Oracle Linux 8 installations with Base Environment "Minimal Install" you also need to install the packages `unzip` `libaio` `oraclelinux-developer-release-el7` `libnsl` and `ncurses-compat-libs`.

- Minimum OS version Oracle Linux 7
- Ensure Packages 'glibc-devel' and 'expect' are installed
- For higher versions such as Oracle Linux 8:
- Ensure Packages 'libnsl' and 'ncurses-compat-libs' are also installed
- `glibc-devel` and `expect` are a must for either versions
- `unzip` `libaio` `oraclelinux-developer-release-el7` `libnsl` and `ncurses-compat-libs` are required for Oracle Linux 8

- Verify that the `/etc/hosts` entry for the host name and IP address are configured as expected, so that the host selected for Zero Downtime Migration software installation resolves to the correct IP address and the IP address is reachable with `ping`.

Note

Using aliases is not supported.

- During the installation, the script might report any missing packages and instructions for setting appropriate values for kernel parameters. Be sure to install the missing packages and set the kernel parameters before the Zero Downtime Migration software installation.
- Optionally, set a `ZDM_HOME` environment variable to the absolute path of the directory where the Zero Downtime Migration software will be installed. All of the examples in this document use `$ZDM_HOME`.

```
zdmuser> export ZDM_HOME=absolute_path_to_zdm_home
```

- The release info file includes the ZDM jar dependencies and the included versions, `zdm.release.info` is located in `zdm home:./zdm_home/rhp/zdm.release.info`.

Example:

```
Apr 06 2026 15:07:56 UTC
jlib/derby.jar 10.17.1000000.Unversioned
jlib/jackson-core.jar 2.18.6
jlib/jersey-common.jar 2.43.0
jlib/jipther-jce.jar 10.31
jlib/jipther-pki.jar 10.15
jlib/json-java.jar 20250517.0.0
jlib/org-everit-json-schema.jar N/A
jlib/sshd-common.jar 2.15.0
rhp/zdm/lib/autoupgrade.jar 26.2.260217
rhp/zdm/lib/cpat/lib/premigration.jar 26.2.0
rhp/zdm/lib/opc_install.jar RDBMS_MAIN_LINUX.X64_170816
micronaut/jlib/micronaut-core.jar 3.8.13-1
jlib/oci-java-sdk-full.jar 2.82.0
```

- In secured environments where access to internet is restricted from the ZDM server, you may have to allow the OCI endpoints in your network firewall. These end points are used by ZDM for API calls to the Oracle Cloud for Autonomous targets. Allow the region-specific endpoints for the following services:
 - [Core services](#)
 - [IAM](#)
 - [Database](#)
 - [Object Storage](#)

2.2 Install Zero Downtime Migration Software

All commands are run as `zdmuser`.

1. Download the Zero Downtime Migration software kit from <https://www.oracle.com/database/technologies/rac/zdm-downloads.html> to the Zero Downtime Migration service host.

Note

Review for new patches if required, by reviewing the Patch 33509650: ZDM PATCH USING MOS.

2. Create home and base directories.

The home directory is where the Zero Downtime Migration software will be installed.

The base directory is where all of the Zero Downtime Migration configuration files, logs, and other artifacts are stored.

For example:

```
/u01/app/zdmhome
```

```
/u01/app/zdmbase
```

3. Install the Zero Downtime Migration software as a non-root user.

In this example the installation user is `zdmuser`.

- a. Change to the directory to where Zero Downtime Migration software is downloaded and unzip the software.

```
zdmuser> cd zdm_download_directory
zdmuser> unzip zdmversion.zip
```

- b. Run the Zero Downtime Migration installation script.

```
zdmuser> ./zdminstall.sh setup oraclehome=zdm_oracle_home
oraclebase=zdm_base_directory
ziploc=zdm_zip_location
```

- `zdminstall.sh` is the installation script
- `oraclehome` is the absolute path to the Oracle Home directory where the Zero Downtime Migration software will be installed

- `oraclebase` is the absolute path to the base directory where all of the Zero Downtime Migration configuration files, logs, and other artifacts are stored
- `ziploc` is the location of the compressed software file (zip) included in the Zero Downtime Migration kit

For example,

```
zdmuser> ./zdminstall.sh setup oraclehome=/u01/app/zdmhome
               oraclebase=/u01/app/zdmbase ziploc=/u01/app/oracle/zdm/shiphome/
               zdm_home.zip
```

Note that the Zero Downtime Migration service host requires PERL to run the install script.

Hereafter, the `oraclehome` value is referred to as `ZDM_HOME`, and the `oraclebase` value is referred to as `ZDM_BASE`.

Note

You can also install two ZDM servers in a single host.

Ignore the following messages which are displayed on the terminal at the end of installation. There is no need to run these scripts.

As a root user, execute the following script(s):

1. `$ZDM_HOME/inventory/orainstRoot.sh`
2. `$ZDM_HOME/root.sh`

4. Start the Zero Downtime Migration service as user `zdmuser`.

```
zdmuser> $ZDM_HOME/bin/zdmservice start
```

You must start `zdmservice` before you can migrate your databases using Zero Downtime Migration.

If you must stop the Zero Downtime Migration service, run the following command.

```
zdmuser> $ZDM_HOME/bin/zdmservice stop
```

5. Verify that the Zero Downtime Migration service installation is successful.

When you run the following command, the output should be similar to that shown here.

```
zdmuser> $ZDM_HOME/bin/zdmservice status
-----
                Service Status
-----
Running: true
Transferport:
Conn String: jdbc:derby:/home/opc/zdm/zdmbase/derbyRepo;create=true
Repo Path: /home/opc/zdm/zdmbase/derbyRepo
RMI port: 8897
HTTP port: 8898
```

```
SSH port: 22
Wallet path: /home/opc/zdm/zdmbase/crsdata/zdmnode/security
```

6. If necessary, change the default MySQL port.

Zero Downtime Migration uses MySQL internally, configuring it by default on port 8897, as shown in the above `zdm service status` example output.

2.2.1 Customizing Port Numbers

You can customize the port numbers by performing the following steps:

1. Run the following command:

```
/scratch/zdmuser/zdmtest/home/bin/zdm service modify mysqlPort=8799
```

2. Edit the MySQL port as follows:

```
Set port=8799 in my.cnf
Set \ljdbc:mysql:\/\localhost:8799\ in rhp.pref
Set \18799 in rhp.pref
```

```
/scratch/zdmuser/zdmtest/home/bin/zdm service modify rmiPort=8797
```

3. Edit the RMI port as shown:

```
Set oracle.jwc.rmi.port=8797 in
    standalone_config.properties
/scratch/zdmuser/zdmtest/home/bin/zdm service modify httpPort=8798
```

4. Edit the HTTP port as shown:

```
Set oracle.jwc.http.port=8798 in standalone_config.properties
Where:
/scratch/zdmuser/zdmtest/home is the ZDMHOME
```

5. Edit the SSH port:

```
Set SSH_PORT=2222 in rhp.pref
or
/scratch/zdmuser/zdmtest/home/bin/zdm service modify ssh_port=2222
```

2.3 Installing Zero Downtime Migration on VM in Oracle Cloud Infrastructure

You can install ZDM on Oracle Linux 8 VM in OCI by performing the following steps:

To install Zero Downtime Migration on Oracle Linux 8 VM in OCI

1. Create your VM instance in OCI and download the private and public keys.
2. Connect to your VM instance through SSH by using your downloaded private key.
3. Download the ZDM image from [Oracle Zero Downtime Migration](#).

4. Install the following software for ZDM:

- expect
- glibc-devel
- ncurses-compat-libs
- libnsl

5. Run the following command:

```
sudo yum install oraclelinux-developer-release-el8 libnsl perl unzip glibc-
devel expect libaio ncurses-compat-libs ncurses-devel numactl-libs openssl
mlocate bind-utils
```

6. Create a directory to store the ZDM home and base.

For example, `mkdir /home/opc/zdm`

7. Unzip the ZDM image.

For example, `[opc@zdminstance20230201 zdm]$ unzip ZDMKIT.zip`

8. Run the ZDM installer:

```
[opc@zdminstance20230201 zdm]$ /home/opc/zdm/zdmkit/zdminstall.sh setup
oraclehome=/home/opc/zdm/home oraclebase=/home/opc/zdm/base ziploc=/
home/opc/zdm/zdmkit/zdm_home.zip
```

9. Start the ZDM service:

```
[opc@zdminstance20230201 zdm]$ home/bin/zdmservice start
```

10. Verify the installed version.

Example:

```
zdmcli -build
full version: "26.1.0"
patch version: ""
label date: 260401
ZDM kit build date: Apr 01 2026 23:53:20 UTC
CPAT build version: 26.2.0
```

11. When ZDM is configured on a compute VM provisioned in OCI, you may need to update `/etc/hosts` to resolve the source and/or target database systems. If the ZDM compute VM is rebooted for some reason, the custom entries in `/etc/hosts` are not saved. To save these custom entries, edit `/etc/oci-hostname.conf` as follows:

```
# This configuration file controls the hostname persistence behavior for
Oracle Linux

# compute instance on Oracle Cloud Infrastructure (formerly Baremetal
Cloud Services)

# Set PRESERVE_HOSTINFO to one of the following values

# 0 -- default behavior to update hostname, /etc/hosts and /etc/
resolv.conf to

# reflect the hostname set during instance creation from the
```



```

metadata service

# 1 -- preserve user configured hostname across reboots; update /etc/
hosts and

#           /etc/resolv.conf from the metadata service

# 2 -- preserve user configured hostname across instance reboots; no
custom

#           changes to /etc/hosts and /etc/resolv.conf from the metadata
service,

#           but dhclient will still overwrite /etc/resolv.conf

# 3 -- preserve hostname and /etc/hosts entries across instance reboots;

#           update /etc/resolv.conf from instance metadata service

PRESERVE_HOSTINFO=2      ==> Set this to at least 2.

```

Entries in `/etc/hosts` will now be saved across instance reboots for ZDM running on a provisioned compute instance or VM in OCI.

2.4 Installing Zero Downtime Migration on Red Hat Enterprise Linux 8 in an Oracle Cloud Infrastructure Instance

You can install ZDM on a Red Hat Enterprise Linux 8 in an OCI instance by performing the following steps:

To install Zero Downtime Migration on Red Hat Enterprise Linux 8

1. Obtain Red Hat Enterprise Linux 8.8 KVM Guest Image from [here](#).
2. Upload the image to a new OCI bucket.
3. Import the image as custom image.
4. Create an instance from the image.
5. Generate new SSH keys.
6. Connect to the RHEL8 OCI instance.

Perform the following steps:

1. Configure `yum` repositories by running the following command:

```

$ sudo yum install https://dl.fedoraproject.org/pub/epel/epel-release-latest-8.noarch.rpm
$ sudo yum-config-manager --add-repo http://yum.oracle.com/repo/OracleLinux/OL8/
baseos/latest/x86_64
$ sudo rpm --import /etc/pki/rpm-gpg/RPM-GPG-KEY-redhat-release
$ sudo rpm --import /etc/pki/rpm-gpg/RPM-GPG-KEY-EPEL-8
$ sudo rpm --import /etc/pki/rpm-gpg/RPM-GPG-KEY-redhat-beta

```

2. Enable `swap` by running the following commands:

```
$ sudo swapon --show
$ sudo fallocate -l 1G /swapfile
$ sudo chmod 600 /swapfile
$ sudo mkswap /swapfile
$ sudo swapon /swapfile
$ sudo swapon --show
```

3. Install the required Red Hat Enterprise Linux 8 packages as follows:

```
$ sudo yum install zip.x86_64 --nogpgcheck
$ sudo yum install expect.x86_64 --nogpgcheck
$ sudo yum install glibc-devel.x86_64 --allowdowngrading --nogpgcheck
$ sudo yum install libnsl.x86_64 --allowdowngrading --nogpgcheck
$ sudo yum install ncurses-compat-libs.x86_64 --allowdowngrading --nogpgcheck
$ sudo yum install libaio.x86_64 --allowdowngrading --nogpgcheck
```

4. Install Zero Downtime Migration.

2.5 Installing Zero Downtime Migration on Red Hat Enterprise Linux 9 in an Oracle Cloud Infrastructure Instance

You can install ZDM on a Red Hat Enterprise Linux 9 in an OCI instance by performing the following steps:

To install Zero Downtime Migration on Red Hat Enterprise Linux 9

1. Obtain Red Hat Enterprise Linux 9 KVM Guest Image from [here](#).
2. Upload the image to a OCI bucket.
3. Create a custom image using the downloaded `qcow2` file.
4. Create an IaaS instance from the new custom image.
5. Generate and download new SSH Keys. You can also use any existing SSH keys.
6. Connect to the instance by using SSH keys or `cloud-user`.

Perform the following steps:

1. Configure `yum` repositories by running the following command:

```
[root@rhel9zdm yum.repos.d]# yum install https://dl.fedoraproject.org/pub/
epel/epel-release-latest-9.noarch.rpm -y
[root@rhel9zdm yum.repos.d]# pwd
/etc/yum.repos.d

[root@rhel9zdm yum.repos.d]# ls -l
total 160
-rw-r--r--. 1 root root 1142 Aug 17 2023 epel-cisco-openh264.repo
-rw-r--r--. 1 root root 1552 Aug 17 2023 epel-testing.repo
-rw-r--r--. 1 root root 1453 Aug 17 2023 epel.repo
-rw-r--r--. 1 root root 3883 Apr 9 16:48 ol9.repo
-rw-r--r--. 1 root root 145427 Apr 9 16:38 redhat.repo
```

```
[root@rhel9zdm yum.repos.d]# cat epel.repo
[epel]
name=Extra Packages for Enterprise Linux $releasever - $basearch
# It is much more secure to use the metalink, but if you wish to use a
local mirror
# place its address here.
#baseurl=https://download.example/pub/epel/$releasever/
Everything/$basearch/
metalink=https://mirrors.fedoraproject.org/metalink?
repo=epel-$releasever&arch=$basearch&infra=$infra&content=$contentdir
enabled=1
gpgcheck=1
countme=1
gpgkey=file:///etc/pki/rpm-gpg/RPM-GPG-KEY-EPEL-$releasever

[epel-debuginfo]
name=Extra Packages for Enterprise Linux $releasever - $basearch - Debug
# It is much more secure to use the metalink, but if you wish to use a
local mirror
# place its address here.
#baseurl=https://download.example/pub/epel/$releasever/
Everything/$basearch/debug/
metalink=https://mirrors.fedoraproject.org/metalink?repo=epel-
debug-$releasever&arch=$basearch&infra=$infra&content=$contentdir
enabled=0
gpgkey=file:///etc/pki/rpm-gpg/RPM-GPG-KEY-EPEL-$releasever
gpgcheck=1

[epel-source]
name=Extra Packages for Enterprise Linux $releasever - $basearch - Source
# It is much more secure to use the metalink, but if you wish to use a
local mirror
# place its address here.
#baseurl=https://download.example/pub/epel/$releasever/Everything/source/
tree/
metalink=https://mirrors.fedoraproject.org/metalink?repo=epel-
source-$releasever&arch=$basearch&infra=$infra&content=$contentdir
enabled=0
gpgkey=file:///etc/pki/rpm-gpg/RPM-GPG-KEY-EPEL-$releasever
gpgcheck=1
[root@rhel9zdm yum.repos.d]#
```

2. Install the required packages as root user and run the following commands :

```
[root@rhel9zdm yum.repos.d]# yum install zip.x86_64 --nogpgcheck
[root@rhel9zdm yum.repos.d]# yum install glibc-devel.x86_64 --allowdowngrading
--nogpgcheck
[root@rhel9zdm yum.repos.d]# yum install libaio.x86_64 --allowdowngrading --
nogpgcheck
[root@rhel9zdm yum.repos.d]# yum install libnsl --allowdowngrading --nogpgcheck
[root@rhel9zdm yum.repos.d]# yum install ncurses-compat-libs.x86_64 --
allowdowngrading --nogpgcheck
[root@rhel9zdm yum.repos.d]# yum install glibc-devel.x86_64 --allowdowngrading
--nogpgcheck
```

```
[root@rhel9zdm yum.repos.d]# yum install expect.x86_64 --nogpgcheck
[root@rhel9zdm yum.repos.d]# yum install wget
```

3. Enable swap by running the following commands:

```
[root@rhel9zdm ~]# swapon --show
[root@rhel9zdm ~]# fallocate -l 1G /swapfile
[root@rhel9zdm ~]# chmod 600 /swapfile
[root@rhel9zdm ~]# mkswap /swapfile
[root@rhel9zdm ~]# swapon /swapfile
[root@rhel9zdm ~]# swapon --show
NAME      TYPE  SIZE USED PRIO
/swapfile file 1024M  0B   -2

[root@rhel9zdm ~]#
```

4. Install Zero Downtime Migration.

3

Configuring Required Connections

Connectivity must be set up between the Zero Downtime Migration service host and the source and target database servers.

Note

The umask setting for host level authenticating user must have umask set to 022. For example, if `zdmuser` is authenticating user for the source or target, then `zdmuser` must have umask set to 022.

3.1 Logical Migration without SSH Access

You can perform logical migration to the target database server host without requiring SSH credentials.

- ZDM performs the logical workflow without SSH access where it handles the upload and download of dumps.
- To have Zero Downtime Migration run Cloud Premigration Advisor Tool (CPAT) validation remotely, set the response file parameter `RUNCPATREMOTELY=TRUE`. See `RUNCPATREMOTELY`.
- ZDM allows CPAT to be started from the ZDM node (referred to above as the ZDM service host) remotely via a JDBC connection to the source or target database.

For migration involving transfer of dumps to OSS, ZDM auto transfers dumps over HTTPS.

To achieve this HTTPS connectivity, you must perform the following steps in the source database host:

- Set up `SSL_WALLET` for HTTPS access see the [Create SSL Wallet with Certificates](#) topic.
- Specify this wallet path to the ZDM job using the `DUMPTRANSFERDETAILS_SOURCE_OCIWALLETLOC` parameter.
- Set up Network ACL: The user performing the export or import requires the necessary network ACL to be granted to access the network from the source and target database host. See [How To Set Network ACLs](#)

Create SSL Wallet with Certificates

To safely access HTTP URLs and Object Stores, a wallet is required with appropriate certificates for the object stores.

Note

Currently Oracle does not ship the certs as part of RUs.

You can download the necessary certificates from the [Create SSL Wallet with Certificates](#) section.

All Object Storage access is done through HTTPS and requires the database to have the certifications of all trusted locations. You need to create a security wallet containing the certificates.

Note

- The wallet has to be created with auto login capabilities.
- On RAC installations, the wallet must either be accessible for all nodes centrally or you have to create the wallet on all nodes for local wallet storage.

The wallet can be stored at any location that is accessible by the user you installed the SW for - typically oracle, but it is recommended to manage the security wallet similar to the tde wallet provided by default for Cloud installation in Oracle OCI: by default, TDE wallets in Oracle Database Cloud installations are stored at `/opt/oracle/dcs/commonstore/wallets/tde/$ORACLE_UNQNAME`. It is recommended to store the SSL wallet in an equivalent location, for example `/opt/oracle/dcs/commonstore/wallets/ssl`. Assuming you are choosing this location and have unpacked the certs in `/home/oracle/dbc`, you have to issue the following commands to create the necessary wallet. If you are already having a wallet for SSL certificates then you do not have to create a new wallet but rather add the required certs to the existing wallet.

```
cd /opt/oracle/dcs/commonstore/wallets/sslorapki
    wallet create -wallet . -pwd <your_chosen_wallet_pw> -auto_login#! /bin/
bashfor i in
    'ls <location of cert files>/*.cer'doorapki wallet add -wallet . -
trusted_cert -cert
    $i -pwd <SSL Wallet password>done
```

You can check the proper addition of the certificates as follows:

```
cd /opt/oracle/dcs/commonstore/wallets/sslorapki wallet display -
wallet .Sample output for a wallet containing only the three certs required
for
    dbms_cloud:[oracle@hb19cee ssl]$ orapki wallet display -
wallet .Oracle PKI
    Tool Release 21.0.0.0.0 - ProductionVersion 21.0.0.0Copyright (c)
2004,
    2020, Oracle and/or its affiliates. All rights reserved.Requested
Certificates:User Certificates:Trusted Certificates:Subject:
    CN=VeriSign Class 3 Public Primary Certification Authority -
G5,OU=(c) 2006 VeriSign\,
    Inc. - For authorized use only,OU=VeriSign Trust
Network,O=VeriSign\,
    Inc.,C=USSubject: CN=Baltimore CyberTrust
Root,OU=CyberTrust,O=Baltimore,C=IESubject: CN=DigiCert Global Root
CA,OU=www.digicert.com,O=DigiCert Inc,C=US
```

For source database servers:

The following parameters indicate the SSL wallet path on source node:

- DUMPTRANSFERDETAILS_SOURCE_NOSSHUPLOADMETHOD
- DUMPTRANSFERDETAILS_SOURCE_OCIWALLETLOC

For target database servers:

The following parameters indicate the SSL wallet path on target node:

- DUMPTRANSFERDETAILS_TARGET_NOSSHUPLOADMETHOD
- DUMPTRANSFERDETAILS_TARGET_OCIWALLETLOC

Related Topics

- DUMPTRANSFERDETAILS_SOURCE_NOSSHUPLOADMETHOD
- DUMPTRANSFERDETAILS_SOURCE_OCIWALLETLOC
- DUMPTRANSFERDETAILS_TARGET_NOSSHUPLOADMETHOD
- DUMPTRANSFERDETAILS_TARGET_OCIWALLETLOC

3.2 Physical and Logical Migration with SSH Access

You can perform physical and logical migration and migrate a database from source to target with SSH access with database user and `sudo` privileged user.

Related Topics

- Setting Up SSH Key Based Authentication
- Generate SSH Keys Without a Passphrase

3.2.1 Migrating with Database User Privileges

You can migrate database from source to target with all actions performed on the source and target database node as `oracle` user. You do not require a privileged user access to perform any action.

Using `dbuser` authentication plug-in:

You can specify the authentication user and identity file for the specified user to connect to source database server and perform migration.

Note

To perform the logical migration using database user plug-in as `dbuser`, you must set value of the `RUNCPATREMOTELY` parameter to `TRUE`.

You require the following arguments:

- `user: Oracle db user-` Specifies the Oracle Database user name that is allowed to perform the migration action. For example, `user:oracle` is capable of performing any Grid Infrastructure (GI) actions required as part of the physical migration workflow.
- `identity_file: Oracle db user SSH private key file-` Specifies the private key file for the specified Oracle Database user name that allows SSH connection for the specified source or target node. For example, `identity_file:/home/zdmnode/keys/source_ssh_private_key.file`.

1. Choose the authentication plug-in `-srcauth` or `-tgtauth` as `dbuser` and specify the authentication user.
2. Identity the file for the specified user to connect to source or target database server respectively and perform migration.
3. Use the following arguments in `migrate` command to support `dbuser` authentication plug-in:

- Source node access: Specify following parameters in ZDMCLI `migrate` command:

```
-srcauth dbuser
  -srcarg1 user:username
  -srcarg2 identity_file:Oracle user private_ssh_key.file
```

- Target node access: Specify following parameters in ZDMCLI `migrate` command:

```
-tgtauth dbuser
  -tgtarg1 user:target_database_server_login_user_name
  -tgtarg2 identity_file:Oracle user private_ssh_key.file
```

Using `dbuser` plug-in for performing logical migration

ZDM supports non-privileged users for both source and target node access.

You must allow `dbuser` specified for authentication to perform all action required for migration in the source and target database server hosts.

Using `dbuser` plug-in for performing physical migration

Restrictions for physical migration: Physical migration is supported for accessing the source database server and conditionally for accessing the target node, detailed as follows:

- You must allow `dbuser` specified for authentication to perform all actions required for migration in the source database server host.
- For OCI target database servers- `dbuser` authentication plug-in is not supported and always requires a privileged user. You must use `zdmauth`.
- For non-cloud target database server, to use `dbuser` for target database in physical migration, the target database must be non-role separated where Oracle Grid Infrastructure (GI) and Oracle Database (DB) must be owned by the same user.
- For source database servers, ensure that either of the following cases are applicable if Grid Infrastructure user and Database user have no role separation. The following actions are not required if `dbuser` and `grid` user are same and if Oracle Database password or TDE wallet is not in ASM:
 - If Grid Infrastructure and Database are role separated and if the Oracle Database password or TDE wallet is on ASM, then copy the password or TDE wallet from ASM to a secure local file system path for `dbuser` access.
 - Ensure that the copied wallet has protected and restricted access only for `dbuser` and the wallet is removed after the completion of migration action.
 - If you copy a TDE wallet or Oracle Database from ASM to local file system, then specify the path in the `SRC_DB_PASSWORDFILE_LOCSRC_DB_PASSWORDFILE_LOC` and `SRC_DB_TDE_WALLET_LOCSRC_DB_TDE_WALLET_LOC` parameters respectively.

Sample migrate command:

```
$ZDM_HOME/bin/zdmcli migrate database -rsp file_name -sourcesid  
source_oracle_sid  
-sourcenode source_database_server_name  
-srcauth dbuser  
-srcarg1 user:username  
-srcarg2 identity_file:ssh_key_path  
-targetnode target_database_server_name  
-tgtauth dbuser  
-tgtarg1 user:target_database_server_login_user_name  
-tgtarg2 identity_file:ZDM_installed_user_private_key_file_location
```

3.2.2 Migrating with SUDO User Privilege

You may need to grant certain users authority to perform operations using `sudo` on the source and target database servers.

You can migrate the database from source to target with all actions on the source and target database node as `sudo user` without the `SUPERUSER` privilege elevation. The indicated user in the authentication argument `user:<auth_user>` is used to connect to the database host over SSH. None of the actions performed expects `SU` (super user) access or direct SSH via database user.

Note

This is an optional method and can be used as an alternative to the [Setting Up SSH Key Based Authentication](#) method which is applicable for role-separated cases.

These steps are applicable for physical migrations and logical migrations where either the source and/or target are accessed using SSH keys (co-managed databases). These steps are **not applicable** for logical migration where the target is Autonomous Database.

Note

The new authentication plugin `sudoasuser` is available only for logical migration. It caters to your environments with SSH access to Database user being locked as well as when the Sudo user is not granted privilege to become Super User.

For source database servers:

- If the source database server is accessed with the `root` user, then there is no need to configure `sudo` privileges.
- If the source database server is accessed through non-`root`, non-database user, then configure `sudo` privilege for the user to perform migration action as database user without prompting for a password.

For target database servers:

- When the target database server is on the cloud, any `sudo` privileges are already configured. Otherwise, configure all `sudo` privileges to run without prompting for a password for the database installed user and the `root` user.
If the target database server is accessed through non-root, non-database user, then configure `sudo` privilege for the user to perform migration action as database user without prompting for a password.

Using `sudoasuser` authentication plugin for logical migration

You can migrate the database from source to target with all actions on the source and target database node as `sudo` user without the `SUPERUSER` privilege elevation. The indicated user in the authentication argument `user:<auth_user>` is used to connect to the database host over SSH. None of the actions performed expects `SU` (super user) access or direct SSH via database user.

Authplugin : '`sudoasuser`'

The plugin offers arguments for you to specify the authentication user, `asuser` and identity file for the specified user to connect to source database server and perform migrate action using `sudo` to become database user.

Following are the arguments required

`user:<auth_user>`

Argument specifies the auth user name with which the connection is made to the remote source node.

'`asuser`:' <Sudo user>

Argument specifies the sudo user name that is allowed to perform the migration action with performing `sudo` to Oracle Database user. For example, `user:zdmuser` can do `sudo oracle` (and become Grid User for Physical migration.) For physical migration, the specified user should be capable of performing any Grid Infrastructure (GI) actions required as part of the migration workflow with `sudo` as GI user.

'identity_file:' <Sudo user SSH private key file>

Argument specifies the private key file for the specified auth user name that will allow SSH connection for the specified source node. For example, `identity_file:/home/zdmnode/keys/source_ssh_private_key.file`.

Following is the sample migrate command:

```
zdmcli migrate database
-sourcedb db_name
-sourcenode source_host_name
-srcauth sudoasuser
-srcarg1 user:source_database_server_login_user_name
-srcarg2 asuser:source_database_server_login_user_name
-srcarg3 identity_file:ZDM_installed_user_private_key_file_location
-srcarg4 sudo_location:/usr/bin/sudo
-targetnode target_host_name
-backupuser Object_store_login_user_name
-rsp response_file_location
-tgtauth zdmauth
-tgtarg1 user:target_database_server_login_user_name
-tgtarg2 identity_file:ZDM_installed_user_private_key_file_location
-tgtarg3 sudo_location:/usr/bin/sudo -tdekeystorepasswd -tgttdekeystorepasswd
```

certs

Note

Use `-srcauth zdmauth` for user with sudo access and `-tgtauth dbuser` for non-sudo user or vice versa.

```
$ZDM_HOME/bin/zdmcli migrate database
-sourcedb source_db_unique_name_value
-rsp response_file_location
-sourcenode <nodename e.g., dbserver or IP
address>
-srcauth zdmauth
-srcarg1 user:username
-srcarg2 identity_file:<user key path on
zdm host e.g. /keys/id.rsa>
-srcarg3 sudo_location:/usr/bin/sudo
-targetnode target_database_server_name
-tgtauth dbuser
-tgtarg1 user:target_database_server_login_user_name
-tgtarg2 identity_file:ZDM_installed_user_private_key_file_location
```

3.3 Zero Downtime Migration Port Requirements

The ports required for communication between the Zero Downtime Migration service host, the source and target database servers, and Oracle Cloud Object Store Service are described in the following table.

Table 3-1 Zero Downtime Migration Communication Ports

Initiator	Target	Protocol	Port	Purpose	Description
Zero Downtime Migration service host	Source and target database servers	TCP	22	SSH	Authentication-based operations to run Zero Downtime Migration operational phases. Source and target database servers should accept incoming connections from the Zero Downtime Migration service host. Not applicable to Autonomous Database targets.

Table 3-1 (Cont.) Zero Downtime Migration Communication Ports

Initiator	Target	Protocol	Port	Purpose	Description
Zero Downtime Migration service host	Source and target database servers	TCP	1521, 2484, or a database SCAN Listener port	SQL*Net	For logical migrations This also allows the connectivity to GoldenGate for the source database.
Zero Downtime Migration service host or GoldenGate Hub	Target ADB	TCPS	1522, or a database SCAN Listener secure port in case of TCPS enabled on source or target	SQL*Net	ADB-S uses port 1522 so you should allow incoming connections on the ADB tenancy from GoldenGate or ZDM, or from the target if the source listens on 1522, and transfer medium is DBLINK over TCPS
Zero Downtime Migration service host	Oracle Cloud Interface REST endpoint	SSL	443	OCI REST endpoint	Target discovery for logical migrations. This also allows connections for ZDM to GoldenGate. Note: Ensure that you consider all the necessary proxy details and provide the details in the ZDM response file.

Table 3-1 (Cont.) Zero Downtime Migration Communication Ports

Initiator	Target	Protocol	Port	Purpose	Description
Source database servers	Target database servers	TCP	1521 or database SCAN Listener port applicable for the job	SQL*Net	<p>Should allow Oracle client connections to the database over Oracle's SQL*Net protocol. Perform database queries, Data Guard sync, and configuration.</p> <p>Note: If you are using a non-default port number (that is, something other than port 1521) for the local listener address, then connections should be allowed to the non-default port.</p>

Table 3-1 (Cont.) Zero Downtime Migration Communication Ports

Initiator	Target	Protocol	Port	Purpose	Description
Target database servers	Source database servers	TCP	1521 or a database SCAN Listener port applicable	SQL*Net	<p>Should allow Oracle client connections to the database over Oracle's SQL*Net protocol</p> <p>Allows redo log shipping if source database needs to be in sync with the new primary on Oracle Cloud after switchover. If there is no communication possible from Oracle Cloud to source database server then set SKIP_FALLBACK to TRUE in the response file to avoid this communication.</p> <p>Note: If you are using a non-default port number (that is, something other than port 1521) for the local listener address, then connections should be allowed to the non-default port.</p>

Table 3-1 (Cont.) Zero Downtime Migration Communication Ports

Initiator	Target	Protocol	Port	Purpose	Description
Source database servers	Oracle Cloud Object Store Service	SSL	443	Database backup store.	If the chosen backup method uses Oracle Cloud Object Store Service as the backup medium, then access ports as documented Oracle Cloud Object Store Service applies. Note: Ensure that you consider all the necessary proxy details and provide the details in the ZDM response file.
Target database servers	Oracle Cloud Object Store Service	SSL	443	Database backup store.	If the chosen backup method uses Oracle Cloud Object Store Service as the backup medium, then access ports as documented Oracle Cloud Object Store Service apply. Note: Ensure that you consider all the necessary proxy details and provide the details in the ZDM response file.

Note

If there is no SSH access to the source database, the following action is skipped as part of the Zero Downtime Migration work flow.

- Zero Downtime Migration will not validate whether the source export path is writable for the database user.

Note

When performing a migration with root credentials (`migrate database -scroot`), during the setup phase, Zero Downtime Migration uses six ports chosen from the ephemeral range, or six ports from the range of ports set in `TRANSFERPORT_RANGE` in `zdmbase/crsdata/zdm_service_host/rhp/conf/rhp.pref`. The specified ports must be allowed to accept incoming connections from the Zero Downtime Migration service host on the source or target database server.

3.4 Configuring Database Connectivity for Online Physical Migration

For physical migration, SQL*NET should be available between the source and target database. You have two options for configuring connectivity between the source and target database servers: SQL*Net connectivity using SCAN or SSH. Optionally, you can configure the connectivity between the target and source database.

Note

Configuring connectivity between the source and target database servers is applicable only for online physical migrations.

3.4.1 SQL*Net Connectivity Using SCAN

- To use this option, ensure that the source can connect to the target through the SCAN of the target database and vice versa.
- Connect to the target database instance over target SCAN through the respective SCAN port and vice versa, using the source database server you specify in the `ZDMCLI migrate database` command `-sourcenode` parameter.
- With SCAN connectivity from both sides, the source database and target databases can synchronize from either direction. If the source database server SCAN cannot be resolved from the target database server, then the `SKIP_FALLBACK` parameter in the response file must be set to `TRUE`, and the target database and source database cannot synchronize after switchover.

Test Connectivity

To test connectivity from the source to the target environment, add a TNS Alias entry in `tnsnames.ora` file that maps to a database connect descriptor. See, [Local Naming Parameters in the tnsnames.ora File](#).

```
[oracle@sourcedb ~] tnsping tnsping <TNS_ALIAS>
```

To test connectivity from the target to the source environment, add a TNS Alias entry in `tnsnames.ora` file that maps to a database connect descriptor.

```
[oracle@targetdb ~] tnsping tnsping <TNS_ALIAS>
```


Note

Database migration to Oracle Exadata Database Service on Cloud@Customer using the Zero Data Loss Recovery Appliance requires mandatory SQL*Net connectivity from the target database server to ZDLRA.

See Also

[Zero Downtime Migration Port Requirements](#)

4

Preparing for a Physical Database Migration

Before starting a Zero Downtime Migration physical database migration you must, prepare the source and target databases, set parameters in the response file, and configure any required migration job customization. Configure connectivity between the source to target databases for online physical migration.

Note

The hostname must be different in both source and target, if the hostname is the same, the migration will fail.

See the Zero Downtime Migration Release Notes for the latest information about new features, known issues, and My Oracle Support notes.

4.1 Prerequisites for Online Physical Migration

You must configure connectivity prerequisites for online physical migration. If connectivity using SCAN and the SCAN port is not possible between the source and target database servers, set up an SSH tunnel from the source database server to the target database server.

Related Topics

- Set up an SSH Tunnel

4.2 Preparing the Source and Target Databases

There are several tasks you must complete on the source and target databases before configuring a migration job. The following are prerequisites that apply to both source and target database.

- Zero Downtime Migration online physical migrations leverage Oracle Data Guard, so you must have the same operating system and database version on both source and target.
- The Zero Downtime Migration physical migration work flow does not support cross-edition migration; however, you can migrate Standard Edition to Enterprise Edition using the logical migration work flow.
- The character set on the source database must be the same as the target database.
- The source and target databases must use a server parameter file (SPFILE).
- ZDM supports the source databases that are not using SPFILE for offline migration. For online migration, you must run the source database with SPFILE.
- System time of the Zero Downtime Migration service host and source database server should be in sync with your Oracle Cloud Infrastructure target.

If the time on any of these systems varies beyond 6 minutes from the time on OCI, it should be adjusted. You can use `ntp time check` to synchronize the time if NTP is configured. If NTP is not configured, then it is recommended that you configure it. If

configuring NTP is not an option, then you need to correct the time manually to ensure it is in sync with OCI time.

- Set the `COMPATIBLE` database initialization parameter to the same value on the source and target database. See [Values for the COMPATIBLE Initialization Parameter in Oracle Database](#) for valid values.
- Ensure that both source and target `SQLNET.ORA` have the same encryption algorithm.
- Ensure that the target database time zone is same as the source or higher. If the source database time zone version is lower than the target database, then post migration, you must upgrade the database timezone. Time zone upgrade will encounter downtime when you adjust the time zone and this involves database to be restarted twice. The downtime involved in the time zone upgrade depends on the amount of data requiring change. Preferably, match the time zone version of the source and the target database to avoid time zone upgrade involving extended downtime. However, ZDM automates upgrading time zone for physical migration as a part of workflow. See `ZDM_TGT_UPGRADE_TIMEZONE_FILE`.
- ZDM enables backup compression and encryption to be turned off. You can turn off the encryption when migrating between on-premises databases only. Encryption is mandatory when migrating to cloud targets. See `ZDM_RMAN_ENCRYPT_BACKUP`.
- You can configure the section size to be used by RMAN. See `ZDM_RMAN_SECTION_SIZE`.
- Ensure that `/tmp` is mounted with `execute` permission as a prerequisite for the source and target databases if you want to perform a physical migration.

4.3 Source Database Prerequisites

Meet the following prerequisites on the source database before the Zero Downtime Migration process starts.

- **Set archiving mode**

The source database must be running in `ARCHIVELOG` mode. See [Changing the Database Archiving Mode](#).

- **Configure the TDE wallet** on Oracle Database 12c Release 2 and later.

For Oracle Database 12c Release 2 and later, if the source database does not have Transparent Data Encryption (TDE) enabled, then it is mandatory that you configure the TDE wallet before migration begins. You need not encrypt the data in the source database; the data is encrypted at target using the wallet setup in the source database. The `WALLET_TYPE` can be `AUTOLOGIN` (preferred) or `PASSWORD` based.

Ensure that the wallet `STATUS` is `OPEN` and `WALLET_TYPE` is `AUTOLOGIN` (For an `AUTOLOGIN` wallet type), or `WALLET_TYPE` is `PASSWORD` (For a `PASSWORD` based wallet type). For a multitenant database, ensure that the wallet is open on all PDBs as well as the CDB, and the master key is set for all PDBs and the CDB.

```
SQL> SELECT * FROM v$encryption_wallet;
```

Enabling TDE on Oracle Database 11g Release 2 (11.2.0.4) and Oracle Database 12c Release 1 is optional.

- **For Oracle RAC:**

If the source is an Oracle RAC database, and `SNAPSHOT CONTROLFILE` is not on a shared location, configure `SNAPSHOT CONTROLFILE` to point to a shared location on all Oracle RAC nodes to avoid the ORA-00245 error during backups to Oracle Object Store.

For example, if the database is deployed on ASM storage,

```
$ rman target /  
RMAN> CONFIGURE SNAPSHOT CONTROLFILE NAME TO '+DATA/db_name/  
snapcf_db_name.f';
```

If the database is deployed on an ACFS file system, specify the shared ACFS location in the above command.

- **Check port connections**

- Verify that port 22 on the source database server allows incoming connections from the Zero Downtime Migration service host.
- Ensure that the scan listener ports (1521, for example) on the source database servers allow incoming connections from the target database servers and outgoing connections to the target database servers.

Alternate SQL connectivity should be made available if a firewall blocks incoming remote connection using the SCAN listener port.

- **Maintain RMAN backup strategy**

To preserve the source database Recovery Time Objective (RTO) and Recovery Point Objective (RPO) during the migration, the existing RMAN backup strategy should be maintained.

During the migration a dual backup strategy will be in place; the existing backup strategy and the strategy used by Zero Downtime Migration.

Avoid having two RMAN backup jobs running simultaneously (the existing one and the one initiated by Zero Downtime Migration).

If archive logs were to be deleted on the source database, and these archive logs are needed by Zero Downtime Migration to synchronize the target cloud database, then these files should be restored so that Zero Downtime Migration can continue the migration process.

- **Configure RMAN to automatically back up to control file**

If RMAN is not already configured to automatically back up the control file and SPFILE, then set `CONFIGURE CONTROLFILE AUTOBACKUP` to ON and revert the setting back to OFF after migration is complete.

```
RMAN> CONFIGURE CONTROLFILE AUTOBACKUP ON;
```

- **Register with SRVCTL**

If the source database is deployed using Oracle Grid Infrastructure and the database is not registered using SRVCTL, then you must register the database before the migration.

- **For offline migrations**

Plan to make sure no incoming transactions take place on the source database before the `ZDM_BACKUP_DIFFERENTIAL_SRC` phase, so that there is no loss of data during the migration.

Once Zero Downtime Migration starts generating backups and transfers them, any new transactions on the source won't be part of the backups and therefore the target in the cloud won't have those changes.

- **Handling of DB_nK_CACHE_SIZE**

Zero Downtime Migration automates the copy of [DB_nK_CACHE_SIZE](#) values from the source `init` file to the target database. This automation benefits migrations where the source database uses any tablespace of variable block size other than `db_block_size`. In such cases, without Zero Downtime Migration handling of `DB_nK_CACHE_SIZE`, the restore process would fail.

Note

For migrations where non-CDB to PDB conversion takes place, you must set this value in the actual target CDB in which the source will be plugged in.

4.4 Target Database Prerequisites

You must create a placeholder target database before beginning a migration to the target environment. The following prerequisites must be met on the target database before you begin the Zero Downtime Migration process.

The placeholder target database is overwritten during migration, but it retains the overall configuration.

- For this release, only Grid Infrastructure-based database services are supported as targets. For example, an LVM-based instance or an instance created in a node without Grid Infrastructure are not supported targets.
- For the Oracle Exadata Database Service on Dedicated Infrastructure and Oracle Exadata Database Service on Cloud@Customer targets, the placeholder database must be created using the Control Plane, not Grid Infrastructure Database Services before database migration begins.

- **Size for the future**

When you create the database from the console, ensure that your chosen shape can accommodate the source database, plus any future sizing requirements. A good guideline is to use a shape similar to or larger in size than source database.

- **Set name parameters**

- `DB_NAME`

If the target database is Oracle Exadata Database Service on Dedicated Infrastructure or Oracle Exadata Database Service on Cloud@Customer, then the database `DB_NAME` should be the same as the source database `DB_NAME`.

If the target database is Oracle Cloud Infrastructure, then the database `DB_NAME` can be the same as or different from the source database `DB_NAME`.

- `DB_UNIQUE_NAME`

If the target database is Oracle Cloud Infrastructure, Oracle Exadata Database Service on Dedicated Infrastructure, or Oracle Exadata Database Service on Cloud@Customer, the target database `DB_UNIQUE_NAME` parameter value must be unique to ensure that Oracle Data Guard can identify the target as a different database from the source database.

Note

Ensure that the name for source and target database are same and they also have the same letter case, lowercase or uppercase.

- **Match the source SYS password**

Specify a `SYS` password that matches that of the source database.

- **Disable automatic backups**

Provision the target database from the console without enabling automatic backups.

For Oracle Cloud Infrastructure and Oracle Exadata Database Service on Dedicated Infrastructure, do not select the **Enable automatic backups** option under the section **Configure database backups**.

For Oracle Exadata Database Service on Cloud@Customer, set Backup destination **Type** to `None` under the section **Configure Backups**.

- **Verify patch level**

The target database version should be the same as the source database version. Oracle recommends that the target database patch level should also be the same as (or higher than) the source database.

Note

While Oracle Zero Downtime Migration supports discrepancies in patch levels, it is always recommended, even for the purposes of migration, to only have a difference of one year maximum between patch levels.

If the target database environment is at a higher patch level than the source database (for example, if the source database is at Jan 2020 PSU/BP and the target database is at April 2020 PSU/BP), then Zero Downtime Migration runs the datapatch utility as part of the migration.

- **Verify time zone file version**

The target placeholder database must have a time zone file version that is the same or higher than the source database. If that is not the case, then the time zone file should be upgraded in the target placeholder database.

To check the current time zone version, query the `V$TIMEZONE_FILE` view as shown here, and upgrade the time zone file if necessary.

```
SQL> SELECT * FROM v$timezone_file;
```

- **Verify TDE wallet folder exists**

Verify that the TDE wallet folder exists, and ensure that the wallet `STATUS` is `OPEN` and `WALLET_TYPE` is `AUTOLOGIN` (For an auto-login wallet type), or `WALLET_TYPE` is `PASSWORD` (For a password-based wallet). For a multitenant database, ensure that the wallet is open on all PDBs as well as the CDB, and the master key is set for all PDBs and the CDB.

```
SQL> SELECT * FROM v$encryption_wallet;
```

- **For Oracle RAC targets:**

If the target is an Oracle RAC database, then verify that SSH connectivity without a passphrase is set up between the Oracle RAC servers for the oracle user.

- **Check disk groups size and usage**

Check the size of the disk groups and usage on the target database (ASM disk groups or ACFS file systems) and make sure adequate storage is provisioned and available on the target database servers.

- **Check connections**

- Verify that ports 22 and 1521 (or the configured database listener port) on the target servers in the Oracle Cloud Infrastructure, Oracle Exadata Database Service on Dedicated Infrastructure, or Oracle Exadata Database Service on Cloud@Customer environment are open and not blocked by a firewall.

An open connection is required from the Zero Downtime Migration host and the and source database server.

- Verify that port 22 on the target database server allows incoming connections from the Zero Downtime Migration service host.

- **Capture the output of the RMAN SHOW ALL command**

Capture output so that you can compare RMAN settings after the migration, then reset any changed RMAN configuration settings to ensure that the backup works without any issues.

```
RMAN> show all;
```

4.5 Setting Up the Transparent Data Encryption Keystore

For Oracle Database 12c Release 2 and later, if the source and target databases do not have Transparent Data Encryption (TDE) enabled, then it is mandatory that you configure the TDE keystore before migration begins.

① Note

For Oracle Database 11.2 and 12.1 sources TDE wallet configuration is not required. If the source does not have a TDE wallet configured, any TDE configuration on the target is removed. After the migration, you must configure the TDE wallet at the target.

① Note

If you migrate Oracle Database 11.2 and 12.1 sources, for unencrypted sources, even when providing a TDE wallet (which is a requirement), ZDM will not be able to use ENCRYPT on RESTORE at the target database. This is applicable when you migrate and upgrade the CDB databases. You must perform any missing encryption tasks manually, post-migration.

TDE should be enabled and the TDE WALLET status on both source and target databases must be set to OPEN. The WALLET_TYPE can be AUTOLOGIN, for an auto-login keystore (preferred), or PASSWORD, for a password-based keystore. On a multitenant database, make sure that the keystore is open on all PDBs as well as the CDB, and that the master key is set for all PDBs and the CDB.

Note

Ensure to open all the PDBs before running any of the commands described.

If TDE is not already configured as required on the source and target databases, use the following instructions to set up the TDE keystore.

Note

When the source TDE wallet is configured with `LOCAL_AUTOLOGIN` single sign-on certificate, ZDM does not copy the single sign-on, because the `LOCAL_AUTOLOGIN` single sign-on certificates are only valid on the nodes for which they are generated. Instead, you must enter the TDE wallet password to generate the `AUTOLOGIN` certificate for the target nodes. So, when the source is using the `LOCAL_AUTOLOGIN` wallet, post migration the target will have `AUTOLOGIN` wallet. ZDM will not generate the `LOCAL_AUTOLOGIN` wallet.

Note

When the source or the target database is using keystore location different from the `FILE` or `ASM` wallet, ZDM does not migrate the TDE keys. Ensure that the wallet keys at the source that are accessible from the target because, when the keystore is available not on file system keystore, the export, import, or migration of the keys need to be handled using keystore specific tools. ZDM cannot migrate the keys from keystores that are different from `FILE` or `ASM`.

ZDM encrypts **all** tablespaces for cases where TDE is mandatory for migrations involving backup/restore or direct migration using restore from service.

ZDM now uses a single restore statement with `encrypt on restore` for the entire database for targets which have Oracle Database 19c and later versions:

```
RESTORE DATABASE AS ENCRYPTED AS ENCRYPTED FROM TAG 'ZDM_JOB_10';
```

Note

This feature affects migrations that uses backup/restore or direct migration using restore from service. For migrations using ZDLRA or direct using active duplicate, ZDM does not perform any additional encryption, the encryption status on the target post restore is same as the source database.

For a password-based keystore, you only need to do steps 1, 2, and 4; for an auto-login keystore, complete all of the steps.

1. Set `ENCRYPTION_WALLET_LOCATION` in the `$ORACLE_HOME/network/admin/sqlnet.ora` file.

```
/home/oracle>cat /u01/app/oracle/product/12.2.0.1/dbhome_4/network/admin/  
sqlnet.ora
```

```
ENCRYPTION_WALLET_LOCATION=(SOURCE=(METHOD=FILE)
```



```
(METHOD_DATA=(DIRECTORY=/u01/app/oracle/product/12.2.0.1/dbhome_4/
network/admin/)))
```

For an Oracle RAC instance, also set `ENCRYPTION_WALLET_LOCATION` in all the nodes.

2. Create and configure the keystore.

a. Connect to the database and create the keystore.

```
$ sqlplus "/as sysdba"
SQL> ADMINISTER KEY MANAGEMENT CREATE KEYSTORE '/u01/app/oracle/product/
12.2.0.1/dbhome_2/network/admin'
identified by password;
```

b. Open the keystore.

For a non-CDB environment, run the following command.

```
SQL> ADMINISTER KEY MANAGEMENT SET KEYSTORE OPEN IDENTIFIED BY password;
keystore altered.
```

For a CDB environment, run the following command.

```
SQL> ADMINISTER KEY MANAGEMENT SET KEYSTORE OPEN IDENTIFIED BY password
container = ALL;
keystore altered.
```

c. Create and activate the master encryption key.

For a non-CDB environment, run the following command.

```
SQL> ADMINISTER KEY MANAGEMENT SET KEY IDENTIFIED BY password with
backup;
keystore altered.
```

For a CDB environment, run the following command.

```
SQL> ADMINISTER KEY MANAGEMENT SET KEY IDENTIFIED BY password with
backup container = ALL;
keystore altered.
```

d. Query `V$ENCRYPTION_KEYS` to get the keystore status, keystore type, and keystore location.

```
SQL> SELECT * FROM v$encryption_keys;
```

```
WRL_TYPE      WRL_PARAMETER
-----
-----
-----
STATUS          WALLET_TYPE      WALLET_OR
FULLY_BAC      CON_ID
-----
-----
FILE           /u01/app/oracle/product/12.2.0.1/dbhome_2/network/admin/
```

OPEN	PASSWORD	SINGLE
NO	0	

The configuration of a password-based keystore is complete at this stage, and the keystore is enabled with status **OPEN** and **WALLET_TYPE** is shown as **PASSWORD** in the query output above.

Continue to step 3 only if you need to configure an auto-login keystore, otherwise skip to step 4.

3. For an auto-login keystore only, complete the keystore configuration.

a. Create the auto-login keystore.

```
SQL> ADMINISTER KEY MANAGEMENT CREATE AUTO_LOGIN KEYSTORE FROM KEYSTORE
'/u01/app/oracle/product/12.2.0.1/dbhome_2/network/admin/' IDENTIFIED
BY password;
keystore altered.
```

b. Close the password-based keystore.

```
SQL> ADMINISTER KEY MANAGEMENT SET KEYSTORE CLOSE IDENTIFIED BY
password;
keystore altered.
```

c. Query **V\$ENCRYPTION_WALLET** to get the keystore status, keystore type, and keystore location.

```
SQL> SELECT * FROM v$encryption_wallet;
WRL_TYPE WRL_PARAMETER
-----
-----
STATUS WALLET_TYPE WALLET_OR FULLY_BAC CON_ID
-----
-----
FILE /u01/app/oracle/product/12.2.0.1/dbhome_2/network/admin/
OPEN AUTOLOGIN SINGLE NO
```

In the query output, verify that the TDE keystore **STATUS** is **OPEN** and **WALLET_TYPE** set to **AUTOLOGIN**, otherwise the auto-login keystore is not set up correctly.

This completes the auto-login keystore configuration.

4. Copy the keystore files to the second Oracle RAC node.

If you configured the keystore in a shared file system for Oracle RAC, or if you are enabling TDE for a single instance database, then no action is required.

If you are enabling TDE for Oracle RAC database without shared access to the keystore, copy the following files to the same location on second node.

- /u01/app/oracle/product/12.2.0.1/dbhome_2/network/admin/ew*
- /u01/app/oracle/product/12.2.0.1/dbhome_2/network/admin/cw*

Note

ZDM can migrate all the wallet files and sub-directories configured under `WALLET_ROOT`. If the source has PDB wallets in isolated mode, ZDM migrates all of the wallet's files in sub-directories under `WALLET_ROOT`.

Handling TDE for the PDB clone: If the source PDB has encrypted data or a TDE master encryption key has been set, you must provide the target keystore password using the `-tgttdekeystorepasswd` CLI parameter. To setup TDE wallet, see [How Configuring Transparent Data Encryption Works](#).

Related Topics

- [Using Transparent Data Encryption](#)
- [Configuring a TDE Wallet](#)

4.6 Using Supported Data Transfer Media

The Zero Downtime Migration physical migration process involves creating a backup of the source database and restoring it to the target database, or using an existing backup.

Oracle Cloud Infrastructure Object Storage

OCI Object Storage is supported as a backup medium when migrating a database to Oracle Cloud Infrastructure, Oracle Exadata Database Service on Dedicated Infrastructure, or any on-premises Oracle Exadata Database Service on Cloud@Customer target.

Zero Downtime Migration service either initiates the source database backup as part of the migration work flow, or you can specify an existing backup already in the Object Storage bucket, and Zero Downtime Migration restores it to the target environment, so Object Storage must be accessible from both the source and target environments.

The source database is backed up to the specified container and restored to the target using RMAN SQL*Net connectivity.

The Zero Downtime Migration service host uses an SSH connection to the source and target database servers to install and configure the backup module software necessary to back up to and restore from Object Storage. The backup from the source database to Object Storage takes place over an RMAN channel.

Make sure that the Object Storage bucket is created using the Oracle Cloud Service Console as appropriate.

Also, make sure adequate storage is provisioned and available on the object store to accommodate the source database backup.

Zero Data Loss Recovery Appliance

Zero Data Loss Recovery Appliance is supported as a backup medium for migrating a database to an Oracle Exadata Database Service on Cloud@Customer target or an Oracle Exadata Database Machine.

If Zero Data Loss Recovery Appliance is chosen as backup medium, then you must ensure that the Zero Data Loss Recovery Appliance has a valid backup of the source database, because Zero Downtime Migration does not initiate a backup to Zero Data Loss Recovery Appliance as part of the work flow.

You must also ensure that all instances of the database are up before initiating a backup to Zero Data Loss Recovery Appliance. The duplicate database operation might fail if the backup is initiated when an instance is down.

The Zero Downtime Migration service accesses the backup in Zero Data Loss Recovery Appliance and restores it to Oracle Exadata Database Service on Cloud@Customer. The Zero Data Loss Recovery Appliance access credentials and wallet location are mandatory input parameters, so that Zero Downtime Migration can handle the Zero Data Loss Recovery Appliance wallet setup at the target database.

Any transfer of redo stream between the source and the target database server, in either direction, takes place over a SQL*Net link.

Refer to the Zero Data Loss Recovery Appliance documentation for information about creating backups.

Network File System (NFS)

NFS is supported as a backup medium when migrating a database to an Oracle Exadata Database Service on Cloud@Customer target, or any on-premises Oracle Exadata Database Machine target.

If you choose to back up the database to an NFS mount, then the Zero Downtime Migration service initiates the source database backup (or you can specify a pre-existing backup) and restores it to the Exadata target environment. The NFS should be accessible from both the source and target environments.

The source database is backed up to the specified path and restored to Oracle Exadata Database Service on Cloud@Customer using RMAN SQL*Net connectivity.

When you perform a migration using offline migration through NFS, SQL*Net connectivity between the source and target are not needed.

Note

For physical migration, NFS is supported for all the target types as long as the storage is shared between the source and the target databases. Also, NFS can be any shared file system, not only the network file system. Other shared file system such as ZFS should work as well.

4.7 Setting Physical Migration Parameters

Set the required physical migration response file parameters. Get the response file template, `$ZDM_HOME/rhp/zdm/template/zdm_template.rsp`, which is used to create your Zero Downtime Migration response file for the database migration procedure, and edit the file as described here.

Note

Currently, only online physical migration is supported when `DATA_TRANSFER_MEDIUM=DIRECT`.

The following response file settings show you how to configure a typical use case. To further customize your configuration you can find additional parameters described in [Zero Downtime Migration Physical Migration Response File Parameters Reference](#).

TGT_DB_UNIQUE_NAME

Set TGT_DB_UNIQUE_NAME to the target database DB_UNIQUE_NAME value. To find DB_UNIQUE_NAME run

```
SQL> show parameter db_unique_name
```

For Cloud type Exadata Cloud at Customer Gen 1, set TGT_DB_UNIQUE_NAME to a different DB_UNIQUE_NAME not currently in use.

PLATFORM_TYPE

Set PLATFORM_TYPE to one of the following:

- VMDB - Oracle Cloud Infrastructure virtual machine or bare metal targets.
- EXACC - Oracle Exadata Database Service on Cloud@Customer, including Oracle Exadata Database Service on Exascale Infrastructure
- EXACS - Oracle Exadata Database Service on Dedicated Infrastructure, including Oracle Exadata Database Service on Exascale Infrastructure
- NON_CLOUD - On-premises Exadata Database Machine

MIGRATION_METHOD

Set MIGRATION_METHOD to one of the following:

- ONLINE_PHYSICAL - Oracle Data Guard (online)
- OFFLINE_PHYSICAL - RMAN backup and restore (offline). Note that this is the only migration method supported for Oracle Database Standard Edition 2.

DATA_TRANSFER_MEDIUM

DATA_TRANSFER_MEDIUM specifies the media used for the source database backup.

- OSS - Oracle Data Guard using Object Storage Service (OSS) for standby initialization.

Supported for PLATFORM_TYPE set to Oracle Cloud Infrastructure (VMDB), Oracle Exadata Database Service on Dedicated Infrastructure (EXACS), and Oracle Exadata Database Service on Cloud@Customer (EXACC).

Also set ZDM_LOG_OSS_PAR_URL to the Cloud Object Store pre-authenticated URL if you want to upload migration logs onto Cloud Object Storage. For information about getting a pre-authenticated URL see Oracle Cloud documentation at <https://docs.oracle.com/en-us/iaas/Content/Object/Tasks/usingpreauthenticatedrequests.htm#usingconsole>.

When you perform a migration using backup and restore (OFFLINE_PHYSICAL) through Object Storage Service, SQL*Net connectivity between the source and target are not needed.

See [Using Supported Data Transfer Media](#) for more information about using OSS.

- ZDLRA - Oracle Data Guard using ZDLRA for standby initialization.

Supported for PLATFORM_TYPE set to Oracle Exadata Database Service on Cloud@Customer (EXACC) or on-premises Exadata Database Machine (NON_CLOUD), and set the following parameters.

- Set SRC_ZDLRA_WALLET_LOC for the wallet location, for example,

```
SRC_ZDLRA_WALLET_LOC=/u02/app/oracle/product/12.1.0/dbhome_3/dbs/zdlra
```

- Set TGT_ZDLRA_WALLET_LOC for the wallet location, for example,
TGT_ZDLRA_WALLET_LOC=target_database_oracle_home/dbs/zdlra.
- Set ZDLRA_CRED_ALIAS for the wallet credential alias, for example,

```
ZDLRA_CRED_ALIAS=zdlra_scan:listener_port/zdlra9:dedicated
```

See [Using Supported Data Transfer Media](#) for more information about using ZDLRA.

- NFS - Oracle Data Guard using backup location such as NFS.

Supported for PLATFORM_TYPE set to Oracle Exadata Database Service on Cloud@Customer (EXACC) or on-premises Exadata Database Machine (NON_CLOUD).

Also set BACKUP_PATH to specify the actual NFS path which is made accessible from both the source and target database servers, for example, an NFS mount point. The NFS mount path should be same for both source and target database servers. This path does not need to be mounted on the Zero Downtime Migration service host.

Note the following considerations:

- The path set in BACKUP_PATH should have 'rwx' permissions for the source database user, and at least read permissions for the target database user (either sharing a common Linux user ID or sharing a common Linux group with the source database user).
- In the path specified by BACKUP_PATH, the Zero Downtime Migration backup procedure will create a directory, \$BACKUP_PATH/dbname, and place the backup pieces in this directory.

See [Mount Options for Oracle files for RAC databases and Clusterware when used with NFS on NAS devices \(Doc ID 359515.1\)](#)

See [Using Supported Data Transfer Media](#) for more information about using NFS.

Now ZDM supports multi mount point scenario for cross data center migrations where the source NFS is not accessible by the target database due to network limitations. ZDM allows different NFS mount point paths for both the source and the target databases.

Set TGT_BACKUP_PATH to specify the target NFS path which is made accessible only from the target database server. To make the backup pieces available for the target database Zero Downtime Migration copies the files from the source NFS path (\$BACKUP_PATH/dbname) into the target NFS path (\$TGT_BACKUP_PATH/dbname). For the copy operation, you can specify the optional BACKUP_TRANSFERTARGET_* parameters:-

- BACKUP_TRANSFERTARGET_HOST: Transfer node host. It defaults to the target node specified for the -targetnode CLI parameter if the property is not specified.
- BACKUP_TRANSFERTARGET_USER: Transfer user that has write permission to the target NFS path. It defaults to the user specified for the target zdmauth plug-in if the property is not specified.
- BACKUP_TRANSFERTARGET_USERKEY: Transfer authentication key. It defaults to the value specified for the identity_file argument of the target zdmauth plug-in.

The backup pieces are copied in parallel using the Linux sftp utility by default. You can use the Linux rsync utility if it is available in both the source database and the target database by setting BACKUP_RSYNC_AVAILABLE to TRUE.

Customize the parallel copy settings by specifying the next parameters:-

- `BACKUP_NFS_PARALLEL_COUNT`: Maximum number of backup pieces to transfer to the transfer node in parallel.
- `BACKUP_NFS_RETRY_COUNT`: Maximum number of times to retry the copy of a backup piece after a failure occurred.

Note

-
- The path set in `BACKUP_PATH_TGT` should have 'rwx' permissions for the transfer user.
- The target database user should share a common group with the transfer user to be able to read the backup pieces.
- The paths specified in both `BACKUP_PATH` and `BACKUP_PATH_TGT` can be different. In that case, Zero Downtime Migration will run the RMAN catalog.

- `DIRECT` - Uses RMAN active database duplication or restore from service to transfer data directly from the source to the target.

The transfer method (restore from service or active duplicate) is configured with `ZDM_RMAN_DIRECT_METHOD`, which is set to `RESTORE_FROM_SERVICE` by default.

ZDM uses the default service and only if you want to use a service other than the default service, then provide the `ZDM_SRC_DB_RESTORE_SERVICE_NAME` parameter.

Note

Here, the source database is the primary source itself.

See [Using Direct Data Transfer](#) for more information about direct data transfer, and see [Using an Existing Standby to Instantiate the Target Database](#) to directly transfer data from a standby.

- `EXTBACKUP` - Oracle Data Guard with existing backup in external location.

Supported for `PLATFORM_TYPE` set to Oracle Exadata Database Service on Cloud@Customer (`EXACC`) or on-premises Exadata Database Machine (`NON_CLOUD`)

See [Using an Existing RMAN Backup as a Data Source](#) for more information.

Additional Oracle Cloud Object Storage Settings

When `DATA_TRANSFER_MEDIUM=OSS`, set the following additional parameters to access Oracle Cloud Object Storage.

- Set `HOST` to the cloud storage REST endpoint URL.
 - For Oracle Cloud Infrastructure storage the typical value format is `HOST=https://swiftobjectstorage.us-phoenix-1.oraclecloud.com/v1/ObjectStorageNamespace`

To find the Object Storage Namespace value, log in to the Cloud Console and select **Menu, Administration, Tenancy Detail**, and in the **Object Storage Settings** section find **Value** against entry **Object Storage Namespace**:

- For Oracle Cloud Infrastructure Classic storage the typical value format is
`HOST=https://acme.storage.oraclecloud.com/v1/Storage-tenancy_name`
- Set the Object Storage bucket `OPC_CONTAINER` parameter.

The bucket is also referred to as a container for Oracle Cloud Infrastructure Classic storage.

TGT_SSH_TUNNEL_PORT

If SSH tunneling is set up, set the `TGT_SSH_TUNNEL_PORT` parameter.

Data and Redo Locations

Zero Downtime Migration automatically discovers the location for data, redo, and redo (for non-Exadata systems) storage volumes from the specified target database. If you need to override the discovered values, specify the target database data files storage (ASM or ACFS) location using the appropriate set of parameters.

- ASM: `TGT_DATADG`, `TGT_REODG`, and `TGT_RECOG`
- ACFS: `TGT_DATAACFS`, `TGT_REDOACFS`, and `TGT_RECOACFS`

SKIP_FALLBACK

Set `SKIP_FALLBACK=TRUE` if you do not want to ship redo logs from the target to the source standby, either voluntarily or because there is no connectivity between the target and the source.

TGT_SKIP_DATAPATCH

Zero Downtime Migration runs the datapatch utility by default as part of the migration process if the target database environment is at a higher patch level than the source database (for example, if the source database is at Jan 2020 PSU/BP and the target database is at April 2020 PSU/BP).

If you want to skip this task set the `TGT_SKIP_DATAPATCH=FALSE` response file parameter.

PHASE_NAME_MONITORING_INTERVAL

Set `PHASE_NAME_MONITORING_INTERVAL=n mins` if you want Zero Downtime Migration to monitor and report the status of backup and restore operations at the configured time interval during the migration. The default interval value is 10 minutes. To disable monitoring, set these values to 0 (zero).

```
ZDM_BACKUP_FULL_SRC_MONITORING_INTERVAL=  
ZDM_BACKUP_INCREMENTAL_SRC_MONITORING_INTERVAL=  
ZDM_BACKUP_DIFFERENTIAL_SRC_MONITORING_INTERVAL=  
ZDM_CLONE_TGT_MONITORING_INTERVAL=  
ZDM_OSS_RESTORE_TGT_MONITORING_INTERVAL=  
ZDM_OSS_RECOVER_TGT_MONITORING_INTERVAL=
```

ZDM_BACKUP_RETENTION_WINDOW

Set `ZDM_BACKUP_RETENTION_WINDOW=number of days` if you wish to retain source database backup after the migration.

ZDM_SRC_TNS_ADMIN

Set `ZDM_SRC_TNS_ADMIN=TNF_ADMIN value` in case of custom location.

ZDM_APPLY_LAG_MONITORING_INTERVAL

Set `ZDM_APPLY_LAG_MONITORING_INTERVAL = {NONE | DAILY | WEEKLY}`, to monitor redo apply lag after standby database creation. This phase queries the current redo apply lag, and waits until redo apply is finished before resuming the job. See `ZDM_APPLY_LAG_MONITORING_INTERVAL`.

4.8 Using an Existing RMAN Backup as a Data Source

Zero Downtime Migration lets you use an existing level 0 backup to skip the full backup phase of a migration job.

This method is supported for Oracle Exadata Database Service on Cloud@Customer or on-premises Exadata Database Machine targets.

Zero Downtime Migration takes level 0 and level 1 backups on the fly for both online and offline physical migration jobs. During a migration job, Zero Downtime Migration lets you re-use existing source database backup in place of performing a full back up.

All types of backup devices, such as DISK, SBT_TAPE, and ZDLRA, are supported as data transfer media for this migration method.

Only level 0 backups with `incremental_level=0` are valid for this use case.

To use an existing RMAN backup, set the following response file parameters.

```
ZDM_USE_EXISTING_BACKUP=TRUE
ZDM_BACKUP_TAG=RMAN backup tag
```

Note

For ZDLRA, you must bring up the pre-existing backup. However, skip the `ZDM_USE_EXISTING_BACKUP` parameter for ZDLRA.

When you run the `ZDMCLI` database migration command in evaluation mode (`ZDMCLI database migration -eval`), Zero Downtime Migration verifies the existence of the backup, checks that it is valid, and displays whether the backup is available and validated in the job output.

In migrate mode (`ZDMCLI database migration`), Zero Downtime Migration performs the same steps done in evaluation mode, then skips full backup and performs other backup operations like incremental and differential backup.

Creating a Backup

To take a valid RMAN backup to use as a migration source, you can run the following commands.

For DISK:

```
RUN {
  ALLOCATE CHANNEL channel_name DEVICE TYPE DISK FORMAT 'directory_path/
  %d_backup_%U';
  ALTER SYSTEM ARCHIVE LOG CURRENT;
  BACKUP AS COMPRESSED BACKUPSET FORCE INCREMENTAL LEVEL 1 FOR RECOVER OF TAG
```

```
'backup_tag'
DATABASE FORMAT 'directory_path/%d_backup_%U_DBF' SECTION SIZE 4G ;
}
```

For SBT_TAPE:

```
RUN {
ALLOCATE CHANNEL channel_name DEVICE TYPE SBT FORMAT '%d_%I_%T-%s_%p'
PARMS 'SBT_LIBRARY=path/libopc.so, SBT_PARMS=(OPC_PFILE=path/OPC/mzdm.conf)';
ALTER SYSTEM ARCHIVE LOG CURRENT;
BACKUP AS COMPRESSED BACKUPSET FORCE INCREMENTAL LEVEL 1 FOR RECOVER OF TAG
'backup_tag'
DATABASE FORMAT '%d_%I_%T-%s_%p_DBF' SECTION SIZE 4G ;
}
```

Creating a Standby Control File Backup

Also, create a standby control file backup in the specified path and provide read permissions to the backup pieces for the target database user. For example,

```
RMAN> BACKUP CURRENT CONTROLFILE FOR STANDBY FORMAT 'BACKUP_PATH/
lower_case_dbname/standby_ctl_%U';
```

Where `standby_ctl_%U` is a system-generated unique file name.

Alternate Use Case

If the `ZDM_BACKUP_TAG` value is provided and `ZDM_USE_EXISTING_BACKUP=FALSE` the Zero Downtime Migration will create a full backup with the provided tag.

Using Backups with Password Authentication

To use an existing backup with backup password authentication, you can specify the password using the `-backuppasswd password` option in the command `migrate database`.

You can also specify a backup wallet path by using `-backupwallet` in the command `migrate database`.

4.9 Using Direct Data Transfer

Zero Downtime Migration supports direct data transfer during a physical migration to avoid backing up the source database to an intermediate store such as Object Storage or NFS.

Active Database Duplication

RMAN active database duplication is supported in Oracle Database 11g (11.2) and later releases.

Restore From Service

RMAN restore from service is supported in Oracle Database 12g (12.1) and later releases. Oracle MAA best practices recommend using active duplication for Oracle Database 11.2 and using restore from service for Oracle Database 12.1 and later.

Because the connection is initiated from the target database host, both active duplication and restore from service direct transfer methods require SQL*Net connectivity from the target to the source database.

4.10 Using an Existing Standby to Instantiate the Target Database

To reduce the load on your primary database system, Zero Downtime Migration can use an existing standby database to instantiate the standby in the target environment in a physical migration.

This migration option is only available when you are using direct data transfer with RMAN restore from service.

Because Oracle Database 11.2 doesn't support RMAN restore from service, it is therefore not supported for migration from an existing standby.

In the previous versions of Zero Downtime Migration, it was required to create a standby control file backup. However, from the 21.4 version of Zero Downtime Migration, you do not require to create a standby control file backup.

Ensure Snapshot Control File is on Shared Storage

In an Oracle Real Application Clusters (Oracle RAC) environment, the snapshot control file location must be on a shared file system- that is, a storage that is accessible to all Oracle RAC instances or ASM.

The snapshot control file location in the RMAN configuration points to the non-shared location in the ORACLE_HOME/dbs/ directory by default.

In cases when data is transferred from a primary database, Zero Downtime Migration configures the snapshot file location, but for direct data transfer from the standby database, Zero Downtime Migration does not configure the location.

You must ensure that RMAN is configured correctly for direct data transfer from the standby.

The example RMAN commands in the following steps set the configuration for the location of the snapshot control file for your cluster database; therefore, ensure that the directory location is shared by all nodes that perform backups.

1. Configure the snapshot control file on one node of source primary database, as shown in this example.

```
RMAN> CONFIGURE SNAPSHOT CONTROLFILE NAME TO  
'+ASM_STBM000038VM5/dbhome2_prim/snapcf_dbhome21.f';
```

```
new RMAN configuration parameters:  
CONFIGURE SNAPSHOT CONTROLFILE NAME TO  
'+ASM_STBM000038VM5/dbhome2_prim/snapcf_dbhome21.f';  
new RMAN configuration parameters are successfully stored
```

```
RMAN> show SNAPSHOT CONTROLFILE NAME;
```

```
RMAN configuration parameters for database with db_unique_name DBHOME2_PRIM  
are:  
CONFIGURE SNAPSHOT CONTROLFILE NAME TO  
'+ASM_STBM000038VM5/dbhome2_prim/snapcf_dbhome21.f';
```

2. Configure the snapshot control file on one node of the source standby database, as shown in this example.

```

RMAN> CONFIGURE SNAPSHOT CONTROLFILE NAME TO
'+ASM_STBM000038VM5/DBHOME2_STBY/snapcf_dbhome21.f';

new RMAN configuration parameters:
CONFIGURE SNAPSHOT CONTROLFILE NAME TO
'+ASM_STBM000038VM5/DBHOME2_STBY/snapcf_dbhome21.f';
new RMAN configuration parameters are successfully stored

RMAN> show SNAPSHOT CONTROLFILE NAME;

RMAN configuration parameters for database with db_unique_name DBHOME2_STBY
are:
CONFIGURE SNAPSHOT CONTROLFILE NAME TO
'+ASM_STBM000038VM5/DBHOME2_STBY/snapcf_dbhome21.f';

```

Enable Target Database Instantiation from the Standby

To request instantiation of the target database from an existing standby, set the following parameters in the physical migration response file.

```

ZDM_USE_EXISTING_STANDBY = TRUE (default FALSE)

ZDM_STANDBY_DB_CONNECT_STRING=connection string to access existing standby
(optional)

```

Keeping Source and Target in Sync

Once the target database is instantiated it is kept in sync by registering with the primary and applying archive redo logs shipped from primary.

Set the following parameters `ZDM_USE_EXISTING_STANDBY = TRUE` (default `FALSE`) and `ZDM_STANDBY_DB_CONNECT_STRING=connection string to access existing standby` (optional). If you want to use the existing standby option, then skip the `ZDM_SRC_DB_RESTORE_SERVICE_NAME` parameter as that is for the source database. By default, ZDM tries to infer the standby database connect string from the Data Guard configuration and you can specify `ZDM_STANDBY_DB_CONNECT_STRING` to override ZDM's standby database connect string discovery.

Existing Oracle Data Guard Broker Configuration Using TNS Aliases

ZDM also supports a standby database with an existing Data Guard Broker configuration using TNS aliases. During the migration, ZDM exports the TNS aliases from the existing configuration and imports only the non-existing ones into the target database by performing the following steps:-

1. Searches the TNS aliases from the existing Data Guard Broker configuration (ZDM_SETUP_SRC phase).
2. Setups non-existing TNS aliases at all target database instances (ZDM_SETUP_TGT phase).

4.11 Preparing for Automatic Application Switchover

To minimize or eliminate service interruptions on the application after you complete the database migration and switchover, prepare your application to automatically switch over connections from the source database to the target database.

Note

In physical migrations, Autonomous Database targets are not supported for automatic application switchover.

In the following example connect string, the application connects to the source database, and when it is not available the connection is switched over to the target database.

```
(DESCRIPTION=
  (FAILOVER=on) (LOAD_BALANCE=on) (CONNECT_TIMEOUT=3) (RETRY_COUNT=3)
  (ADDRESS_LIST=
    (ADDRESS=(PROTOCOL=TCP) (HOST=source_database_scan) (PORT=1521))
    (ADDRESS=(PROTOCOL=TCP) (HOST=target_database_scan) (PORT=1521)))
  (CONNECT_DATA=(SERVICE_NAME=zdm_prod_svc)))
```

On the source database, create the service, named `zdm_prod_svc` in the examples.

```
srvctl add service -db clever -service zdm_prod_svc -role PRIMARY
  -notification TRUE -session_state dynamic -failover_type transaction
  -failover_method basic -commit_outcome TRUE -failover_retry 30 -failover_delay
10
  -replay_init_time 900 -clbgoal SHORT -rlbgoal SERVICE_TIME -preferred
clever1,clever2
  -retention 3600 -verbose
```

If the `db_domain` changes between the source and target then the connect string specified in the application should cater to both for failover to be effective.

```
(DESCRIPTION_LIST=
  (FAILOVER=ON)
  (LOAD_BALANCE=ON)
  (DESCRIPTION=
    (ADDRESS= (PROTOCOL=TCP) (HOST=SRC_SCAN) (PORT=1521))
    (CONNECT_DATA=
      (SERVICE_NAME=SVC.SRC_DOMAIN)))
  (DESCRIPTION=
    (ADDRESS= (PROTOCOL=TCP) (HOST=TGT_SCAN) (PORT=1521))
    (CONNECT_DATA=
      (SERVICE_NAME= SVC.TGT_DOMAIN)))
```

① See Also

Oracle MAA white papers about client failover best practices on the [MAA Best Practices - Oracle Database](https://www.oracle.com/goto/maa) page at <https://www.oracle.com/goto/maa>.
High Availability in Oracle AI Database Development Guide

4.12 Using Oracle Data Guard Broker Role Switchover

In physical migrations, Zero Downtime Migration can leverage the Oracle Data Guard broker to manage database role switchover.

Typically, the Zero Downtime Migration service manages database role switchover after the data migration is complete. You can alternatively enable an option that lets the broker handle the switchover.

The Data Guard Broker is a feature of Data Guard, which is available via the online migration workflow. The Data Guard broker is a distributed management framework that automates the creation, maintenance, and monitoring of Data Guard configurations. You can use a Data Guard broker configuration to improve usability and centralize management and monitoring of the Oracle Data Guard configuration. Using the broker helps not only to set up replication, but also performs gap detection, switchover, and switchback operations.

① Note

Currently, ZDM broker enabled migrations from single instances is only supported if the source environment has an existing Data Guard broker enabled configuration. All the Oracle RAC sources are supported. If you want to migrate a single instance database with no active Data Guard Broker configuration, proceed to migrate with ZDM without the Data Guard Broker.

Prerequisites

Broker-managed role switchovers require two-way SQL*Net connectivity.

Note that broker configuration is not supported for Oracle Database 11.2.0.4.

Enabling Broker Database Role Switchover

You can enable or disable the broker-managed role switchover option using the `ZDM_USE_DG_BROKER` response file parameter.

```
ZDM_USE_DG_BROKER = TRUE | FALSE
```

`ZDM_USE_DG_BROKER` is set to `FALSE` by default, meaning that the broker does not handle the switchover.

Broker Option Validation

When the broker-managed switchover option is enabled, Zero Downtime Migration verifies that the source primary database has no existing standby that is not broker-managed. This check is done because the broker configuration cannot co-exist with a non-broker managed standby.

With the broker option enabled, in cases when the primary (source) database does not have an existing standby, or has a standby that is already managed by the broker, Zero Downtime Migration creates a broker configuration to manage the target (Data Guard standby) database.

4.13 Configuring Resiliency to Intermittent Network Failures

Zero Downtime Migration physical migrations are resilient to intermittent network failures that can cause backups or SSH connectivity to fail.

Zero Downtime Migration can auto-detect intermittent network failures. Zero Downtime Migration automatically retries the RMAN retry-able errors, and some retry customization is available.

SSH connection retries are customized using the following parameters:

`SRC_SSH_RETRY_TIMEOUT`

`TGT_SSH_RETRY_TIMEOUT`

You can customize RMAN backup retries with following parameters:

`ZDM_OPC_RETRY_WAIT_TIME`

`ZDM_OPC_RETRY_COUNT`

`ZDM_OPC_RETRY_WAIT_TIME`

4.14 Converting a Non-CDB Database to a CDB During Migration

As part of the physical migration process, Zero Downtime Migration can handle conversion of a non-CDB source database to a PDB of the same version in the cloud. The conversion process transforms the source non-CDB into a target PDB that is then plugged into an existing CDB in the target.

Downtime will increase due to the non-CDB to CDB conversion. This process is offline (no redo transport and apply), and no rollback is possible.

ZDM physical migration allows the conversion between Non-CDB sources and PDB targets. Define the name of the target PDB before starting the migration with the `ZDM_NONCDBTOPDB_PDB_NAME` response file parameter.

① Note

For the conversion use case, when a non-CDB source database is being migrated to a target CDB database as a PDB, if the target database has a standby configured, then the unplug or plug process does not replicate the PDB database to the target standby database. To migrate the new PDB, either you need to rebuild the standby or you need to replicate the PDB. Refer to [this](#) MOS note for the steps for replicating the PDB to standby.

Source non-CDB Database Prerequisites

- Oracle Database 12c or later versions, because this is when multitenant architecture became available

- Same character set as the target CDB

Target Database CDB and PDB Prerequisites

- The target CDB must not contain a PDB with same name as the resulting converted PDB, because Zero Downtime Migration will create the PDB.
- The target database must be at least the same major version as the source database.
 - If the minor version is different on the target, it must be a higher minor version than the source database.
 - If the patch level is different, you must set the response file parameter `TGT_SKIP_DATAPATCH=FALSE`.
- Ensure that the target CDB database has sufficient resources such as memory and CPU, to accommodate migrating a non-CDB database and converting to a PDB, that is plugged into the target CDB database.

Transparent Data Encryption Requirements

- For source credentials, the `migrate database` command must include either `-tdekeystorepasswd` or the `-tdekeystorewallet auto-login` option.
- If any of these options is used then the target credentials must be also provided by using either `-tgttdekeystorepasswd` or the `-tgttdekeystorewallet auto-login` option.

Application Express Requirements

- If Application Express (APEX) is not installed on the source there are no further requirements.
- If APEX exists on the source, and the source database is a non-CDB, you must choose one of the following options:
 - Remove APEX from the source non-CDB.
 - Verify that the APEX version on the target CDB is the same as that on the source. If APEX is not at the same version conversion is not possible; APEX schemas vary between versions and the target PDB will not be able to open.

The target CDB is not dropped in the process, and the presence or absence of other PDBs does not affect the outcome of the conversion and plug-in.

Parameters in the response file are set as follows:

- (Required) `NONCDBTOPDB_CONVERSION`: Set to `TRUE` to indicate that you want to convert a source database from non-CDB to PDB.
- (Optional) `NONCDBTOPDB_SWITCHOVER`: Set to `TRUE` for a physical migration using Data Guard switchover, to execute switchover operations during a migration job with non-CDB to PDB conversion enabled.

Note

Ensure that the `AUX` name (PDB name) that you specify in the response file does not overlap with the target `db_name`, `db_unique name`, and any target `SID` names. ZDM assumes the `SID` name for `AUX` as `<AUX_NAME>1`, as well as `<AUX_NAME>` and if either of those overlap with the target `db_name`, `db_unique name`, or target `SIDs`, that can cause an issue. You can also run the `-eval` option. Ensure that the `AUX` name is kept to 11 or fewer characters to ensure that `SID` does not exceed 12 characters.

The following are examples of the ZDMCLI `migrate database` command usage for converting a non-CDB to a PDB during migration using the TDE credentials.

Example interactively supplying passwords:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-sourcedb source_db_unique_name_value
-sourcenode source_database_server_name
-srcroot
-targetnode target_database_server_name
-backupuser Object_store_login_user_name
-rsp response_file_location
-tgtauth zdmauth
-tgtarg1 user:target_database_server_login_user_name
-tgtarg2 identity_file:ZDM_installed_user_private_key_file_location
-tgtarg3 sudo_location:/user/bin/sudo
-tdekeystorepasswd
-tgttdekeystorepasswd
```

Example using auto-login wallet for CDB TDE keystore:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-sourcedb source_db_unique_name_value
-sourcenode source_database_server_name
-srcroot
-targetnode target_database_server_name
-backupuser Object_store_login_user_name
-rsp response_file_location
-tgtauth zdmauth
-tgtarg1 user:target_database_server_login_user_name
-tgtarg2 identity_file:ZDM_installed_user_private_key_file_location
-tgtarg3 sudo_location:/user/bin/sudo
-tdekeystorepasswd
-tgttdekestorewallet /scratch/credentials/cdbtde.sso
```

4.15 Migrating an On-Premises Database to an On-Premises Exadata Database Machine

An on-premises migration to an on-premises Exadata Database Machine target using Zero Downtime Migration works the same way as a migration to a cloud target. In the response file, you indicate that the migration target is on-premises by setting `PLATFORM_TYPE=NON_CLOUD`.

Just like in cloud migration scenarios, you must provision the target database with the shape and size desired, including configuring any initialization parameters, before starting the migration. The target database is expected to be the same major version as the source database, Oracle Grid Infrastructure is mandatory at the target database, and target datafiles can be stored on ASM or ACFS.

One aspect where an on-premises to on-premises migration is different from migrating to the cloud is in the handling of Transparent Data Encryption (TDE). On the cloud, TDE is mandatory for Oracle Database 12.2 and later releases; however, for an on-premises to on-premises migration, TDE must be configured at the target only if TDE is used at the source. You must configure TDE at the target before the migration starts; Zero Downtime Migration does not configure it for you.

You can specify that TDE is not configured at the source or target by setting the response file parameter `ZDM_TDE_MANDATORY=FALSE`. This parameter can only be used when you set `PLATFORM_TYPE=NON_CLOUD`. With `ZDM_TDE_MANDATORY=FALSE` set, Zero Downtime Migration does not require TDE at the target when the source is not using TDE, and does not encrypt the target on restore.

For an on-premises Exadata target database migration, `MIGRATION_METHOD` can be set to `ONLINE_PHYSICAL` or `OFFLINE_PHYSICAL`, and `DATA_TRANSFER_MEDIUM` can be set to any of the values supported by Zero Downtime Migration. Set the remaining parameters as you would for a cloud migration.

4.16 Creating an Oracle Cloud Native Disaster Recovery Strategy

In a typical migration, ZDM migrates a source database to only one target database (single point of failure). Now you can create a DR (Disaster Recovery) strategy during post-migration to be able to respond to and recover from an event that negatively affects your business operations.

Two target databases are instantiated during the migration (target primary database and target standby database), where both can be in different regions (to reduce impacts of natural disasters). During post-migration, Oracle Data Guard Broker configuration is restored in both target databases to allow cloud native operations like switchover and failover (in the Oracle Database Cloud Service console).

Prerequisites:

1. Instantiate both target database and target standby database before beginning the migration process. These environments are assumed to be configured using Data Guard (DG) Broker.
 - When ExaCS/ExaCC is used for `platform_type`, this can be done using DG Associations (in the Oracle Database Cloud Service console).
 - For VMDB `platform_type`, the configuration can be done (manually) using DGMGRL Oracle Data Guard Broker CLI tool.
2. Supported migration methods: Only online migrations are supported (where Oracle Data Guard is used).
3. Supported data transfer methods: OSS, ZDLRA, Direct.
4. Supported Platform type: ExaCS, ExaCC, VMDB (ZDLRA is not supported).
5. Set the parameters in the response file as follows:
Required:
 - Set `TGT_STBY_NODE` to the target standby database IP address to indicate that you want to configure a DR strategy on post-migration.
 - `TGT_STBY_DB_UNIQUE_NAME`: can identify the target standby as a different database from both the source database and the target database.
 - For connectivity to the target standby database, set `TGT_STBY_AUTH= zdmauth` and configure `TGT_STBY_SUDO_USER` (`target_standby_database_server_login_user_name`), `TGT_STBY_IDENTITY_FILE` (`ZDM_installed_user_private_key_file_location`), and `TGT_STBY_SUDO_PATH` (`sudo_path`).

Optional:

- To keep the target standby database in sync during the migration, set `ZDM_TGT_STBY_CASCADING` to `TRUE` (default value) to allow redo log shipping from the target database or set to `FALSE` to allow the redo log shipping from the source database (primary).
- Set `TGT_STBY_ZDLRA_WALLET_LOC` if you want to use ZDLRA as the data transfer medium.

Note

This use case is only supported for Non-CDB to Non-CDB migrations and for CDB to CDB migrations, migrations that require conversion are not currently supported.

When migrating NON-CDB to PDB using regular migration, it will get plugged into the target CDB. The target CDB can be setup to have a DR setup (for example using Oracle Data Guard Association in the console) of its own and when the NON-CDB is plugged into the target CDB, it would be replicated via the target CDB.

For DR migrations using ZDM, the source database will not be added (during post migration) to the OCI Oracle Data Guard Broker Configuration so it won't be managed by the OCI Console. However, the source database will still continue to receive the redo logs from the target database after the switchover.

4.17 Migration and Upgrade of CDB Databases

ZDM performs migration of a CDB database to a CDB database and later upgrades the target CDB database to a version of `ORACLE_HOME` provided in the `ZDM_UPGRADE_TARGET_HOME` parameter.

ZDM supports migration and upgrade of CDB for the target environment VMDB (Oracle Base Database Service) using `dbcli` utility. For other target environments apart from Oracle Base Database Service, Oracle Exadata Database Service on Dedicated Infrastructure, and Oracle Exadata Database Service on Cloud@Customer, ZDM uses `autoupgrade` to perform upgrade of CDB.

ZDM supports migration and upgrade of CDB for Oracle Exadata Database Service on Dedicated Infrastructure and Oracle Exadata Database Service on Cloud@Customer target environment using the `dbaascli` utility.

Note

For VMDB/EXACC/EXACS CDB upgrade target auth plugin, `dbuser`, and `sudoasuser` are not supported. Only `zdmauth` is the supported plugin in this scenario.

Note

You must ensure that the source database has TDE configured and you provide the wallet details, this ensures that post the migration and upgrade, the Oracle Database 19c target database has TDE configured. For upgrade and migrate scenario, TDE is mandatory for all releases. This is mandatory for all source versions, including Oracle Database 11.2 and Oracle Database 12.1. TDE is mandatory in the Oracle Cloud, for Oracle Database 12.2 and higher versions. For more information, see [Setting Up the Transparent Data Encryption Keystore](#).

Note

Currently, for Oracle Base Database Service, when you provision an Oracle Database 19c, the GI provisioned is also of the same version Oracle Database 19c. Currently, it is not possible to upgrade the Oracle Grid Infrastructure 19c to Oracle Grid Infrastructure 26ai either. So effectively, it is currently not possible to install an Oracle AI Database 26ai database on the VMDB system initially created with Oracle Database 19c/GI. So, for the migration and upgrade scenario, provision the database version at the same version as source and provide an additional database version running at a higher version.

Autoupgrade is used only for non_cloud targets. For all cloud platforms such as Oracle Exadata Database Service on Dedicated Infrastructure, Oracle Exadata Database Service on Cloud@Customer as well as Oracle Base Database Service, cloud tooling is used for upgrade. For Oracle Exadata Database Service on Dedicated Infrastructure and Oracle Exadata Database Service on Cloud@Customer dbaascli is used and dbcli for Oracle Base Database Service.

As a prerequisite, provision ORACLE_HOME in Oracle Base Database Service, Oracle Exadata Database Service on Dedicated Infrastructure, and Oracle Exadata Database Service on Cloud@Customer environments as follows:

- Provision ORACLE_HOME in VMDB using the following command:
`/opt/oracle/dcs/bin/dbcli create-dbhome -v <supported db version>`

Note

For the use cases that do not involve Non-CDB to PDB conversion, the provisioned target database must be of the same version as the source database.

- Provision ORACLE_HOME in EXACC/EXACS using console or by using the following command:
`dbaascli dbhome create --version <supported_version>`

The upgrade starts after the completion of migration. Perform the following steps:

1. Select the same version of the source and the target CDB.
2. Provision the ORACLE_HOME to the version you want to upgrade in the target database.
3. Provide the path of the provisioned ORACLE_HOME in the ZDM_UPGRADE_TARGET_HOME parameter.

For migrate+upgrade scenario, not involving conversion to PDB, ZDM will migrate the source database as is to the target. You can use any of the existing migration method, offline/online for

this. Once the database is running in the target, ZDM uses the cloud platform tooling or autoupgrade to upgrade the database.

4.18 Migration, Upgrade, and Conversion of a Non-CDB to a PDB Database

In a single migration job, ZDM can migrate a non-CDB database to the target environment, upgrade the database to a PDB, and then plug in the upgraded PDB into the provided target CDB.

ZDM supports migration and plug in of a non-CDB source database to a higher version target database using `autoupgrade.jar` to perform upgrade precheck, fixups and upgrade+plug operation. For example, the source non-CDB database could be of version Oracle Database 12.1 and target database could be a CDB of version Oracle Database 19c.

Note

For the upgrade of Non-CDB database, Oracle Database 11g Release 2 (11.2.0.4) , `catbundle.sql` is required. ZDM validates in the target database, the `catbundle.sql` location for the upgrade scenario of Oracle Database 11g Release 2 (11.2.0.4) database.

The following inputs are required for this type of migration:

1. The source database is a non-CDB, presumably at a lower release than target CDB (for example 12.1)
2. A CDB on the target host at the desired database version (for example, 19c).
3. A database `ORACLE_HOME` of the same major version as the current source non-CDB version located on the target host.
This home is used by ZDM to create an auxiliary Non-CDB database that is used during the migration process.

Set the `ZDM_PRE_UPGRADE_TARGET_HOME` response file parameter to the path of this `ORACLE_HOME`.

For migrate+upgrade+conversion use case, ZDM will first migrate non-CDB as non-CDB database to target. Initially non-CDB will be migrated as an auxiliary staging database using any of the existing migration methods offline or online. The auxiliary will be running at the same version as source. ZDM does need an additional home at the same version as the source to migrate and stage the non-CDB first. Once the database is running on the target, ZDM will use AutoUpgrade to unplug or plug and upgrade non-CDB into 19c CDB target. Additionally, unplug or plug and/or upgrade, is an offline operation, meaning these operations involve additional downtime. If an online method was used for migrating the data, ZDM will first disconnect the target and source database before proceeding to unplug/plug and/or upgrade phase.

4.19 Using External Keystores

When the TDE keys are on external keystore, then you must migrate the keys on your own.

Ensure proper installation, password configuration, and communication setup for seamless operation.

Work with your external keystore vendor for detailed configuration steps. The details outlined below provides a high-level overview of the generic steps required to configure an external keystore.

External Keystore Server Installation: You are responsible for installing and configuring the external keystore server using the documentation provided by the vendor.

External Keystore Password Format: The format of the external keystore password varies depending on the provider.

Network Configuration: Ensure that a connection is established between the Guest VM and the external keystore server by: -

- Setting up the required network.
- Opening the necessary ports.
- Enabling the protocol specified by the external keystore vendor.

PKCS#11 Library Installation: Install the PKCS#11-related software and configure the PKCS#11 library on the VMs according to the external keystore vendor's documentation.

Communication Validation: Verify that the PKCS#11 library can successfully communicate with the external keystore.

Note

The cloud automation does not perform prechecks to validate this connection. If the key is inaccessible, the database will return an error with the relevant details.

You must migrate the encryption keys on the external keystore and then set the `ZDM_SKIP_TDE_WALLET_MIGRATION=TRUE` parameter in the RSP file to skip the ZDM TDE Wallet migration.

ZDM supports automatic keystore migration if the source or target are configured with OKV (Oracle Key Vault) external keystore. For more information, see [Migrating Source Database with OKV Keystore Configured as an External Keystore](#).

4.19.1 Migrating Source Database with OKV Keystore Configured as an External Keystore

ZDM performs migration of external keystore wallets if the source or target database are configured to use OKV (Oracle Key Vault) external keystore.

There are four supported scenarios when migrating a wallet with ZDM:

- Source database with OKV wallet to Target database with OKV wallet
- Source database with OKV wallet to Target database with File wallet.
- Source database with File wallet to Target database with OKV wallet
- Source database with File wallet to Target database with File wallet.

You can migrate a source database configured with or without an OKV wallet to a target database configured with or without an OKV wallet. Currently, ZDM allows migrating databases that use the file TDE wallets and also it allows migrations where the wallet is not transferred during the ZDM workflow.

Note

ZDM does not provision the OKV wallet on the endpoints. You must configure and provision the OKV wallet on all endpoints.

ZDM identifies whether the source database is configured to use OKV wallet and it will download the keys from the OKV wallet to then migrate them to the target database. If the target database is also configured with OKV wallet, ZDM will upload the keys to the OKV wallet. Do not change the default value of `ZDM_SKIP_TDE_WALLET_MIGRATION` parameter to allow ZDM to migrate the OKV wallet.

As prerequisite, the `$OKV_HOME` location should be inside the `wallet_root` folder, pointing to `<wallet_root>/okv`. If the `$OKV_HOME` location is in a different folder, you can set the `ZDM_SRC_DB_OKV_HOME` and `ZDM_TGT_DB_OKV_HOME` parameters in the RSP file to specify `$OKV_HOME` for the respective source and target database. ZDM will validate that `$OKV_HOME` contains the `bin/okvutil` utility for downloading and uploading the OKV wallets.

There are two options to specify the OKV endpoint passwords to the ZDM migration job:

- If OKV endpoint password and the TDE wallet password are different, provide the `-okvkeystorepasswd` input parameter to specify the OKV endpoint password in the source DB or provide the `-tgtokvkeystorepasswd` input parameter to specify the OKV endpoint password in the target DB.
- If OKV endpoint password and the TDE wallet password are the same, provide the `-tdekeystorepasswd` input parameter to specify the OKV endpoint password in the source DB or provide the `-tgttdekeystorepasswd` input parameter to specify the OKV endpoint password in the target DB.

ZDM will download or upload the keys from/to the default OKV wallet configured for the endpoint. If you need to download the wallet from a non-default wallet, provide the `ZDM_SRC_DB_OKV_VIRTUAL_WALLET_NAME` parameter in the RSP file to specify the correct OKV wallet from which ZDM will download the keys.

If you need to upload the keys to a wallet other than the default, provide the `ZDM_TGT_DB_OKV_VIRTUAL_WALLET_NAME` parameter in the RSP file to specify the correct OKV wallet where ZDM will upload the keys.

OKV: Oracle Key vault is a full-stack, security-hardened software appliance built to centralize the management of keys and security objects within the enterprise.

4.20 Migration Using PDB Clone

You can migrate an Oracle database using Pluggable Database (PDB) cloning in a streamlined approach that leverages Oracle's multi-tenant architecture. This method involves cloning either a PDB from a source CDB or a non-CDB into a target CDB, where the target PDB can be refreshed periodically to keep it up-to-date, allowing for a flexible and efficient migration process. Depending on the allowed downtime, you can select one of the three PDB clone methods.

Note

Refreshable PDB using switchover requires matching credentials and database link.

You can either use the steps listed in **Migration, Upgrade, and Conversion of a Non-CDB to a PDB Database** or refer to the **Migration Using PDB Clone**.

Select the first option if you have larger databases and it uses RMAN method for backup and restore.

However, you can select the second option as you can migrate a single container at once over DBLINK. The following two options are two available:

- Offline PDB clone methods create a point-in-time PDB copy of a source PDB. Set `MIGRATION_METHOD=OFFLINE_PHYSICAL` to use any of the offline PDB clone methods:
 - **Cold Clone PDB**
 - * Best for backups or when a precise point-in-time is needed and no source database activity is required.
 - * The PDB must be in read-only mode.
 - * Oracle Database 12.1.0.2 or higher is required.
 - * Set `ZDM_PDB_CLONE_METHOD=COLD` to use this method.
 - **Hot Clone PDB**
 - * The source and target platforms must share the same endianness.
 - * Requires both source CDB and target CDB to be in ARCHIVELOG mode and have LOCAL UNDO enabled.
 - * The database options on the source platform must either match or be a subset of those on the target platform.
 - * Creates up-to-date copy of a PDB without stopping user activity.
 - * The source PDBs can remain in read-write mode during the cloning.
 - * Oracle Database 12.2 or higher is required.
 - * Set `ZDM_PDB_CLONE_METHOD=HOT` to use this method.

Note

A database link is required at the target CDB pointing to the source PDB or to the non-CDB for the cloning (created automatically by ZDM).

- Online PDB Clone method creates a PDB copy that can be continuously updated with redo data from the source PDB or from the source non-CDB. Set `MIGRATION_METHOD=ONLINE_PHYSICAL` to use the online PDB clone method:
Refreshable PDB clone:
 - The source and target platforms must share the same endianness.
 - Requires both source CDB and target CDB to be in ARCHIVELOG mode and have LOCAL UNDO enabled.
 - The database options on the source platform must either match or be a subset of those on the target platform.
 - Provides near-real-time replica of a source PDB that can be automatically updated.
 - Requires source PDB to be in read-write mode.
 - Oracle Database 12.2 or higher is required.
 - Set `ZDM_PDB_CLONE_METHOD=REFRESHABLE` to use this method.

- The refresh interval can set using `ZDM_PDB_REFRESH_INTERVAL=<interval in minutes>`. By default, the refresh interval is 60 minutes.
- A database link is required at the target CDB pointing either to the source PDB or to the non-CDB for the cloning (created automatically by ZDM).
- PDB switchover is also supported from Oracle Database 18c. You can enable it by setting `ZDM_SWITCHOVER=TRUE`.

Note

Key considerations for Refreshable PDB clone using switchover:

- Oracle Database 18c or higher is required.
- A Secure External Password Store (SEPS) wallet is required at the source CDB. See the **Setting up the SEPS Wallet** section for information about SEPS wallet setup.
- A database link is required at the source CDB pointing to the target CDB. The source database link name must share the same name and credentials with the target CDB database link. Both the database links are created automatically by ZDM.

All the supported PDB clone methods use a database link to copy the database files during the cloning. For any PDB clone method set `DATA_TRANSFER_MEDIUM=DBLINK`.

Once the PDB clone method has been selected, you must specify both the source and the target PDB names:

- `ZDM_SRC_PDB_NAME`: Name of the source PDB. For non-CDB, leave this parameter blank.
- `ZDM_TGT_PDB_NAME`: Name of the new target PDB to be cloned.

A new phase `ZDM_CLONE_PDB_TGT` is also introduced for this functionality along with the following new parameter: `ZDM_PDB_CLONE_METHOD`.

By default, ZDM creates a database link at the target CDB pointing to the source database using TCP protocol. Provide an existing database link by setting the `ZDM_TGT_DBLINK_NAME=<name of the existing database link>` parameter.

ZDM also creates the credentials used by the database link. For Hot, Cold and Refreshable PDB clone methods, the user is created at the source PDB or at the non-CDB. For Refreshable PDB clone method using switchover, a common user is created at the source CDB or a regular user is created at the non-CDB.

Provide the existing credentials to be used by the database link created by ZDM.

`ZDM_TGT_DBLINK_USERNAME=<database username>`

`ZDM_TGT_DBLINK_PASSWORD_WALLET=<absolute path of the wallet containing the password>`

For Refreshable PDB clone method using switchover, by default ZDM creates a second database link at the source CDB pointing to the target CDB. When you enter an existing database link for the target database and if there is no matching database link for the source database then the credentials are required for ZDM to create the second database link. Database link credentials are provided using the `ZDM_TGT_DBLINK_USERNAME` and `ZDM_TGT_DBLINK_PASSWORD_WALLET` parameters.

Database user creation for Cold, Hot, and Refreshable PDB clone methods:

```
ALTER SESSION SET CONTAINER = <source_pdb>;
CREATE USER <pdb_clone_user> IDENTIFIED BY <secure_password>;
GRANT CREATE SESSION, SET CONTAINER, CREATE PLUGGABLE DATABASE TO
<pdb_clone_user>;
```

Database user creation for Refreshable PDB clone method using switchover:

```
CREATE USER c##<pdb_clone_user> IDENTIFIED BY <secure_password>;
GRANT CREATE SESSION, RESOURCE, CREATE ANY TABLE, UNLIMITED TABLESPACE,
CREATE PLUGGABLE DATABASE, SYSOPER TO c##<pdb_clone_user>;
```

Database link creation:

```
CREATE DATABASE LINK ZDM_DBLINK CONNECT TO <pdb_clone_user> IDENTIFIED BY
<secure_password> USING '<TNS alias pointing to the database>';
SELECT count(*) FROM dual@ZDM_DBLINK;
```

Key considerations:

- Source database: The PDB clone can be either from a PDB or from a non-CDB. When the source database is a non-CDB, ZDM automatically handles the non-CDB to PDB conversion.
- Database version: The source database version can be lower than the target CDB version. When direct upgrade is supported between the source database and the target CDB, ZDM automatically handles the PDB upgrade by leveraging Oracle AutoUpgrade Tool. See the Table 2 to check if direct upgrade is supported by your specific scenario. If direct upgrade is not supported for your source database release and the required target CDB release, you can upgrade to an intermediate database release that is supported for direct upgrade.
- Character sets: If the character set of the CDB to which the PDB is being cloned is not AL32UTF8, then the source and target must have compatible character sets and national character sets.
- If the source PDB has encrypted data or a TDE master encryption key has been set, you must provide the target keystore password using the `-tgttdekeystorepasswd` CLI parameter.

Note

ZDM re-keys the master encryption key of the cloned PDB during the `ZDM_POST_DATABASE_OPEN_TGT` phase as it will eventually follow its own course and have its own data and security policies.

Note

PDB clone method represents an alternative method to the unplug or plug method (already supported by ZDM) for non-CDB to PDB migration.

Comparison between PDB clone methods

Clone Type	Required Source Mode	Minimum Required Database Version	Allow Updates
Cold	Read-Only	12.1.0.2	No
Hot	Read-Write	12.2	No
Refreshable	Read-Write	12.2	Yes
Refreshable + Switchover	Read-Write	18	Yes

Supported Direct Upgrade Paths

Source Oracle Database version	Target Oracle Database version
12.1.0.1, 12.1.0.2, 11.2.0.3 or later	12.2
12.2.0.1, 12.1.0.1, 12.1.0.2, 11.2.0.3, 11.2.0.4	18c
18c (all releases), 12.2.0.1, 12.1.0.2, 11.2.0.4	19c
19c (all releases), 18c (all releases), 12.2.0.1	21c
21c, 19c (all releases)	26ai

4.21 Setting up the SEPS Wallet

The refreshable PDB along with switchover use case requires you to configure the Secure External Password Store (SEPS) wallet in the source CDB.

Perform the following steps:

1. Query the wallet root directory:

```
SQL> show parameter root
```

NAME	TYPE	VALUE
wallet_root	string	/var/opt/oracle/dbaas_acfs/db/wallet_root/

2. Create the SEPS wallet directory:

```
$ mkdir /var/opt/oracle/dbaas_acfs/db/wallet_root/tde_seps
```

3. Set the `EXTERNAL_KEYSTORE_CREDENTIAL_LOCATION` parameter:

```
SQL> alter system set EXTERNAL_KEYSTORE_CREDENTIAL_LOCATION = '/var/opt/oracle/dbaas_acfs/db/wallet_root/tde_seps' scope=spfile;
```

4. Bounce the database:

```
SQL> shutdown immediate;
SQL> startup;
```

5. Create the SEPS wallet:

```
SQL> administer key management ADD SECRET '<Source TDE keystore password>'
for client 'TDE_WALLET' using TAG 'TDE keystore password' to auto_login
keystore '/var/opt/oracle/dbaas_acfs/db/wallet_root/tde_seps';
```

Preparing for a Logical Database Migration

The following topics describe how to complete the Zero Downtime Migration prerequisites before running a logical database migration job.

5.1 Best Practices for a Logical Database Migration

The following best practices are recommended for a logical database migration.

Source database workload and activity

- During the migration job it is recommended that your database avoid Data Definition Language (DDL) operations to provide the most optimal environment for fast database replication. When DDL is replicated, Oracle GoldenGate Replicat serializes data to ensure that there are no locking issues between DML and DDL on the same objects. See Data Replication for details.
- Patching and Upgrade operations are not recommended during migration as they can result in lot of DDL operations
- During the migration period, to provide the most optimal environment for fast database replication, avoid large batch DML operations. Running large batch operations, like a single transaction that affects multimillion of rows, can slow down replication rates.
- You can specify ZDM parameters `GOLDENGATESETTINGS_EXTRACT_WARNLONGTRANS_DURATION` and `GOLDENGATESETTINGS_EXTRACT_WARNLONGTRANS_CHECKINTERVAL` to generate GoldenGate Extract warnings for long running transactions.
- ZDM sets parameter `SPLIT_TRANS_RECS` for GoldenGate Replicat.

Source database configuration

- Apply recommended/required Oracle GoldenGate and RDBMS patches. See [Oracle GoldenGate -- Oracle RDBMS Server Recommended Patches \(Doc ID 1557031.1\)](#) and [Latest GoldenGate/Database \(OGG/RDBMS\) Patch recommendations \(Doc ID 2193391.1\)](#) for details.
 - Enable `ARCHIVELOG` mode
 - Enable `FORCE LOGGING`
 - Enable database minimal supplemental logging
 - Set `STREAMS_POOL_SIZE` to at least 2GB
- See [Source Database Prerequisites for Logical Migration](#) for details.

Source tables uniqueness

- Oracle GoldenGate requires a unique row identifier on the source and target tables to locate the correct target rows for replicated updates and deletes.

This is usually considered with primary key or unique key indexes. If there are tables identified that do not have any such keys, GoldenGate must construct a pseudo key that contains all of the allowable columns in the table, excluding virtual columns, UDTs,

function-based columns, extended (32K) VARCHAR2/NVARCHAR2 columns, and any columns that are explicitly excluded from the Oracle GoldenGate configuration by an Oracle GoldenGate user.

However, constructing a key from all of the columns will significantly impede the performance of Oracle GoldenGate.

If the source database is version Oracle Database 12g (12.2) or later, use the data dictionary view DBA_GOLDENGATE_NOT_UNIQUE to identify all of the tables that do not have a primary key or non-null unique columns.

- See [Ensuring Row Uniqueness in Source and Target Tables](#) for details.

MAX_STRING_SIZE

- If source database is configured with MAX_STRING_SIZE=STANDARD, then set MAX_STRING_SIZE=STANDARD for the target database.
- See [MAX_STRING_SIZE](#) for details.

Source database server CPU and memory requirements

If there are enough FREE CPU resources on the source system, set ZDM configuration parameter

GOLDENGATESETTINGS_EXTRACT_PERFORMANCEPROFILE = HIGH. Else, set ZDM configuration parameter GOLDENGATESETTINGS_EXTRACT_PERFORMANCEPROFILE = LOW-RES

GOLDENGATESETTINGS_EXTRACT_PERFORMANCEPROFILE = HIGH

Resource usage on source system:

- OCPUs: up to 3 (6 vCPUs)
- RAM: 3 GB (SGA steam pool)

GOLDENGATESETTINGS_EXTRACT_PERFORMANCEPROFILE = LOW

Resource usage on source system:

- OCPUs: up to 2 (4 vCPUs)
- RAM: 16.8MB (SGA stream pool)

Target database server CPU and memory requirements

Use ZDM parameter GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE to tune Oracle GoldenGate Replicat. Setting performance profile automatically configures relevant parameters to achieve the desired throughput and latency. ZDM defaults to HIGH.

GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE = HIGH

Replicat Appliers = 2 * CPU_COUNT of target database

GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE = LOW

Replicat Appliers = CPU_COUNT of target database / 2

Oracle GoldenGate server CPU requirements

OCPUs for GoldenGate server = $\text{ceil}(((\#replicat_appliers^1 / 2) + \#vCPU_extract^2 + \#vCPU_OS^3) / 2)$

¹#replicat_appliers: number of GoldenGate Replicat Appliers configured using ZDM parameter GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE

²#vCPU_extract: based on ZDM parameter

GOLDENGATESETTINGS_EXTRACT_PERFORMANCEPROFILE

³#vCPU_OS: used for Operating System resources management (set to 2 vCPUs)

Example:

When:

- GOLDENGATESETTINGS_EXTRACT_PERFORMANCEPROFILE= HIGH
- GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE = HIGH
- Target DB CPU_COUNT = 5

#vCPU_extract = 6

#replicat_appliers = 10

#vCPU_OS = 2

then,

OCPUs for GG server = $\text{ceil}(6.5) = 7$

See [Oracle Zero Downtime Migration – Logical Migration Performance Guidelines](#) for details.

Oracle GoldenGate server trail file storage space requirement

The space required depends upon the selected size of the trails, the amount of data being captured for replication, and how long the consumed trails are kept on the disk. The recommended minimum disk allocated for trails is computed as:

((transaction log size * 0.33) * number of log switches per day) * number of days to retain trails

For example, if the transaction logs are 1GB in size and there is an average of 10 log switches per day, it means that Oracle GoldenGate will capture 3.3GB data per day. To be able to retain trails for 7 days, the minimum amount of disk space needed to hold the trails is 23GB. See [Other Disk Space Considerations](#) for details.

GGADMIN users in non-ADB source and target databases

Create a GoldenGate administration user, `ggadmin`, in source database granting all of the permissions listed in the example. If the source database is multitenant (CDB), create the user in the source PDB, as shown in this example.

```
SQL> create user ggadmin identified by password
defaulttablespace users temporary tablespace temp;
SQL> grant connect, resource to ggadmin;
SQL> alter user ggadmin quota 100M ON USERS;
SQL> grant unlimited tablespace to ggadmin;
SQL> grant select any dictionary to ggadmin;
SQL> grant select any table to ggadmin;
SQL> grant create view to ggadmin;
SQL> grant execute on dbms_lock to ggadmin;
SQL> exec dbms_goldengate_auth.GRANT_ADMIN_PRIVILEGE('ggadmin');
```

If the source database is multitenant (CDB), also create user `c##ggadmin` in `CDB$ROOT` as shown in this example:

```
SQL> create user c##ggadmin identified by password defaulttablespace
userstemporary tablespace temp;
SQL> alter user c##ggadmin quota 100M ON USERS;
SQL> grant unlimited tablespace to c##ggadmin;
SQL> grant connect, resource to c##ggadmin container=all;
SQL> grant select any dictionary to c##ggadmin container=all;
SQL> grant select any table to ggadmin;
SQL> grant create view to c##ggadmin container=all;SQL> grant set container
to c##ggadmin container=all;
SQL> grant execute on dbms_lock to c##ggadmin container=all;
SQL>
execdbms_goldengate_auth.GRANT_ADMIN_PRIVILEGE('c##ggadmin',container=>'all');
SQL> create user c##ggadmin identified by password
```

If the target database is not an Autonomous Database, create a GoldenGate administration user, `ggadmin`, in the target database granting all of the permissions listed in the example. If the target database is multitenant (CDB), create the user in the target PDB, as shown in this example.

```
SQL> create user ggadmin identified by password default tablespace users
temporary tablespace temp;
SQL> grant connect, resource to ggadmin;
SQL> alter user ggadmin quota 100M ON USERS;
SQL> grant unlimited tablespace to ggadmin;
SQL> grant select any dictionary to ggadmin;
SQL> grant create view to ggadmin;
SQL> grant select any table to ggadmin;
SQL> grant insert any table to ggadmin;
SQL> grant update any table to ggadmin;
SQL> grant delete any table to ggadmin;
SQL> grant comment any table to ggadmin;
SQL> grant execute on dbms_lock to ggadmin;
SQL> exec dbms_goldengate_auth.GRANT_ADMIN_PRIVILEGE('ggadmin');
```

Network connectivity requirements

- Additional Connectivity Prerequisites for Oracle GoldenGate Hub
- Zero Downtime Migration Port Requirements

Application switchover

Handling Application Switchover in a Logical Migration

5.2 Source Database Prerequisites for Logical Migration

During the migration job it is recommended that your database avoid Data Definition Language (DDL) operations to provide the most optimal environment for fast database replication. When DDL is replicated, Oracle GoldenGate Replicat serializes data to ensure that there are no locking issues between DML and DDL on the same objects.

Table 5-1 List of the required patches per use case at the source database

Patch	Feature	Description
Oracle GoldenGate -- Oracle RDBMS Server Recommended Patches (Doc ID 1557031.1)	Oracle GoldenGate -- Oracle RDBMS Server Recommended Patches	Recommended/Required for source databases when GoldenGate is being used.
Latest GoldenGate/Database (OGG/RDBMS) Patch recommendations (Doc ID 2193391.1) ,	Latest GoldenGate/Database (OGG/RDBMS) Patch recommendations. It lists the additional RDBMS patches needed on top of the latest DBBP/RU for Oracle Database 12c and later.	Recommended/Required for source databases when GoldenGate is being used.
Database PSU 11.2.0.4.210720	Includes a fix for Oracle GoldenGate performance bug 28849751 - IE PERFORMANCE DEGRADES WHEN NETWORK LATENCY BETWEEN EXTRACT AND CAPTURE IS MORE THAN 8MS	For Oracle Database 11.2.0.4 source databases
OGG RDBMS patch 32248879 MERGE REQUEST ON TOP OF DATABASE PSU 11.2.0.4.201020 FOR BUGS 32048478 20448066	This patch contains mandatory fix for Oracle GoldenGate Microservices bug 20448066 DBMS_XSTREAM_GG APIS SHOULD BE ALLOWED FOR SCA PROCESSES	For Oracle Database 11.2.0.4 source databases
RDBMS patch for bug 29374604	Integrated Extract not starting against Oracle RDBMS Standard Edition	If the source is Oracle Database Standard Edition 2 available with Oracle Database 18c or Oracle Database 19c and is lower than DBRU 19.11
Patch 20448066	DBMS_XSTREAM_GG APIS SHOULD BE ALLOWED FOR SCA PROCESSES	For Oracle Database 12.1.0.2 source databases
Perl patch 5.28.2 or later	ZDM service host requires Perl to run the install script	Required for Oracle Database 11.2.0.4 source databases

Complete the following prerequisites on the source database to prepare for a logical migration.

Offline and Online Migrations Require:

- The character set on the source database must be the same as the target database.
- Configure the streams pool with the initialization parameter `STREAMS_POOL_SIZE`.

For offline logical migrations, for optimal Data Pump performance, it is recommended that you set `STREAMS_POOL_SIZE` to a minimum of 256MB-350MB, to have an initial pool allocated, otherwise you might see a significant delay during start up.

For online logical migrations, set `STREAMS_POOL_SIZE` to at least 2GB. See <https://support.oracle.com/epmos/faces/DocumentDisplay?id=2078459.1> for the recommendation 1GB `STREAMS_POOL_SIZE` per integrated extract + additional 25 percent.

- System time of the Zero Downtime Migration service host and source database server should be in sync with your Oracle Cloud Infrastructure target.

If the time on any of these systems varies beyond 6 minutes from the time on OCI, it should be adjusted. You can use `ntp time check` to synchronize the time if NTP is

configured. If NTP is not configured, then it is recommended that you configure it. If configuring NTP is not an option, then you need to correct the time manually to ensure it is in sync with OCI time.

- If you are using a database link, and your target database is on Autonomous Database Shared Infrastructure, you must configure TCPS on the source. Autonomous Database Shared Infrastructure doesn't allow a database link to a source that is not configured with TCPS.
- If you are migrating from an Amazon Web Services RDS environment, see [Migrating from Amazon Web Services RDS to Oracle Autonomous AI Database](#) for information about source environment preparations.
- In the PDB being exported, if you have created local objects in the C## user's schema and you want to import them, then either make sure a common user of the same name already exists in the target CDB instance (for non-Autonomous Database targets) or use the following Zero Downtime Migration parameter to rename the schema on import.

```
DATAPUMPSETTINGS_METADATAREMAPS-1=type:REMAP_SCHEMA,oldValue:c##common_user,
newValue:new_ name
```

- If you are migrating to Oracle Autonomous AI Database on Exadata Cloud@Customer from any on-premises Oracle Database, including existing Exadata Cloud@Customer systems, see [Migrating to Oracle Autonomous AI Database on Exadata Cloud@Customer](#) for additional prerequisite setup tasks.

Online Migrations Require:

- If the source is Oracle Database 11.2, apply mandatory 11.2.0.4 RDBMS patches on the source database.
- If the source is Oracle Database 12.1.0.2 or a later release, apply mandatory RDBMS patches on the source database.
- If the source is Oracle Database 11.2, ensure to exclude SYSMAN user and provide an example.
- Enable ARCHIVELOG mode for the database. See [Changing the Database Archiving Mode](#).
- Enable FORCE LOGGING to ensure that all changes are found in the redo by the Oracle GoldenGate Extract process. See [Specifying FORCE LOGGING Mode](#).
- Enable database minimal supplemental logging. See [Minimal Supplemental Logging](#).

```
SQL> ALTER DATABASE ADD SUPPLEMENTAL LOG DATA;
```

- Enable initialization parameter ENABLE_GOLDENGATE_REPLICATION.
- Install the UTL_SPADV or UTL_RPADV package for Integrated Extract performance analysis.

[Source database version 19c and later](#), see UTL_SPADV

Operational notes: To use this package, you must connect to an Oracle database as an Oracle Replication administrator (for example, ggadmin) and run the utlspadv.sql script in the rdbms/admin directory in ORACLE_HOME.

[Earlier database versions](#), see UTL_SPADV Operational Notes

Operational notes: To use this package, you must connect to an Oracle database as an Oracle Replication administrator (for example, ggadmin) and run the utlspadv.sql script in the rdbms/admin directory in ORACLE_HOME.

- During the migration period, to provide the most optimal environment for fast database replication, avoid large batch DML operations. Running large batch operations, like a single transaction that affects multi-millions of rows, can slow down replication rates. Create, alter, and drop DDL operations are not replicated.
- Set `WALLET_SOURCEADMIN` to specify the path to the directory that contains the auto login wallet file `cwallet.sso`, which provides the source database administrator password. See `WALLET_SOURCEADMIN`.
- For adding large number of `INCLUDEOBJECTS` in Datapump component, create a table in the Source database in the export user schema to list all the `TABLE` objects to be filtered and specify the following parameters. For example, create a table `SYSTEM.INCLUDE_TEMP_LIST` and list all objects specified in `INCLUDEOBJECTS` to be filtered for `SCHEMA SCOTT`:

```
INCLUDEOBJECTS-1=owner:SCOTT
DATAPUMPSETTINGS_METADATAFILTERS-1=name:NAME_EXPR,value:'IN(select OBJECT_NAME
from SYSTEM.INCLUDE_TEMP_LIST)', objectType:TABLE
```

Offline Migrations Require:

- The `DATAPUMP_EXP_FULL_DATABASE` and `DATAPUMP_IMP_FULL_DATABASE` roles are required. These roles are required for Data Pump to determine whether privileged application roles should be assigned to the processes comprising the migration job.

`DATAPUMP_EXP_FULL_DATABASE` is required for the export operation at the source database for the specified database user. The `DATAPUMP_IMP_FULL_DATABASE` role is required for the import operation at the specified target database for specified target database user.

See the Oracle Data Pump documentation for more information.
- Oracle Database Standard Edition 2 does not allow Data Pump dump encryption support so you must encrypt the target database post-migration. To proceed with the migration, set `DATAPUMPSETTINGS_DATAPUMPPARAMETERS_ENCRYPTION =NONE`. See, `DATAPUMPSETTINGS_DATAPUMPPARAMETERS_ENCRYPTION` for more information. So, specify `NONE` if database is Oracle Database Standard Edition 2 and Oracle Advanced Security is not enabled.

Prerequisites when the source database is IBM AIX:

1. Ensure that `CURL` is available if `OSS` is used as the data transfer medium.
2. Ensure that the `id` command is available. See [id Command](#) for more information.

Configuring the `PROFILE` parameter:

Specify the full path to the source database profile file. ZDM maintains a key-value template for each of the supported database `PROFILE`. See [PROFILE](#)

① Note

If you plan to migrate from Oracle Database 11.2.0.4 sources for Zero Downtime Migration to invoke `CPAT` remotely, set the `RUNCPATREMOTELY` parameter to `TRUE` to avoid patching the Perl in the source database host.

5.3 Target Database Prerequisites for Logical Migration

Complete the following prerequisites on the target database to prepare for a logical migration.

Data Pump-only logical migrations require:

- The `DATAPUMP_IMP_FULL_DATABASE` role is required for the import operation at the specified target database for specified target database user.

All logical migrations require:

- The character set on the source database must be the same as the target database.
- System time of the Zero Downtime Migration service host and source database server should be in sync with your Oracle Cloud Infrastructure target.
- All source database requirements be met. Some tasks are performed on both the source and target. See [Source Database Prerequisites for Logical Migration](#)
- Ensure to set the [ENCRYPT_NEW_TABLESPACES](#) parameter which specifies whether to encrypt newly created user tablespaces. Set the parameter to `ALWAYS` to encrypt the tablespace.

Note

For logical migration, if the target is Oracle Database Appliance and the data transfer medium is Object Storage Service (OSS), ensure that OSS connectivity works. Fetch the CA certificates for OCI and update certificate store of Oracle Database Appliance. See [Obtain the Root CA Certificate from Oracle Identity Cloud Service](#) for more information.

Online logical migrations require:

- Disable auto-purge jobs on the target database immediately after instantiation (Data Pump Import). Otherwise, the purge jobs will cause data inconsistency condition on the target database causing GoldenGate Replicat to fail. Some of these jobs will purge data.
 - During the `ZDM_POST_DATAPUMP_TGT` phase, ZDM will disable purge jobs in the target database.
 - ZDM enables the purge jobs in the target database during the `ZDM_POST_SWITCHOVER_TGT` phase.

5.4 Additional Logical Migration Prerequisites

Complete the following additional prerequisites to prepare for a logical migration.

Create an OCI API key pair

See [Required Keys and OCIDs](#) for details.

Configure AWS S3 security credentials

If you are migrating from an Amazon Web Services RDS environment, see [Migrating from Amazon Web Services RDS to Oracle Autonomous Database](#) for information about source environment preparations.

Set Up Data Transfer Media

- To use Object Storage data transfer medium:

Create an Object Store bucket on Oracle Cloud Infrastructure if you are using Object Storage as a data transfer medium. This is not required for Oracle Exadata Database Service on Cloud@Customer or on-premises Exadata Database Machine targets.
- To use NFS shared storage:

Ensure that the NFS is shared between the source and target database server and mapped to the Database Directory object.

For information about how to mount NFS for dump storage, see [Mount Options for Oracle files for RAC databases and Clusterware when used with NFS on NAS devices \(Doc ID 359515.1\)](#).

- To use a database link (DBLINK):

If you are using an **existing** database link between the target database to an on-premises source database by `global_name` of the source database, ensure that the database link is not broken. Zero Downtime Migration can reuse the pre-existing database link for migration if that data transfer medium is configured.

Zero Downtime Migration supports the use of a database link for all Autonomous Database targets; however, when you set up the database link for Autonomous Database Dedicated Infrastructure, you must use the Easy Connect syntax or provide a complete descriptor in the `USING 'connect string'` clause. You cannot use a network service name because the `tnsnames.ora` file is not available for lookup. Database links can only be used for TCP connections because TCPS connections require a wallet.

See [SQL Commands with Restrictions in Autonomous Database](#) and [Create Database Links from Autonomous Database to Oracle Databases](#)

- If you are **not** using a database link for data transfer, ensure that the file system used for the Data Pump export directory has sufficient space to store Data Pump dump files.
- To use Amazon S3 bucket:

See [Setting Up S3 Bucket Data Transfer Medium](#)

If the source uses self-signed database server certificates:

If the source database listener is configured with TLS (TCPS) using self-signed database server certificates, then ensure that the self-signed certificate is added to the Zero Downtime Migration home cert store as follows.

```
keytool -import -keystore ZDM_HOME/jdk/jre/lib/security/cacerts -trustcacerts
-alias "src ca cert" -file source_db_server-certificate
```

Online Migration Additional Prerequisites

For online migration, do the following additional prerequisite tasks:

- **Set up an Oracle GoldenGate Microservices hub:**

For Oracle Database Cloud Services targets, deploy the "Oracle GoldenGate for Oracle - Database Migrations" image from Oracle Cloud Marketplace.:

The "Database Migrations" version of the Oracle GoldenGate Marketplace image provides limited free licensing for use with OCI Database Migration Service. See the license agreement for details.

Any other use of GoldenGate requires purchasing a license for the Oracle GoldenGate product. See the Oracle GoldenGate documentation for more information.

1. Log in to Oracle Cloud Marketplace.
2. Search for the "Oracle GoldenGate for Oracle - Database Migrations" Marketplace listing.
3. From the Marketplace search results, select the "Oracle GoldenGate for Oracle - Database Migrations" listing.

4. For instructions to deploy the Marketplace listing, see [Deploying Oracle GoldenGate Microservices on Oracle Cloud Marketplace](#).

Note

The above step is applicable only if you are migrating Oracle Database 11g or Oracle Database 12c to Oracle Database 19c.

5. For instructions to deploy the Marketplace listing for migrations between Oracle Database 19c to Oracle Database 19c or Oracle Database 19c to Oracle AI Database 26ai, see [Deploying Oracle GoldenGate Microservices on Oracle Cloud Marketplace](#).

For guidance in configuring Zero Downtime Migration GoldenGate settings and choosing the correct GoldenGate Hub shape, see Oracle MAA technical brief, [Oracle Zero Downtime Migration – Logical Migration Performance Guidelines](#).

If you are migrating to Exadata Cloud@Customer, or any on-premises Oracle Exadata Database Machine, you must use an on-premises Oracle GoldenGate Microservices instance to create a deployment for the source and target. The “Oracle GoldenGate for Oracle – Database Migrations” marketplace offering now contains a downloadable docker image for migrations to ExaCC. You can review the latest marketplace VM at https://cloudmarketplace.oracle.com/marketplace/en_US/listing/96175416, and the documentation for this functionality can be found at [Migrating to Exadata Cloud@Customer Using Oracle Zero Downtime Migration](#).

By default, Oracle GoldenGate deployment endpoints are configured using self-signed HTTPS certificate. Either of the following options are available:

- Specify the GOLDENGATEHUB_ALLOWSELSIGNEDCERTIFICATE parameter to TRUE in response file to indicate that ZDM can trust the self-signed HTTPS certificate.
 - Update the configuration for Oracle GoldenGate deployment to use a certificate issued by a trusted Certificate Authority.
- **Create a GoldenGate administration user:**

Note that the examples shown below are for basic migrations. For comprehensive Oracle GoldenGate permissions information, see [Granting the Appropriate User Privileges](#) in *Using Oracle GoldenGate with Oracle Database*.

- On the Source Database:
 - * Create a GoldenGate administration user, ggadmin, granting all of the permissions listed in the example. If the source database is multitenant (CDB), create the user in the source PDB, as shown in this example.

```
SQL> create user ggadmin identified by password
      default tablespace users temporary tablespace temp;
SQL> grant connect, resource to ggadmin;
SQL> alter user ggadmin quota 100M ON USERS;
SQL> grant unlimited tablespace to ggadmin;
SQL> grant select any dictionary to ggadmin;
SQL> grant create view to ggadmin;
SQL> grant execute on dbms_lock to ggadmin;
SQL> exec dbms_goldengate_auth.GRANT_ADMIN_PRIVILEGE('ggadmin');
```

- * If the source database is multitenant (CDB), also create user `c##ggadmin` in `CDB$ROOT` as shown in this example.

```
SQL> create user c##ggadmin identified by password default
tablespace users
temporary tablespace temp;
SQL> alter user c##ggadmin quota 100M ON USERS;
SQL> grant unlimited tablespace to c##ggadmin;
SQL> grant connect, resource to c##ggadmin container=all;
SQL> grant select any dictionary to c##ggadmin container=all;
SQL> grant create view to c##ggadmin container=all;
SQL> grant set container to c##ggadmin container=all;
SQL> grant execute on dbms_lock to c##ggadmin container=all;
SQL> exec
dbms_goldengate_auth.GRANT_ADMIN_PRIVILEGE('c##ggadmin',container=>'
all');
```

– On the Target Database:

- * If the target is Autonomous Database, unlock the pre-created `ggadmin` user.
- * If the target is not Autonomous Database, create a `ggadmin` user in the target PDB as shown in the above examples. This user is similar to the `ggadmin` user on the source database. Grant the following additional privileges:

```
SQL> grant select any table to ggadmin;
SQL> grant insert any table to ggadmin;
SQL> grant update any table to ggadmin;
SQL> grant delete any table to ggadmin;
```

See [Establishing Oracle GoldenGate Credentials](#) for information about privileges required for a "Replicat all modes" user.

- Regardless of migration mode (FULL or SCHEMA or TABLE), ZDM enforces the following privileges for `ggadmin` user in the target database for DML replication:

```
grant select any table to ggadmin;
grant insert any table to ggadmin;
grant update any table to ggadmin;
grant delete any table to ggadmin;
```

- Similarly, in case of DDL replication, ZDM enforces the following privileges for `ggadmin` user in the target database:

```
GRANT CREATE ANY TABLE to GGADMIN;

GRANT ALTER ANY TABLE to GGADMIN;

GRANT DROP ANY TABLE to GGADMIN;

GRANT CREATE ANY INDEX to GGADMIN;

GRANT ALTER ANY INDEX to GGADMIN;

GRANT DROP ANY INDEX to GGADMIN;
```

```
GRANT CREATE ANY VIEW to GGADMIN;
```

```
GRANT ALTER ANY VIEW to GGADMIN;
```

```
GRANT DROP ANY VIEW to GGADMIN;
```

```
GRANT CREATE ANY PROCEDURE to GGADMIN;
```

```
GRANT ALTER ANY PROCEDURE to GGADMIN;
```

```
GRANT DROP ANY PROCEDURE to GGADMIN;
```

- To replicate tables with Oracle GoldenGate `support_mode = ID KEY`, the following privileges are required for `ggadmin` user in the source database. See [Setting Flashback Query](#) for more information.

```
GRANT FLASHBACK ANY TABLE TO ggadmin;
```

- **If the source database is configured to use SSL/TLS:**

If the source database is configured to use SSL/TLS, then ensure that the wallet containing certificates for TLS authentication is located in directory `/u02/deployments/deployment_name/etc` on the GoldenGate instance.

- **If Oracle Database Vault is enabled in the source or target database:**

If you want to use Oracle GoldenGate in an Oracle Database Vault environment in the source or target database, then you must have the appropriate privileges granted for an Oracle GoldenGate account.

See [Privileges for Using Oracle GoldenGate with Oracle Database Vault](#) for more information.

- **If the target database is configured to use SSL/TLS:**

Ensure that the wallet containing certificates for TLS authentication is located in the correct location on the GoldenGate instance, as follows:

- For an Autonomous Database, the wallet file should be located in directory `/u02/deployments/deployment_name/etc/Wallet_<adbname>` path or `/u02/deployments/deployment_name/etc/adb`. The new path is an alternate to use the Oracle GoldenGate for concurrent migration to two different targets.
- For a co-managed database, the wallet file should be located in directory `/u02/deployments/deployment_name/etc/Wallet_<dbname>`

Autonomous databases are always configured to use TLS.

- **If GoldenGate schema name is different from the default value `ggadmin`:**

ZDM supports GoldenGate schema name different from default value other than `ggadmin`. By default, GoldenGate deployment is configured with `GGSCHEMA= ggadmin` in the `GLOBALS` file. You can specify a different GoldenGate schema name for source (PDB, CDB) and target. If you specify a different GoldenGate schema name, then you will need to update the `GLOBALS` file.

- **Dynamic Export Parallelism for online logical migration**

In some cases, GoldenGate replication from source to target is unsuccessful due to `INSTANTIATION_SCN MISMATCH` between `DBA_APPLY_INSTANTIATED_SCHEMAS` and `DBA_APPLY_INSTANTIATED_OBJECTS`. As a solution, ZDM limits initial parallelism for Data

Pump jobs to 1, until the `SCHEMA/PROCACT_SCHEMA` path is processed. Subsequently, ZDM adjusts the parallelism to the expected level for the remaining data export.

- **Connecting to OCI through proxy server**

When ZDM server requires to access OCI REST endpoints through `HTTP_PROXY`, import the HTTP PROXY server certificate to the ZDM server `$ZDM_HOME/jre/lib/security/cacerts` using the `ZDM_HOME/jdk/bin/keytool` binary.

- **Source and target database requirements for Oracle AI Database 26ai**

For database versions earlier than Oracle AI Database 26ai, continue granting privileges as follows:

```
SQL> exec dbms_goldengate_auth.GRANT_ADMIN_PRIVILEGE('ggadmin');
```

However, for Oracle AI Database 26ai, grant the following roles for source and target:

```
Source ggadmin: grant OGG_CAPTURE to ggadmin;
```

```
Target ggadmin: grant OGG_APPLY to ggadmin;
```

- **Source and target database requirements for non Autonomous databases**

Ensure to have the supported default shell as `bash`. If this is not the case, then you might get the following error: `ZDM_VALIDATE_SRC` fails with `PRCZ-2103 : Failed to execute command "/usr/bin/id" LANG=en_US.UTF-8`.

This is the issue with default shell being `cshell` and not `bash`. On `cshell`, the environment parameters are not recognized so all the commands with environments will fail.

- **If the version of the target database is earlier than Oracle Database 19c (19.18)**

You require Bug 34677088 if the version of the non-ADB target database is earlier than Oracle Database 19c (19.18) to avoid the following error:

```
ORA-43853: SECUREFILE LOBs (Large Objects) cannot be used in non-automatic segment space management tablespace
```

During import, ZDM applies the transform parameter `LOB_STORAGE` to `SECUREFILE` and if the target tablespace is not `ASSM`, then import can fail with `ORA-43853: SECUREFILE LOBs (Large Objects) cannot be used in non-automatic segment space management tablespace`.

If you cannot apply BLR for Bug 34677088 in the target database, then set `DATAPUMPSETTINGS_SECUREFILELOB` to `FALSE`. However, the action makes all other objects (present in `ASSM` tablespaces) to not get transformed to secure LOB.

- Ensure that `/tmp` is mounted with `execute` permission as a prerequisite for the source and target databases if you want to perform a logical migration with host SSH access.
- If you do not specify SSH details for the source or target database in FSS or NFS based migration, instead of generating an error due to missing database server access details, ZDM validates the shared directory path between the source and target databases by creating a validation file in the source database node and by checking the readability of same file in the target database node or vice-versa.
- Now `event_table` is used in the source and target databases for you to indicate if migration is complete using Database Migration Service provided API.

Database Migration Service inserts a record in the event table and ZDM monitors Replicat until it stops after receiving the transaction record in the event table. Once the event is triggered and Replicat is down, ZDM ensures the same values are found in the source and target databases and ZDM checks replication log information to confirm if the Replicat was stopped by the `EVENTACTION`. Then ZDM stops Extract and finally Database Migration Service drops events data in the source and target databases.

Note

Currently, online logical migration is not supported for Autonomous AI Database target with Lakehouse workload type.

5.4.1 Additional Connectivity Prerequisites for Oracle GoldenGate Hub

To perform online logical migrations with Oracle GoldenGate, in addition to the connectivity between the Zero Downtime Migration service host and the source and target database servers, you must also ensure connectivity between the Oracle GoldenGate hub and the source and target database servers.

Ensure that the OCI network security rules allow the following connections.

Table 5-2 Prerequisite Connections for Online Logical Migration

Initiator	Target	Protocol	Port	Purpose
GoldenGate hub	Source database	TCP TCPS	1521 User-defined	SQL*Net
GoldenGate hub	Target database	TCP TCPS	1521 1522 for ADB- Serverless, port 2484 for ADB- Dedicated, or user- defined for non- ADB	SQL*Net
ZDM server	GoldenGate hub	HTTPS	443	Oracle GoldenGate Microservice REST API calls

The Zero Downtime Migration server should be allowed to make HTTPS over port 443 calls to an OCI REST endpoint.

5.4.2 Validating Connections to and from the Oracle GoldenGate Marketplace Instance

1. From Zero Downtime Migration server to Oracle GoldenGate server.

On Zero Downtime Migration server, run

```
curl -v --insecure -u oggadmin_username https://ogg_instance_fqdn_or_ip/
services/v2/deployments
```

Oracle GoldenGate server credentials can be found in `/home/opc/ogg-credentials.json` on the GoldenGate server.

2. From Oracle GoldenGate server to source database server.

Assuming that the source database listener is not TLS/SSL enabled, on the Oracle GoldenGate server, run

```
export LD_LIBRARY_PATH=/u01/app/ogg/lib:/u01/app/ogg/lib/instantclient
/u01/app/ogg/lib/instantclient/sqlplus
```

```
username@'source_listener_hostname_or_ip:source_listener_port/  
source_db_service_name'
```

Note

This is applicable only for Oracle GoldenGate 21c and higher versions.

3. From Oracle GoldenGate server to target database server

If the target database is an Autonomous Database, refer to "Online Migration Additional Prerequisites" at [Additional Logical Migration Prerequisites](#), and ensure that the Autonomous Database wallet containing certificates for TLS authentication exists in the correct location on the Oracle GoldenGate instance.

On Oracle GoldenGate server, run

```
export LD_LIBRARY_PATH=/u01/app/ogg/lib:/u01/app/ogg/lib/instantclient  
/u01/app/ogg/lib/instantclient/sqlplus username@'tcps://  
adb_listener_hostname_or_ip:adb_listener_port/adb_service_name?  
wallet_location=dir_path&ssl_server_cert_dn=cert_dn'
```

Refer to [Connect SQL*Plus with TLS Authentication](#) for more details about connecting to an Autonomous Database using SQL*Plus.

If the target database is not an Autonomous Database and is not TLS/SSL enabled, on the Oracle GoldenGate server, run

```
export LD_LIBRARY_PATH=/u01/app/ogg/lib:/u01/app/ogg/lib/instantclient  
/u01/app/ogg/lib/instantclient/sqlplus  
username@'target_listener_hostname_or_ip:target_listener_port/  
target_db_service_name'
```

Note

This is applicable only for Oracle GoldenGate 21c and higher versions.

5.4.3 Validating Connections to and from an Oracle GoldenGate Docker Deployment

1. From Zero Downtime Migration server to Oracle GoldenGate deployment.

On Zero Downtime Migration server, run

```
curl -v --insecure -u oggadmin_username https://ogg_deployment_fqdn_or_ip/  
services/v2/deployments
```

2. From Oracle GoldenGate deployment to source database server.

As an ogg user inside the docker container, run

```
export ORACLE_HOME=/u01/ogg/lib/instantclient  
$ORACLE_HOME/bin/sqlplus
```

```
username@'source_listener_hostname_or_ip:source_listener_port/  
source_db_service_name'
```

3. From Oracle GoldenGate server to target database server

As an ogg user inside the docker container, run

```
export ORACLE_HOME=/u01/ogg/lib/instantclient  
export LD_LIBRARY_PATH=/u01/ogg/lib/instantclient  
$ORACLE_HOME/  
sqlplususername@'target_listener_hostname_or_ip:target_listener_port/  
target_db_service_name'
```

5.5 Setting Logical Migration Parameters

Set the required logical migration response file parameters. Get the response file template, `$ZDM_HOME/rhp/zdm/template/zdm_logical_template.rsp`, which is used to create your Zero Downtime Migration response file for the database migration procedure, and edit the file as described here.

The logical migration response file settings are described in detail in [Zero Downtime Migration Logical Migration Response File Parameters Reference](#).

The following parameters are required for an offline or online logical migration:

- **MIGRATION_METHOD:** Set to `ONLINE_LOGICAL` for online migration with GoldenGate or `OFFLINE_LOGICAL` for an offline Data Pump transfer.

- **DATA_TRANSFER_MEDIUM:** Set to

OSS for Object Storage bucket

NFS for a shared Network File System

DBLINK for a direct transfer using a database link

COPY to use secure copy

AMAZONS3 to use an Amazon S3 bucket (only applies to migrations from an AWS RDS Oracle source), see [Migrating from Amazon Web Services RDS Oracle to Oracle Cloud](#)

Unless you are using the default data transfer servers for handling the Data Pump dumps, you may also need to configure the data transfer node settings for the source and target database environments.

See [Configuring the Transfer Medium and Specifying Transfer Nodes](#) for details.

- For a logical migration of an Oracle Database 11g source to an 11g target, set `DATAPUMPSETTINGS_SECUREFILELOB=FALSE` or you may get errors.

- Set the following target database parameters.

- `TARGETDATABASE_OCID` specifies the Oracle Cloud resource identifier.

For example:

```
ocid1.instance.oc1.phx.abuw4ljrlsfqw6vzzxb43vyypt4pkodawglp3wqxjqofakrwwou52g  
b6s5a
```

See also <https://docs.cloud.oracle.com/en-us/iaas/Content/General/Concepts/identifiers.htm>

- TARGETDATABASE_ADMINUSERNAME specifies the database administrator user name. For example, for a co-managed database migration user name as `system` and for an Autonomous Database migration user name as `admin`.
- TARGETDATABASE_CONNECTIONDETAILS_SERVICENAME specifies the fully qualified service name.

This parameter is optional for Autonomous AI Database targets; however if an HTTP proxy is required to connect, specify it.

In addition, for Oracle Autonomous AI Database on Dedicated Exadata Infrastructure and Oracle Autonomous AI Database on Exadata Cloud@Customer with **fractional OCPU** service you must specify the appropriate alias with TLS service in the parameter.

You can specify any predefined fractional service alias available; however, for Autonomous Transaction Processing workloads TP* services are preferred over LOW* services because LOW* is meant for low priority batch jobs.

- * TP_TLS, LOW_TLS (for Autonomous Transaction Processing workloads)
- * LOW_TLS (for Autonomous Data Warehouse workloads)

- Set the following source database parameters.

- SOURCEDATABASE_ADMINUSERNAME specifies the database administrator user name. For example, user name as `system`.
- SOURCEDATABASE_CONNECTIONDETAILS_HOST specifies the listener host name or IP address. In case of Oracle RAC, the SCAN name can be specified. (not required for Autonomous Database)
- SOURCEDATABASE_CONNECTIONDETAILS_PORT specifies the listener port number. (not required for Autonomous Database)
- SOURCEDATABASE_CONNECTIONDETAILS_SERVICENAME specifies the fully qualified service name. (not required for Autonomous Database)

For example: `service_name.DB_domain`

See also <https://docs.cloud.oracle.com/en-us/iaas/Content/Database/Tasks/connectingDB.htm>

- For migrations from an AWS RDS source, see Migrating from Amazon Web Services RDS to Oracle Autonomous Database for additional parameter settings.

- Set the following OCIAUTHENTICATIONDETAILS parameters.

Note

The OCIAUTHENTICATIONDETAILS parameter is optional for the target databases if there is no OCI endpoint connectivity.

For more information about the required settings, see <https://docs.cloud.oracle.com/en-us/iaas/Content/API/Concepts/apisigningkey.htm#RequiredKeysandOCIDs>

- OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_TENANTID specifies the OCID of the OCI tenancy. You can find this value in the Console under Governance and Administration, Administration, Tenancy Details. The tenancy OCID is shown under Tenancy Information.

For example:

```
ocid1.tenancy.oc1..aaaaaaaaba3pv6wkr4jqae5f44n2b2m2yt2j6rx32uzr4h25vqstifsds
q
```

See also <https://docs.cloud.oracle.com/en-us/iaas/Content/Identity/Tasks/managingtenancy.htm>

- OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_USERID specifies the OCID of the IAM user. You can find this value in the Console under Profile, User Settings.

See also <https://docs.oracle.com/en-us/iaas/Content/Identity/Tasks/managingusers.htm>

- OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_FINGERPRINT specifies the fingerprint of the public API key.
- OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_PRIVATEKEYFILE specifies the absolute path of API private key file.
- OCIAUTHENTICATIONDETAILS_REGIONID specifies the OCI region identifier.

See the Region Identifier column in the table at <https://docs.cloud.oracle.com/en-us/iaas/Content/General/Concepts/regions.htm>

Oracle GoldenGate Settings

During the migration job it is recommended that your database avoid Data Definition Language (DDL) operations to provide the most optimal environment for fast database replication. When DDL is replicated, Oracle GoldenGate Replicat serializes data to ensure that there are no locking issues between DML and DDL on the same objects.

The `DBOPTIONS DEFERREFCONST parallel` will only be added to the Replicat configuration when you set `GOLDENGATESETTIGS_REPLICATIONMODE=PARALLEL_NON_INTEGRATED` in the response file. The `DBOPTIONS DEFERREFCONST` option is set by default for Oracle GoldenGate Replicat non-integrated Parallel Replicat. `DEFERREFCONST` allows to migrate constraints and not disable the constraints on the target tables or setting them to `DEFERRED`. When used, `DEFERREFCONST` defers both `DEFERABLE` and `NOT DEFERABLE` constraints. `DEFERREFCONST` applies to every transaction that is processed by Replicat.

For online logical migrations, in addition to the above, you must also set the GoldenGate parameters, `TARGETDATABASE_GGADMINUSERNAME`, `SOURCEDATABASE_GGADMINUSERNAME`, `SOURCECONTAINERDATABASE_GGADMINUSERNAME`, and the parameters prefixed with `GOLDENGATEHUB` and `GOLDENGATESETTINGS`.

By default, Zero Downtime Migration excludes all DDL from GoldenGate replication. However, you can override this behavior by setting the parameter `GOLDENGATESETTINGS_REPLICATEDDL=true`.

By default, ZDM ensures that Oracle GoldenGate Extract and Replicat are auto start enabled for resiliency to any unexpected failures.

See [Zero Downtime Migration Logical Migration Response File Parameters Reference](#) for details about these parameters.

Set `GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE` to simplify Oracle GoldenGate Replicat configuration. This parameter replaces the need to configure four separate `GOLDENGATESETTINGS_REPLICAT_*` parameters listed below.

Starting with Oracle Zero Downtime Migration 21c (21.4) release, the following parameters are deprecated and will be desupported in a future release:

- `GOLDENGATESETTINGS_REPLICAT_MAPPARALLELISM`

- GOLDENGATESETTINGS_REPLICAT_APPLYPARALLELISM
- GOLDENGATESETTINGS_REPLICAT_MAXAPPLYPARALLELISM
- GOLDENGATESETTINGS_REPLICAT_MINAPPLYPARALLELISM

If you configure the GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE parameter, then you do not have to configure the deprecated parameters. However, if you do configure these deprecated parameters, then the GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE parameter will not be valid.

Oracle Data Pump Settings

Zero Downtime Migration automatically sets optimal defaults for Data Pump parameters to achieve better performance and ensure data security. If you need to further tune performance, there are several Data Pump settings that you can configure in the response file.

You can set DATAPUMPSETTINGS_EXPORTVERSION parameter to specify the Data Pump job export version. ZDM already sets the version parameter based on source and target version. This version parameter setting to 12 is required only for legacy Database upgraded to 11.2.0.4 and having Work Space Manager enabled. You can select the following values:

- COMPATIBLE
- 12
- LATEST

The default DATAPUMPSETTINGS_JOBMODE=SCHEMA is recommended for migrations to Autonomous AI Database.

See [Default Data Pump Parameter Settings for Zero Downtime Migration](#) for information about the default Data Pump property settings, how to select schemas or objects for inclusion or exclusion, and Data Pump error handling.

See [Zero Downtime Migration Logical Migration Response File Parameters Reference](#) for all of the Data Pump parameters you can set through Zero Downtime Migration.

See Migrating from Amazon Web Services RDS to Oracle Autonomous AI Database for information about setting Data Pump parameters for migration from AWS RDS.

Creating PAR URL once per job:

For logical migration, ZDM creates a PAR URL in the start/resume of every job and deletes the same PAR URL on completion/failure of job. ZDM uses this PAR URL for upload/download of all the dump and log files. You can customize the validity of PAR URL using the oracle.zdm.datapump.par_url_validity_in_days property.

Settings for performing logical migration from ADB (ADBS/ADBD) as source

ZDM supports logical migration from ADB (ADB-S/ADB-D) source. You can either provide ADB connection details with the existing SOURCEDATABASE_CONNECTIONDETAILS properties or use a new parameter SOURCEDATABASE_OCID.

Note

The value of SOURCEDATABASE_ENVIRONMENT_DBTYPE must be ADBD/ADBS.

Setting for printing all the reloadable objects with their sizes

ZDM will be printing all the reloadable objects with their sizes as part of the EVAL run. This property represents the minimum size in MB of the reloading table. Other tables are not be printed however, will still be reloaded. By default, the value will be 0, meaning all the tables that are reloaded as part of ZDM_RELOAD_PARALLEL_EXPORT_IMPORT phase are listed in the job log of the eval run.

For example, if you set `oracle.zdm.datapump.reload.print_threshold=10`, then the tables with size less than 10MB are not printed in the job log. This threshold is only to avoid populating the job log with too many table names if the reload list being too long.

5.6 Registering a New Region

Use the following response parameters to register a new realm:

- `OCISDKCONFIG_REGISTERREGIONDETAILS_REALM_KEY=OC4`
- `OCISDKCONFIG_REGISTERREGIONDETAILS_REALM_DOMAINCOMPONENT=realm.example`

Use the following response parameters to register a new region:

- `OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_REALMKEY=OC4`
- `OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_KEY=REGID`
- `OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_ID=region-id`

For example, to register `eu-dcc-milan-1` Region and `OC14` Realm, use the next configuration:

- `OCISDKCONFIG_REGISTERREGIONDETAILS_REALM_KEY=OC14`
- `OCISDKCONFIG_REGISTERREGIONDETAILS_REALM_DOMAINCOMPONENT=oraclecloud14.com`
- `OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_REALMKEY=OC14`
- `OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_KEY=BGY`
- `OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_ID=eu-dcc-milan-1`

For information related to the available regions with the following parameter values:

- Region Identifier
- Region Key
- Realm Key

See <https://docs.oracle.com/en-us/iaas/Content/General/Concepts/regions.htm>.

For information about OCI SDK configuration values for the most recent Regions and Realms, see:

- [Region](#)
- [Realm](#)

5.7 Configuring the Transfer Medium and Specifying Transfer Nodes

Zero Downtime Migration offers various transfer options to make Oracle Data Pump dumps available to the target database server.

Using the `DATA_TRANSFER_MEDIUM` response file parameter you can configure the following data transfer methods:

- `OSS`: Oracle Cloud Object Storage.
Supported for all migration types and targets.
- `NFS`: Network File System
Supported for co-managed and user managed targets.
- `DBLINK`: Direct data transfer from the source to the target over a database link.
Supported for all migration types and targets.
- `COPY`: Transfer dumps to the target transfer node using secure copy.
Supported for co-managed and user managed targets.
- `AMAZON3`: Amazon S3 bucket
- Only applies to migrations from an AWS RDS Oracle source. See *Migrating from Amazon Web Services RDS Oracle to Oracle Cloud* for more information.

Note

To take advantage of parallelism and achieve the best data transfer performance, Oracle recommends that you transfer data using `OSS` or `NFS` for databases over 50GB in size. The `DBLINK` transfer medium can be convenient for smaller databases, but this choice may involve uncertainty in performance because of its dependence on network bandwidth for the duration of the transfer.

Once the export of dumps on the source is completed, the dumps are uploaded or transferred in parallel as defined by parameter `DUMPTRANSFERDETAILS_PARALLELCOUNT` (defaults to 3), and any transfer failures are retried by default as specified in the parameter `DUMPTRANSFERDETAILS_RETRYCOUNT` (defaults to 3).

The transfer of dumps can be done from any node at the source data center, provided that the dumps are accessible from the given node. It is crucial to ascertain the network connectivity and transfer workload impact on the source database server in order to decide which data transfer approach to take.

Direct Transfer from Source to Target

This option applies only to co-managed cloud target databases.

Zero Downtime Migration enables logical migration using direct transfer of the Data Pump dump from the source to the target securely. The data is copied over from the source database directory object path to the target database server directory object path, or to a target transfer node, using either secure copy or `RSYNC`. This avoids the data being transferred over a WAN or needing additional shared storage between the source and target environments. This capability greatly simplifies the logical migration within the data center.

About Transfer Nodes

You will configure a node, referred as a **transfer node**, for both the source data center and the target tenancy.

The response file parameters that are prefixed with `DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE` designate the node that handles the export dumps at the source data center. This **source transfer node** defaults to the source database.

Similarly, the response file parameters that are prefixed with `DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE` designate the node that handles the import of dumps at the target. This **target transfer node** defaults to the target database, for co-managed targets.

Transfer Node Requirements

The source transfer node can be any of the following:

- Source database server (default)
- NAS mounted server
- Zero Downtime Migration service node

The target transfer node can be any of the following:

- Target Database server (default)
- NAS mounted server
- Zero Downtime Migration service node

For a server to be designated as transfer node, the following critical considerations are necessary.

- Availability of CPU and memory to process the upload or transfer workload
- Connectivity to the specified upload or transfer target
 - Port 443 connectivity to Object Storage Service if the chosen data transfer medium is `OSS`
 - Port 22 connectivity to target storage server if the chosen transfer medium is `COPY`
- Availability of Oracle Cloud Infrastructure CLI. For speedier and resilient upload of dumps this is the recommended transfer utility for the `OSS` transfer medium.
- OCI CLI must be installed and configured as detailed in <https://docs.oracle.com/en-us/iaas/Content/API/SDKDocs/cliinstall.htm>.

Installing and configuring OCI CLI on each source database server may not be feasible. In such cases, one of the nodes in the data center can be designated as a transfer node with OCI CLI configured, and this node can share a network storage path with the database servers for Data Pump dumps to be created. This also avoids the upload workload consuming additional CPU and memory on production database servers.

The designated transfer node can act as the gateway server at the data center for the external data transfer allowing transfer data traffic, thus avoiding the need to allow data transfer from the source database server or to the target database server.

Optionally, the additional transfer node requirement can be avoided by leveraging the Zero Downtime Migration server as the transfer node, provided that the Zero Downtime Migration service is placed in an on-premises data center and can meet the transfer node requirements listed above.

For transfer node and database server sharing storage to stage the dumps, ensure that the user on transfer node and database user share a common primary group for the dump files to be read on both the nodes.

Note

The `dbuser` plug-in shares a common group.

Using the Oracle Cloud Object Storage Transfer Medium

Object Storage data transfer medium is supported for all migration types and targets.

When using Object Storage as the data transfer medium, by setting `DATA_TRANSFER_MEDIUM=OSS`, it is recommended that dumps be uploaded using OCI CLI for faster and more secure and resilient uploads. You must configure OCI CLI in the upload node, and set parameter `DUMPTRANSFERDETAILS_SOURCE_USEOCICLI` to `TRUE`, the parameters for OCI CLI are

```
DUMPTRANSFERDETAILS_SOURCE_USEOCICLI
```

```
DUMPTRANSFERDETAILS_SOURCE_OCIHOME
```

For Oracle Cloud Object Storage based migration, ensure that the cloud access user is privileged to create a pre- authenticated URL for object storage bucket, specified for Data Pump Dump staging. See [Using Pre-Authenticated Requests](#) for details.

Using the Database Link Transfer Medium

Supported for online and offline migrations to all migration targets

When you set `DATA_TRANSFER_MEDIUM=DBLINK`, a database link is created from the OCI co-managed database or Autonomous Database target to the source database using the `global_name` of the specified source database.

Zero Downtime Migration creates the database link if it does not already exist, and the link is cleaned once the Data Pump import phase is complete.

Using the NFS Transfer Medium

The NFS mode of transfer is available, by setting `DATA_TRANSFER_MEDIUM=NFS`, for co-managed target databases that avoid the transfer of dumps. You should ensure that the specified path is accessible between the source and target database server path.

Zero Downtime Migration ensures the security of dumps in the shared storage by preserving the restricted permission on the dumps such that only the source and target database users are allowed to access the dump.

See [Mount Options for Oracle files for RAC databases and Clusterware when used with NFS on NAS devices \(Doc ID 359515.1\)](#)

Using the Copy Transfer Medium

Supported for co-managed and user managed target databases only.

1. To use COPY use the `oracle` user and set it in `DUMPTRANSFERDETAILS_TRANSFERTARGET_USER`.
2. Configure the `ssh` authentication ready for database user `oracle` in the target database.

Note

The `DUMPTRANSFERDETAILS_TRANSFERTARGET_USERKEY` RSA public key must be in the `authorized_keys` file.

3. The `zdmuser` connects from the ZDM node to the source database as an `auth` user using `zdmauth` or `dbuser` authentication plugins.

4. ZDM copies over the RSA key file from ZDM node, specified in `DUMPTRANSFERDETAILS_TRANSFERTARGET_USERKEY`.
5. The `zdmuser` uses the SSH connection as `sudo` user (such as `opc`) or `dbuser` (Oracle) to the source database and performs copy of dumps connecting to the target database as `DUMPTRANSFERDETAILS_TRANSFERTARGET_USER`.
6. ZDM deletes the copied RSA key from the source node.
You can transfer the dumps from the source to the target securely, by setting `DATA_TRANSFER_MEDIUM=COPY`.

The relevant parameters are as follows:

```
DUMPTRANSFERDETAILS_TRANSFERTARGET_USER
DUMPTRANSFERDETAILS_TRANSFERTARGET_USERKEY
DUMPTRANSFERDETAILS_TRANSFERTARGET_HOST
DUMPTRANSFERDETAILS_TRANSFERTARGET_SUDOPATH
DUMPTRANSFERDETAILS_TRANSFERTARGET_DUMPDIRPATH
```

You can leverage the RSYNC utility instead of SCP. Set `DUMPTRANSFERDETAILS_RSYNCAVAILABLE` to `TRUE`, and verify that RSYNC is available both at the source and target transfer nodes.

5.8 Selecting Objects for Migration

In Zero Downtime Migration, you can specify objects to include or exclude from a logical migration job using parameters in the response file.

Specify rules for objects to include, exclude, or reload in a migration job using the `EXCLUDEOBJECTS-n`, `RELOADOBJECTS-n` and `INCLUDEOBJECTS-n` response file parameters. You can either include or exclude objects in a migration, but you cannot do both.

If no rule is defined, all schemas and objects of the source database will be migrated, with exceptions listed in [What Is Migrated During Initial Load](#).

If you specify **Include** rules, the migration will only move the specified objects and their dependent objects; all other objects are automatically excluded. `USER` and `TABLESPACE_QUOTA` objectType associated with included schema are included by default.

When specifying **Exclude** rules, the specified objects and their dependent objects will not be migrated using Oracle Data Pump and will not be replicated using Oracle GoldenGate.

If you specify **Reload** rules, the specified objects will not be replicated using Oracle GoldenGate. Instead, the specified objects will be migrated to target database using Oracle Data Pump during phase `ZDM_RELOAD_PARALLEL_EXPORT_IMPORT` when there is no active workload on source database.

ZDM will be printing all the reloadable objects with their sizes as part of the `EVAL` run. This property represents the minimum size in MB of the reloading table. Other tables will not be printed however, will still be reloaded. By default, the value will be 0, which means all tables that will be reloaded will be listed as part of `ZDM_RELOAD_PARALLEL_EXPORT_IMPORT` phase in the `eval` run in the job log.

For example: If you set `oracle.zdm.datapump.reload.print_threshold=10`, then tables with size less than 10MB will not be printed in the job log. This threshold is only to avoid populating the job log with too many table names if the reload list is too long.

You can define multiple include, exclude, or reload rules by incrementing the integer appended to the parameter name, as shown in these examples.

Example of a single include rule:

```
INCLUDEOBJECTS-1=owner:ownerValue1, objectName:objectNameValue1,  
objectType:objectTypeValue1
```

Example of two exclude rules:

```
EXCLUDEOBJECTS-1=owner:ownerValue1, objectName:objectNameValue1,  
objectType:objectTypeValue1
```

```
EXCLUDEOBJECTS-2=owner:ownerValue2, objectName:objectNameValue2,  
objectType:objectTypeValue2
```

Example of two reload rules:

```
RELOADOBJECTS-1=owner:ownerValue1, objectName:objectNameValue1,  
objectType:objectTypeValue1
```

```
RELOADOBJECTS-2=owner:ownerValue2, objectName:objectNameValue2,  
objectType:objectTypeValue2
```

Use of wildcard expressions are allowed for RELOADOBJECTS parameter:

```
RELOADOBJECTS-1=ownerValue1,objectName:.*,objectType:TABLE
```

```
RELOADOBJECTS-1=owner:ownerValue1,objectName:EMPL.*,objectType:TABLE
```

Example of two excluded objects from Extract and reloaded during switchover:

```
GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS-1=owner:ownerValue1,  
objectName:objectNameValue1, objectType:objectTypeValue1
```

```
GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS-2=owner:ownerValue2,  
objectName:objectNameValue2, objectType:objectTypeValue2
```

Example of two excluded objects from Replicat and reloaded during switchover:

```
GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS-1=owner:ownerValue1,  
objectName:objectNameValue1, objectType:objectTypeValue1
```

```
GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS-2=owner:ownerValue2,  
objectName:objectNameValue2, objectType:objectTypeValue2
```

Note

Starting with the Oracle Zero Downtime Migration 26 (26.1) release, the RELOADOBJECTS parameter is deprecated and will be desupported in a future release. This parameter is replaced by the new GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS and GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS parameters. The GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS and GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS parameters are supported only for online logical migration.

Required Parameter Fields

To specify `INCLUDEOBJECTS-n`, `EXCLUDEOBJECTS-n`, and `RELOADOBJECTS-n` response file parameters, enter values for each of the following fields:

- **owner** specifies the owner of the selected database objects. When using Include rules, all rules must be for the same owner, and wild characters are not allowed.
- **objectName** specifies the name of selected database objects
- **objectType** specifies the type of selected database objects. You can select ALL to select objects of all types (default).

You can filter owner and objectName fields using any valid pattern in [Java class Pattern](#). For example, you can enter `.*` in the objectName field to select objects of any name.

If you exclude a larger number of tables using the `EXCLUDEOBJECTS-*` parameter, then ZDM copies them to a `temp_table` and adds that table to the filter. For example:

```
NOT IN (select * from TEMP_EXCLUDE_TABLE);
```

Restrictions

You must note the following restrictions:

- When excluding an object in a specified schema, and an object of the same name exists in a different schema that is also part of the migration, the objects will not be excluded (that is, the rule is ignored). The exclusion can be accomplished by migrating the schemas in separate migrations.
- When creating Include rules in FULL job mode, only schema-level rules (objectName is `.*` and objectType is ALL) are allowed.
- If an Include rule has `.*` in objectName, no other rule for the same objectType is allowed. If the rule has ALL as objectType, no other rule for any type is allowed.
- The objectType ALL is only allowed for schema-level rules (objectName is `.*`).
- The objectType TABLE is not allowed for schema-level rules where the owner is specified (objectName is `.*` and owner is any pattern other than `.*`).
- Object-level rules (objectName is any pattern other than `.*`) can only be used for the following object types: DIRECTORY, FUNCTION, JOB, MATERIALIZED_VIEW, PACKAGE, PROCEDURE, TRIGGER, SEQUENCE, TABLE, ROLE, PROFILE (Restricted to job mode FULL), PROCOBJ.

All other objectTypes must be either included or excluded using the `.*` pattern in objectName, and in addition for exclude, the owner should be `.*`

- The RELOADOBJECTS parameter is only supported for online logical migration.
- SEQUENCE after migration is not advanced in the following cases:
 - If the sequence name ends with `_SEQ` or `_SHSEQ`
 - If the sequence name starts with `AQ$_` or `ISEQ$$_`
 - If the sequence is marked secondary = 'Y' in `dba_objects` table.

Supported objectTypes for object-level filtering

objectName can be chosen or can be `.*`

DIRECTORY

FUNCTION

JOB

MATERIALIZED_VIEW

PACKAGE

PROCEDURE

TRIGGER

SEQUENCE

TABLE

ROLE

PROFILE (Restricted to job mode FULL)

PROCOBJ

Supported objectTypes for generic objectType-level exclude or include

(objectName must be .*)

CLUSTER

DB_LINK

GRANT

OBJECT_GRANT

SYSTEM_GRANT

ROLE_GRANT

PROCOBJ_GRANT

PROCDEPOBJ_GRANT

INDEX

INDEXTYPE

MATERIALIZED_VIEW_LOG

MATERIALIZED_ZONEMAP

POST_TABLE_ACTION

PROCOBJ

PROFILE

REF_CONSTRAINT

RLS_POLICY

SYNONYM

TABLESPACE

TABLESPACE_QUOTA

USER

XMLSCHEMA
VIEW
AUDIT_TRAILS
ON_USER_GRANT

Filtering other objectTypes

To filter other objectTypes that are NOT listed above like COMMENT, FGA_POLICY, and so on, use the [DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXCLUDETYPELIST](#) parameter.

Examples

Example 5-1 Include all objects of schema MySchema

```
INCLUDEOBJECTS-1=owner:MySchema, objectName:.*, objectType:ALL
```

owner	objectName	objectType
MySchema	.*	ALL

Example 5-2 Include all tables starting with PROD and procedure MYPROC of schema MySchema, including all dependent objects

```
INCLUDEOBJECTS-1=owner:MySchema, objectName:PROD.*, objectType:TABLE
```

```
INCLUDEOBJECTS-2=owner:MySchema, objectName:MYPROC, objectType:PROCEDURE
```

owner	objectName	objectType
MySchema	PROD.*	TABLE
MySchema	MYPROC	PROCEDURE

Example 5-3 Exclude schemas starting with Experimental, the table MySchema.OldTable (also excluding all dependent objects) and all objects of type DB_LINK

Note that MySchema.OldTable will not be excluded if a table called OldTable is present in a different schema that is also migrated.

```
EXCLUDEOBJECTS-1=owner:Experimental.*, objectName:.*, objectType:ALL
```

```
EXCLUDEOBJECTS-2=owner:MySchema, objectName:OldTable, objectType:TABLE
```

```
EXCLUDEOBJECTS-3=owner:.*, objectName:.*, objectType:DB_LINK
```

owner	objectName	objectType
Experimental.*	.*	ALL
MySchema	OldTable	TABLE
.*	.*	DB_LINK

Specify Included and Excluded Objects with Special Characters

The following examples show you how to specify objects names that use special characters in the EXCLUDEOBJECTS and INCLUDEOBJECTS parameters.

- To escape a special character, use a back slash (\) before and after all the characters in the string before the special character.

For example, to escape dollar sign (\$):

```
\INCLUDEOBJECTS-3= owner:GRAF_MULTI\$_HR
```

- To match all characters in between prefix and suffix pattern, add a period and an asterisk (.*) where the matching should occur.

For example, to exclude all schemas starting with GRAF and ending with HR:

```
EXCLUDEOBJECTS-3= owner:GRAF.*HR
```

5.8.1 Migrating Objects with Different Oracle GoldenGate Support Modes

You can migrate objects with different Oracle GoldenGate support modes.

Note

Zero Downtime Migration sets up Oracle GoldenGate replication only for `TABLE` objects.

Note

Oracle GoldenGate cannot replicate materialized views without `UPDATE` clause. Also, materialized view and source table cannot be replicated at the same time. Accordingly, for an online logical migration job, ZDM queries `dba_mviews` in the source database for materialized views that meet the following conditions:

- `UPDATABLE = 'N' OR MASTER_LINK = NULL`
`OR`
- `MASTER_LINK = <global_name>`

ZDM sets a `TABLEEXCLUDE` parameter for GoldenGate Extract to avoid replicating the materialized view, for each materialized view identified using the above query.

Migrating Tables with `support_mode = INTERNAL`

Zero Downtime Migration detects and notifies you about tables with `support_mode = INTERNAL`.

DML replication: Oracle GoldenGate automatically ignores DML for tables with `support_mode = INTERNAL`. Zero Downtime Migration does not set GoldenGate Extract parameter `TABLEEXCLUDE` for tables with `support_mode = INTERNAL`.

Oracle GoldenGate excludes DML replication for Global Temporary Tables.

DDL replication: If you set parameter `GOLDENGATESETTINGS_REPLICATEDDL = TRUE`, then Zero Downtime Migration sets Oracle GoldenGate Extract parameter `DDLOPTIONS CAPTUREGLOBALTEMPTABLE`.

Migrating Tables with `support_mode = ID KEY`

Under normal operation, Zero Downtime Migration reports an error listing all user tables with Oracle GoldenGate `support_mode = ID KEY`.

If you set parameter `GOLDENGATESETTINGS_USEFLASHBACKQUERY = TRUE`, Zero Downtime Migration sets the following Oracle GoldenGate Extract parameters that allow ID KEY support mode objects to be replicated.

- `STATOPTIONS REPORTFETCH`
- `FETCHOPTIONS USESNAPSHOT, NOUSELATESTVERSION, MISSINGROW REPORT`

Ensure that the source database has sufficient UNDO size to allow Oracle GoldenGate to use Flashback Query. For best fetch results, configure the source database as documented at [Setting Flashback Query](#) in *Using Oracle GoldenGate with Oracle Database*.

Migrating Tables with `support_mode = NONE` and `support_mode = PLSQL`

The `ZDM_VALIDATE_SRC` phase queries view `DBA_GOLDENGATE_SUPPORT_MODE` and reports list of tables with `support_mode = NONE` and `support_mode = PLSQL`.

Set the following ZDM parameters to migrate such objects:

- `GOLDENGATESETTINGS_RELOADUNREPLICATEDOBJECTS`
- `RELOADOBJECTS-LIST_ELEMENT_NUMBER`

Related Topics

- Handling Application Switchover in a Logical Migration
- `GOLDENGATESETTINGS_RELOADUNREPLICATEDOBJECTS`
- `RELOADOBJECTS-LIST_ELEMENT_NUMBER`
- [DBA_GOLDENGATE_NOT_UNIQUE](#)

5.9 Migrating METADATA

You can perform a phased migration using this feature.

Migrating METADATA and DATA as separate phases in ZDM workflow has the following benefits:

- Workflow performs regular EXPORT and a phased import that involves Pre-data Metadata Import which includes:
 - USER and PROFILE creation
 - METADATA creation
 - DATA import
- This helps with inserting workflow customization in the workflow.

If you specify a different GoldenGate schema name, then you will need to update the `GLOBALS` file.

To import METADATA before DATA, set value of the `DATAPUMPSETTINGS_METADATAFIRST` parameter to `TRUE`.

Related Topics

- Zero Downtime Migration Process Phases

5.10 Setting Advanced Data Pump Parameters

Zero Downtime Migration automatically sets optimal defaults for Oracle Data Pump parameters to achieve better performance and ensure security of data. To further tune performance, change the export modes, or rename database objects, there are several Data Pump settings that you can configure in the migration response file.

These parameters are set in the response file at `$ZDM_HOME/rhp/zdm/template/zdm_logical_template.rsp`.

5.10.1 Default Data Pump Parameter Settings for Zero Downtime Migration

The following table lists the Data Pump parameters set by Zero Downtime Migration, and the values they are set to. If there is a Zero Downtime Migration response file parameter available to override the default, it is listed in the Optional Zero Downtime Migration Response File Parameter to Override column. The override parameters are set in the response file at `$ZDM_HOME/rhp/zdm/template/zdm_logical_template.rsp`.

Table 5-3 Data Pump Parameter Defaults

Data Pump Parameter	Default Value	Optional ZDM Response File Parameter to Override
EXCLUDE	cluster (ADB-D, ADB-S) indextype (ADW-S) db_link (ADB) statistics (User managed Target and ADB)	<p>Allows additional EXCLUDE entries to be specified. See EXCLUDEOBJECTS-LIST_ELEMENT_NUMBER for information.</p> <p>Note Specifying invalid object types for EXCLUDE will lead to a Data Pump export error. Ensure that a valid object type is specified for the DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXCLUDETYPELIST parameter.</p> <p>To see a list of valid object types, query the following views: DATABASE_EXPORT_OBJECTS for FULL mode, SCHEMA_EXPORT_OBJECTS for SCHEMA mode, and TABLE_EXPORT_OBJECTS for TABLE and TABLESPACE mode. The values listed in the OBJECT_PATH column are the valid object types.</p> <p>For example, specifying the invalid object type parameter in the response file will lead to export error.</p> <p>ORA-39038: Object path "<specified invalid>" is not supported for SCHEMA jobs.</p>

Table 5-3 (Cont.) Data Pump Parameter Defaults

Data Pump Parameter	Default Value	Optional ZDM Response File Parameter to Override
PARALLEL	ZDM sets PARALLEL parameter by default as follows For User managed DB :- (Sum of (2 x (no. of physical CPU) per node)) with Max 32 cap. For ADB :- No. of OCPUs	DATAPUMPSETTINGS_DATAPUMPPARAMETERS_IMPORTPARALLELISMDEGREE DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXPORTPARALLELISMDEGREE
CLUSTER	ZDM always sets the Cluster mode as default	DATAPUMPSETTINGS_DATAPUMPPARAMETERS_NOCLUSTER
COMPRESSION	COMPRESSION_ALGORITHM is set to BASIC(for 11.2) and MEDIUM (for 12.1+) COMPRESSION is set to ALL	N/A
ENCRYPTION	ENCRYPTION is set to ALL ENCRYPTION_ALGORITHM is set to AES128 ENCRYPTION_MODE is set to PASSWORD	N/A
FILESIZE	FILESIZE is set to 5G	N/A
FLASHBACK_SCN	For OFFLINE_LOGICAL ZDM set FLASHBACK_TIME System time now. For ONLINE LOGICAL ZDM uses neither FLASHBACK_SCN not FLASHBACK_TIME	N/A
REUSE_DUMPFILES	Always set to YES	N/A
TRANSFORM	Always sets OMIT_ENCRYPTION_CLAUSE:Y for 19c+ targets Always sets LOB_STORAGE:SECUREFILE For ADB target, following transform is set by default SEGMENT_ATTRIBUTES:N DWCS_CVT_IOTS:Y CONSTRAINT_USE_DEFAULT_INDEX:Y	Allows additional TRANSFORM to be specified
METRICS	Always set to Yes	N/A
LOGTIME	Always set to ALL	N/A
TRACE	Always set to 1FF0b00	N/A

Table 5-3 (Cont.) Data Pump Parameter Defaults

Data Pump Parameter	Default Value	Optional ZDM Response File Parameter to Override
LOGFILE	<p>Always set to Data Pump job name and created under specified export or import directory object.</p> <p>Say if Data Pump job is ZDM_2_DP_EXPORT_8417 and directory object used is DATA_PUMP_DIR, then the operation log is created by name ZDM_2_DP_EXPORT_8417.log under DATA_PUMP_DIR.</p>	N/A

5.10.2 Automatic Tablespace Creation

For logical migrations, Zero Downtime Migration automatically discovers the source database tablespaces associated with user schemas that are being migrated, and automatically create them in the target database before the Data Pump import phase.

Note

By default, all the tablespaces are automatically created. If you do not want to create a tablespace automatically, use the `TABLESPACEDETAILS_EXCLUDE` parameter and specify the tablespaces to be excluded from automatic creation at the target database.

Zero Downtime Migration generates the DDL required to pre-create the tablespaces, creates the tablespaces on the target, and runs the generated DDL.

Automatic tablespace creation is enabled by default for ADB-Dedicated and non-ADB targets. With automatic creation enabled, Zero Downtime Migration skips automatic creation for any tablespaces that are specified in the `REMAP` section in the response file, or that already exist in the target database.

Zero Downtime Migration validates whether tablespace creation is supported on the given target. There are no limitations for co-managed database systems. If the target is an Autonomous Database system, the following limitations apply:

- Autonomous Database systems support only BIGFILE tablespaces, so Zero Downtime Migration enforces BIGFILE tablespace by default on Autonomous Database targets, and reports an error if SMALLFILE tablespaces are found. You can remap any SMALLFILE tablespaces instead.
- Autonomous Database Shared systems do not support the automatic creation of tablespaces. Automatic tablespace REMAP to DATA is applied by default.

Use the following response file parameters to automatically create the required tablespaces at target database.

- `TABLESPACEDETAILS_AUTOCREATE` is enabled by default for automatic tablespace creation.

Note that if you set `TABLESPACEDETAILS_AUTOCREATE` to `FALSE`, then automatic tablespace remapping (`TABLESPACEDETAILS_AUTOREMAP`) is applied by default. If both `AUTOCREATE` and `AUTOREMAP` are set to `FALSE`, then none is applied.

- `TABLESPACEDETAILS_USEBIGFILE` allows you to convert `SMALLFILE` tablespaces to `BIGFILE` tablespaces. Normally set to `FALSE` by default, Zero Downtime Migration enforces `TRUE` for Autonomous Database targets.
- `TABLESPACEDETAILS_EXTENDSIZEMB` enables tablespaces to `AUTOEXTEND` to avoid extend errors, with a default `NEXT EXTEND` size of 512MB.
- `TABLESPACEDETAILS_EXCLUDE` specifies tablespaces to be excluded from automatic creation at the target database during import of user schemas. By default 'SYSTEM', 'SYSAUX', 'USERS' tablespaces are excluded.

Note

If the current usage is less than 100M, then a default size of 100M is set as the initial size. If current usage of tablespace is higher than 100M, then the actual current size is set as the initial size. `AUTOEXTEND` ensures that there is no maximum limit. For `SMALLFILE`, if the `incrementby` clause is 0 (zero), then the default value of 1 is applied to determine the `AUTOEXTEND ON NEXT` size.

5.10.3 Automatic Tablespace Remap

For logical migrations, Zero Downtime Migration can automatically remap tablespaces on the source database to a specified tablespace on the target database.

Zero Downtime Migration automatically discovers the source database tablespaces necessary for migration. With automatic remap enabled, Zero Downtime Migration discovers the source tablespaces that require remapping by excluding any tablespaces that meet the following conditions:

- Specified for remap in `DATAPUMPSETTINGS_METADATAAREMAPS`
- Specified for exclude in `TABLESPACEDETAILS_EXCLUDE`
- Tablespaces with the same name that already exist on the target database

Use the following response file parameters to automatically remap the required tablespaces.

- `TABLESPACEDETAILS_AUTOREMAP` enables automatic tablespace remap.
- `TABLESPACEDETAILS_REMAPTARGET` specifies the name of the tablespace on the target database to which to remap the tablespace on the source database. The default value is `DATA`.

Verifying Tablespace Remaps

Run command `ZDMCLI migrate database` in evaluation mode (`-eval`) to ensure that all necessary tablespaces to be remapped are listed. If any tablespaces are missed, you remap them using the `DATAPUMPSETTINGS_METADATAAREMAPS` parameter.

Note

For a tablespace to be used as REMAP target, the user performing the import operation, for example, SYSTEM, should have some quota on the chosen tablespace.

Performance Considerations

There is operational overhead involved in tablespace remapping that adds to the overall Data Pump import time. To optimize performance, review and drop unwanted tablespaces from the source database to minimize the number of remapped tablespaces. For more information, see the REMAP_* section in [What Data Pump And Oracle RDBMS Parameters And Features Can Significantly Affect Data Pump Performance ? \(Doc ID 1611373.1\)](#).

Remap of temporary Tablespaces

- For Autonomous target database, ZDM remaps temporary tablespaces by default and remaps to TEMP by default.
- For non-Autonomous target database, opt for remapping temporary tablespaces and specify the target temporary tablespace to be remapped to, using the TABLESPACEDETAILS_REMAPTEMPTARGET parameter.
- When you migrate to Oracle Autonomous AI Database Serverless in FULL mode, tablespaces are remapped to DATA by default. Tablespace creation is not allowed so, set the following parameter:
DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXCLUDETYPELIST=TABLESPACE

5.10.4 Metadata Remapping

The DATAPUMPSETTINGS_METADATAREMAPS* parameter lets you rename database objects during a migration job. Specify the object to rename with **type**, then enter the **oldValue** and **newValue**.

For example:

```
DATAPUMPSETTINGS_METADATAREMAPS-1=type:REMAP_TABLESPACE,oldValue:TS_DATA_X,newValue:DATA
```

```
DATAPUMPSETTINGS_METADATAREMAPS-2=type:REMAP_TABLESPACE,oldValue:DBS,newValue:DATA
```

Supported object types are REMAP_DATAFILE, REMAP_SCHEMA, REMAP_TABLE, and REMAP_TABLESPACE.

Quota grants for individual users to tablespaces are not remapped, so you must manually create these grants for tablespace DATA.

When migrating to an Autonomous Database Shared Infrastructure target, all tablespaces are automatically mapped to DATA. You can override this by explicitly mapping tablespaces to a different target in the response file.

Note

The REMAP_SCHEMA parameter does not remap the references embedded within the body of definitions of types, views, procedures, and packages. See [REMAP_SCHEMA](#) for more information.

See METADATA_REMAP Procedure for more information.

5.10.5 Data Pump Error Handling

Some errors are ignored by Zero Downtime Migration. You must review any remaining errors appearing in the Data Pump log.

The following Data Pump errors are ignored by Zero Downtime Migration.

- ORA-31684: XXXX already exists
- ORA-39111: Dependent object type XXXX skipped, base object type
- ORA-39082: Object type ALTER_PROCEDURE: XXXX created with compilation warnings

Ensure that you clear all Cloud Premigration Advisor Tool (CPAT) reported errors to avoid any underlying Data Pump errors.

5.11 Migrating Schemas in Parallel Using Batches

Zero Downtime Migration lets you run multiple schema migrations as batches in parallel.

You can specify schema batches that need to be migrated in parallel. Determine groups of dependent schemas and specify all dependent schemas as part of same batch.

The migration work flow handles the schemas as batches and runs Data Pump export, dump upload, and import operations in parallel for each batch specified.

Any error that occurs in one batch does not affect the other batch operations.

A progress monitor identifies the progress of each batch progress, reports progress individually, and errors specific to a batch are reported at the completion of all batch Data Pump Import operations.

Zero Downtime Migration also supports random batch selection by batch count, where the identified user schemas to be migrated are grouped randomly by the specified number of batches and migrated in parallel.

A new migration job phase ZDM_PARALLEL_EXPORT_IMPORT is cumulative of ZDM_DATAPUMP_EXPORT_SRC, ZDM_UPLOAD_DUMPS_SRC, and ZDM_DATAPUMP_IMPORT_TGT phases, and it handles all three actions for an identified sublist of schemas per thread, that is, export, transfer, and import the sublist of schemas in parallel.

To configure batch mode:

In the RSP, set DATAPUMPSETTINGS_JOBMODE parameter to SCHEMA.

The batch mode of operation is not enabled by default; you must enable it by setting one of the following RSP parameters:

- DATAPUMPSETTINGS_SCHEMABATCHCOUNT=*integer* indicates how many schemas to include in each batch.

In this case Zero Downtime Migration does not guarantee the set of schemas per batch (the Data Pump job).
- DATAPUMPSETTINGS_SCHEMABATCH=*n*, where *n* can be -1, -2, 03, lets you specify a list schemas to place in a batch for parallel handling.

Note that DATAPUMPSETTINGS_SCHEMABATCHCOUNT and DATAPUMPSETTINGS_SCHEMABATCH are mutually exclusive.

Also, note that database initialization parameter `MAX_DATAPUMP_JOBS_PER_PDB` determines the maximum number of concurrent Oracle Data Pump jobs for each PDB.

Restrictions

`DATAPUMPSETTINGS_JOBMODE` value other than `SCHEMA` is prohibited if a batch of schemas is specified.

Specifying `INCLUDEOBJECTS` is prohibited if batch of schemas is specified.

No SSH Source and parallel migration is not allowed - the job must be paused for manual upload of dumps that defeats the purpose exporting schemas in parallel.

`MAX_DATAPUMP_JOBS_PER_PDB` determines the maximum number of concurrent Oracle Data Pump jobs per PDB. Exceeding this limit causes ORA-39391: maximum number of Data Pump jobs (n) exceeded.

5.12 Migrating from Amazon Web Services RDS Oracle to Oracle Cloud

You can migrate an Oracle Database from Amazon Web Services (AWS) RDS to Oracle Autonomous AI Database (ADB), OCI user-managed databases, and Oracle Exadata Database Service on Cloud@Customer using the Zero Downtime Migration logical migration method (online and offline).

5.12.1 Setting Amazon as the Source Environment

In the Zero Downtime Migration logical migration response file, set the following parameters to migrate Oracle databases from Amazon Web Services:

```
SOURCEDATABASE_ENVIRONMENT_NAME=AMAZON
```

```
SOURCEDATABASE_ENVIRONMENT_DBTYPE=RDS_ORACLE
```

5.12.2 Configure Secure Connections

Ensure that the subnet Amazon RDS security policy allows connections from Zero Downtime Migration to the DB instance on the specified secure port. See the AWS documentation for details:

[Scenarios for accessing a DB instance in a VPC](#)

[Scenarios for accessing a DB instance not in a VPC](#)

Setting Endpoint Information

1. Find the Amazon RDS Oracle Instance endpoint (DNS name) and port number in the RDS console DB Instance **Connectivity & security** tab.

See [Finding the endpoint of your Oracle DB instance](#) for detailed help.

2. Specify the endpoint and port number information in following Zero Downtime Migration logical response file parameters:

```
SOURCEDATABASE_ADMINUSERNAME
```

```
SOURCEDATABASE_CONNECTIONDETAILS_HOST
```



```
SOURCEDATABASE_CONNECTIONDETAILS_SERVICENAME
```

```
SOURCEDATABASE_CONNECTIONDETAILS_PORT
```

3. If connecting to Amazon RDS from the Zero Downtime Migration service host requires a proxy, then specify these logical response file parameters:

```
SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME
```

```
SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT
```

Allowing Zero Downtime Migration to connect to Amazon RDS Oracle DB instance using SSL/TLS

1. Enable Secure Socket Layer (SSL) or Transport Layer Security (TLS) in the Amazon RDS Oracle Instance to secure the connection from Zero Downtime Migration to Amazon RDS Oracle Instance. See [Encrypting client connections with SSL](#) for details.
2. Create an orapki wallet as detailed in [Updating applications to use new SSL/TLS certificates](#).
3. Set the following parameters in the Zero Downtime Migration logical response file:

```
SOURCEDATABASE_CONNECTIONDETAILS_TLSDETAILS_DISTINGUISHEDNAME
```

```
SOURCEDATABASE_CONNECTIONDETAILS_TLSDETAILS_CREDENTIALSLOCATION
```

5.12.3 Setup the Source Oracle on Amazon RDS for Oracle GoldenGate

Perform the following steps in the source Oracle on Amazon RDS to enable Oracle GoldenGate replication.

1. Turn on the minimum database-level supplemental logging:

```
EXEC rdsadmin.rdsadmin_util.alter_supplemental_logging(p_action =>
    'ADD')
```

2. Set the `ENABLE_GOLDENGATE_REPLICATION` initialization parameter to `TRUE`.
3. Enable force logging:

```
EXEC rdsadmin.rdsadmin_util.force_logging(p_enable => true);
```

4. Set the log retention period. For example, set the retention period for archived redo logs to 24 hours as follows:

```
EXEC rdsadmin.rdsadmin_util.set_configuration('archive log retention
    hours', 24)
```

5. Ensure sufficient space for the log files. Run the following query, specifying the number of hours:

```
SELECT SUM(BLOCKS * BLOCK_SIZE) BYTES FROM V$ARCHIVED_LOG WHERE
    NEXT_TIME>=SYSDATE-num_hours/24 AND DEST_ID=1;
```

6. Create the GGADMIN user, as follows:

```
CREATE USER GGADMIN IDENTIFIED BY "password"
    DEFAULT TABLESPACE <USER TABLESPACE> TEMPORARY TABLESPACE <TEMP_TS>;
ALTER USER GGADMIN QUOTA UNLIMITED ON <USER TABLESPACE>;
```

```

GRANT CREATE SESSION, ALTER SESSION TO GGADMIN;
GRANT RESOURCE TO GGADMIN;
GRANT SELECT ANY DICTIONARY TO GGADMIN;
GRANT FLASHBACK ANY TABLE TO GGADMIN;
GRANT SELECT ANY TABLE TO GGADMIN;
GRANT SELECT_CATALOG_ROLE TO rds_master_user_name WITH ADMIN OPTION;
EXEC rdsadmin.rdsadmin_util.grant_sys_object ('DBA_CLUSTERS', 'GGADMIN');
GRANT EXECUTE ON DBMS_FLASHBACK TO GGADMIN;
GRANT SELECT ON SYS.V_$DATABASE TO GGADMIN;
GRANT ALTER ANY TABLE TO GGADMIN;
EXEC rdsadmin.rdsadmin_dbms_goldengate_auth.grant_admin_privilege (
    grantee => 'GGADMIN',
    privilege_type => 'capture',
    grant_select_privileges => true,
    do_grants => TRUE);

```

5.12.4 Configuring the Data Transfer Method

To transfer the data from AWS, you have the following options:

- Amazon Simple Storage Service (Amazon S3) Bucket
- Database link (DBLINK)

5.12.4.1 Setting Up Database Link Transfer Method

To use a database link (DBLINK) to migrate Amazon RDS Oracle Database schema to Oracle Autonomous AI Database (ADB), you must have direct network connectivity between the Amazon RDS Oracle instance and the ADB target.

Set the following parameters in the Zero Downtime Migration logical response file.

1. Set the parameter `DATATRANSFERMEDIUM` to `DBLINK`.
2. Set the parameter `SOURCEDATABASE_ENVIRONMENT_*` as shown in Setting Amazon as a Source Environment.

5.12.4.2 Setting Up S3 Bucket Data Transfer Medium

Zero Downtime Migration performs the following steps to migrate an Amazon RDS Oracle Database schema to Oracle Autonomous AI Database target using an S3 bucket:

- **Export dumps** - Invoke the `DBMS_DATAPUMP` procedure in the Amazon RDS Oracle Database instance to generate dumps in `DATA_PUMP_DIR`.
- **Upload dumps to S3 using RDSADMIN** – Upload dumps from the RDS instance to the specified S3 bucket.
- **Import dumps from S3 to ADB** – Import the schema to the ADB instance from the S3 bucket.

To configure the environments to use the S3 bucket for data transfer, complete the following tasks.

Complete AWS RDS Prerequisites

The RDS Oracle instance must have been integrated with S3 and the DB user should be allowed to upload the dumps to S3 bucket via RDSADMIN package.

1. **Integrate RDS and S3** - Ensure that the RDS instance and S3 are integrated.
Enable RDS and S3 integration for the Oracle Database instance if not configured already.
See [Amazon S3 integration](#) for the detailed steps.
2. **S3 Access Key** - Create and provide Zero Downtime Migration with the AWS S3 Access Key and Access secret.
See [AWS Account and Access Keys](#) for the detailed steps.
3. **S3 and RDS region** - Ensure that the S3 bucket and RDS Oracle Database instance are in the same region, for example us-east-2.

Set Required Response File Parameters

Set the following parameters to perform a migration using the S3 bucket:

1. Set the parameter `DATATRANSFERMEDIUM` to `AMAZONS3`.
2. Set the `SOURCEDATABASE_ENVIRONMENT_*` as shown in Setting Amazon as a Source Environment.
3. Set the following additional parameters:
`DUMPTRANSFERDETAILS_S3BUCKET_NAME=`
`DUMPTRANSFERDETAILS_S3BUCKET_REGION=`
`DUMPTRANSFERDETAILS_S3BUCKET_ACCESSKEY=`
`DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_NAME=`

5.13 Migrating to Oracle Autonomous AI Database on Exadata Cloud@Customer

Zero Downtime Migration supports migrations to Oracle Autonomous AI Database on Exadata Cloud@Customer from any on-premises Oracle Database, including existing Exadata Cloud@Customer systems, using the logical migration method and NFS as a data transfer medium.

Supported Use Cases

The following migration scenarios are supported by Zero Downtime Migration:

- Oracle Exadata Database Service on Cloud@Customer (Gen 1 or Gen 2) source to Oracle Autonomous AI Database on Exadata Cloud@Customer target (given that the source and target databases have the same standard UID/GID for the Oracle user)
- On-premises Oracle Database source to Oracle Autonomous AI Database on Exadata Cloud@Customer target (given that the source database has a non-standard UID/GID for the Oracle user)

Migration Parameters

In addition to the required source and target connection parameters, set the following in the logical migration response file:

`MIGRATION_METHOD=OFFLINE_LOGICAL or ONLINE_LOGICAL`

`DATA_TRANSFER_MEDIUM=NFS`

Source Prerequisites

In addition to the usual source database prerequisites documented in Source Database Prerequisites for Logical Migration, you must also set up access to the Data Pump dump directory as detailed in the procedures below.

Prerequisite Setup for Exadata Cloud@Customer Environments

1. In all Oracle RAC nodes:

```
[root@onprem ~]# cat /etc/fstab | grep nfsshare
nas-server.us.com:/scratch/nfsshare /u02/app/oracle/mount nfs defaults 0 0
[root@onprem ~]#
```

2. On the Autonomous Database target, mount the path

```
nas-server.us.com:/scratch/nfsshare
```

to the Exadata infrastructure resource, giving you

```
specified_mount_path/CDB/PDB_GUID
```

For example:

```
/scratch/nfsshare/CDB/PDB_GUID
```

For information about the option to mount NFS, contact support for details.

3. On the source PDB, run the following:

```
SQL> create or replace directory DATA_PUMP_DIR_ADBCC as '/u02/app/oracle/
mount/CDB/PDB_GUID';
```

Directory created.

```
SQL> select grantee from all_tab_privs where table_name =
'DATA_PUMP_DIR_ADBCC';
```

no rows selected

```
SQL> grant read, write on directory DATA_PUMP_DIR_ADBCC to SYSTEM;
```

Grant succeeded.

4. On the source, mount point permissions expected (drwxr-x---

```
[oracle@onprem opc]$ ls -ldrt /u02/app/oracle/mount/CDB/PDB_GUID
drwxr-x--- 2 oracle asmadmin 4096 Jul 12 11:34 /u02/app/oracle/mount/CDB/
PDB_GUID
[oracle@onprem opc]$
```

Prerequisite Setup for On-Premises Environments

1. In all Oracle RAC nodes:

```
[root@onprem ~]# cat /etc/fstab | grep nfsshare
nas-server.us.com:/scratch/nfsshare /u02/app/oracle/mount nfs defaults 0 0
[root@onprem ~]#
```

2. Create a group with GID 1001 - miggrp

```
root> groupadd -g 1001 miggrp
```

3. Add the database user to this group.

```
root> usermod -aG migrp oracle
```

4. On the Autonomous Database target, mount the NFS share (Group should get *rw*)

```
nas-server.us.com:/scratch/nfsshare
```

to the Exadata infrastructure resource, giving you

```
specified_mount_path/CDB/PDB_GUID
```

For example:

```
/scratch/nfsshare/CDB/PDB_GUID
```

For information about the option to mount NFS, contact support for details.

5. Ensure that the directory is writable.

```
Touch specified_mount_path/CDB/PDB_GUID/test.txt
```

6. In the source PDB, run the following:

```
SQL> create or replace directory DATA_PUMP_DIR_ADBCC as '/u02/app/oracle/  
mount/CDB/PDB_GUID' ;
```

Directory created.

```
SQL> select grantee from all_tab_privs where table_name =  
'DATA_PUMP_DIR_ADBCC' ;
```

no rows selected

```
SQL> grant read, write on directory DATA_PUMP_DIR_ADBCC to SYSTEM;
```

Grant succeeded.

7. On the source, mount point permission expected (*drwxrwx-*), and the group should match the migration dummy group created.

```
[oracle@onprem opc]$ ls -ldrt /u02/app/oracle/mount/CDB/PDB_GUID  
drwxrwx--- 2 1001 asmadmin 4096 Jul 12 11:34 /u02/app/oracle/mount/CDB/  
PDB_GUID  
[oracle@onprem opc]$
```

Prerequisites for performing online logical migration:

If the online logical migration involves Oracle GoldenGate on docker, set up the target Autonomous Database wallet in Oracle GoldenGate on docker. See, Additional Logical Migration Prerequisites .

Note

If there is no connectivity to OCI endpoints, then specify the target database type in the `TARGETDATABASE_DBTYPE` parameter and skip the following parameters:

- `TARGETDATABASE_OCID`
- `OCIAUTHENTICATIONDETAILS_*`

Migrating to Oracle Autonomous AI Database on Exadata Cloud@Customer without OCI access granted to ZDM Host:

Follow the steps for performing a logical migration from on-premises Oracle Database source to Oracle Autonomous AI Database on Exadata Cloud@Customer without OCI access granted to the ZDM host:

Note

When the OCI access is not available, then do not specify the OCI Authentication details (`OCIAUTHENTICATIONDETAILS_*`) and Target database OCID (`TARGETDATABASE_OCID`).

- Set the following parameters:

```
TARGETDATABASE_DBTYPE=ADBCC
TARGETDATABASE_ADMINUSERNAME=<User performing import. For example, admin>
TARGETDATABASE_CONNECTIONDETAILS_HOST=<<Target database access endpoint.
For example, adb.us-ashburn-1.oraclecloud.com>
TARGETDATABASE_CONNECTIONDETAILS_SERVICE_NAME=<ADB service alias to be used
to connect. For example, HIGH or
HIGH_TLS>
```

- If proxy is required to access the Oracle Autonomous AI Database on Exadata Cloud@Customer database, then specify the parameters as follows:

```
TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME=<<Proxy to be used>>
TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT=<Port to be used>
```

- If the access to target is over TLS, then specify the parameters as follows:

```
TARGETDATABASE_CONNECTIONDETAILS_TLSDETAILS_*
```

Related Topics

- `TARGETDATABASE_DBTYPE`
- `TARGETDATABASE_OCID`
- `OCIAUTHENTICATIONDETAILS_REGIONID`

5.14 Migrating to Co-Managed Database Server with NFS Data Transfer Medium

The dumps in NFS mounted path are not readable for target database user unless the Unique Identifiers (UIDs) for the source database user matches with the target database user.

Complete the following prerequisites on the source database to prepare for a logical migration.

The following scenarios are possible:

- If the IDs match, dumps are readable by default and no action is required.
- If the IDs do not match, ZDM automatically discovers the primary group of the target database user and changes the group of the dump to the primary group of the target database user.

Note

Currently, this option is not supported in IBM AIX.

- To perform this action, the source database user in the database server must be a part of a group having the same group ID as that of the target database user's primary group.
- If there is no group available, then create an auxiliary group on the source database server with GID matching to the GID of target database user.
- Make the source database user to be a part of the auxiliary group.

Note

As an example, refer to Step 1 through Step 3 of *Prerequisite Setup for Exadata Cloud@Customer Environments* topic in *Migrating to Oracle Autonomous AI Database on Exadata Cloud@Customer*.

- However, if GID is not available and the above two conditions cannot be met, as an option you can set value of the DUMPTRANSFERDETAILS_PUBLICREAD to `TRUE` to make the dump files on NFS readable for others.

Note

Any user having access to the network storage can read the Data Pump dumps if value of DUMPTRANSFERDETAILS_PUBLICREAD is `TRUE`.

5.15 Migrating to Autonomous Database Server with File Storage Service as the Data Transfer Medium

ZDM allows to leverage Oracle Cloud Infrastructure File Storage Service (FSS) as the data transfer medium for physical and logical migration.

- The use of FSS in logical migration avoids OSS upload or download of Datapump dumps.
- ZDM attaches the FSS to ADB automatically part of the migration workflow.
- You must ensure that the file storage service is accessible over the NFS protocol in all the source database servers. ADB allows ingress and egress traffic for the known NFS ports.
- You can use File system as the supported data transfer medium for Datapump.

Complete the following prerequisites on the source database to prepare for a logical migration.

1. Ensure that network access exists between OCI and on-premises database. FastConnect or a Site-to-Site VPN are the options to connect to the on-premises data center to access data in an Autonomous Database from the file systems in an on-premises data center . See [FastConnect](#) and [Site-to-Site VPN](#) for more information.
2. Create a file system in OCI FSS. See [Creating File Systems](#) for more information.

Note

Step1 and step 2 do not apply for Autonomous Database on Exadata Cloud@Customer.

3. For Dedicated infrastructure or for ADB database in private subnet, add Virtual Cloud Network (VCN) security rules for OCI File Storage Service (FSS) access in ADB. See [External File Storage Requirements](#).
4. Obtain the FQDN or IP address for the mount target: See [To view details of a mount target](#) to get its FQDN.
5. Mount the exported filesystem in all Source Database server host and map to Data Pump export directory object path or specify the mounted path and a non-existent export directory object name for ZDM to create directory object in source database to be exported.
6. Enable the private endpoints for the Autonomous database for attaching it to a private File Storage service.
For more information, see:
 - [OCI File Storage Service](#)
 - [Configuring Network Access with Private Endpoints](#)
 - See usage notes in [Summary of DBMS_CLOUD_ADMIN Subprograms](#).

To migrate to ADB using FSS as the data transfer medium:

- Specify the Data transfer medium for datapump dump transfer as NFS or FSS based on the type of file system used. Specify the following parameters:
 - DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_NAME= <Directory object name>
 - DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_PATH= <NFS Mount path on Source Database host, must be available on instance host>
 - DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_NAME= <Directory object name>
 - DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_PATH= < to be left blank >
- Specify DATA_TRANSFER_MEDIUM=NFS for migrating to ADB target.
- Specify DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_NAME= <custom directory object.> Default: DATA_PUMP_DIR> that mounts the FSS to the target. For ADB, ZDM automounts

FSS to this specified Directory Name. You need to mount FSS to all target database hosts in case of non ADB targets.

- You must specify FSS or NFS host IP address and FSS mount point for migrating to ADB database if the `DATA_TRANSFER_MEDIUM` chosen is NFS. ZDM mounts the FSS in your Autonomous Database.

You need to configure NFS/FSS and specify the mount points for ADBS and ADBD for data ingestion/data migration (Datapump Dumps staging).

For ADB target ADB access you should be ADMIN user or a user with EXECUTE privilege on `DBMS_CLOUD_ADMIN`.

- Set the following optional logical parameters:
 - `DUMPTRANSFERDETAILS_SHAREDSTORAGE_NAME=` <Name of Exported filesystem to be specified for mount in ADB>
 - `DUMPTRANSFERDETAILS_SHAREDSTORAGE_HOST=` <Export Hostname to access shared path in ADB>
 - `DUMPTRANSFERDETAILS_SHAREDSTORAGE_PATH=` <Exported path to be mounted in ADB>
The above parameter are required to specified for mounting NFS on ADB. AutoMounting of NFS in source or non-ADB is not supported as it needs root access.

The AutoMount feature checks:

- skip mount action - if the `DATA_PUMP_DIR` objects specified in `DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_NAME` is already mounted to the same storage.
- error - if the `DATA_PUMP_DIR` objects specified in `DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_NAME` is already mapped to a different path other than that specified in `DUMPTRANSFERDETAILS_SHAREDSTORAGE_PATH`.

Migrating from an Autonomous Database to Autonomous Database with File Storage Service as the Data Transfer Medium

1. ZDM supports migration from an Autonomous Database to Autonomous Database using FSS as the data transfer medium. During the `ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC` phase, FSS is attached to the source ADB if it is not already attached. The `ZDM_DATAPUMP_EXPORT_SRC` phase supports FSS in the source ADB. Additionally, in the `ZDM_POST_ACTIONS` phase, ZDM now detaches the FSS from the source ADB if it had attached it earlier in the phases.
2. Similar to the `ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC` phase, in the `ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT` phase also FSS is attached to the target ADB if it is not already attached. `ZDM_DATAPUMP_IMPORT_TGT` also supports FSS in the target ADB. In the `ZDM_POST_ACTIONS` phase, ZDM detaches the FSS from the target ADB if it had earlier attached it in the phases.

5.16 Migrating to non-Autonomous Database with File Storage Service as the Data Transfer Medium

ZDM allows to leverage Oracle Cloud Infrastructure File Storage Service (FSS) as the data transfer medium for non-Autonomous Databases.

To migrate to non-ADB targets using FSS as the data transfer medium:

- You must mount FSS in non-ADB targets similar to NFS as FSS works on the NFS protocol.

- You must ensure that the `Oracle` user has write permission on the mounted file system path.

5.17 Logical Migration from an Autonomous AI Database

You can perform a logical migration from an Autonomous AI Database to an Autonomous AI Database by using DBLINK, OSS, or FSS or any supported shared storage medium that can be shared between source ADB and target database.

ZDM supports the following use cases for migrating Autonomous database as the source database:

- ADB to ADB over OSS, FSS, NFS or DBLINK as Data transfer medium. The source and target databases can be Autonomous Serverless or Dedicated.
- ADB to Non-Autonomous over FSS, NFS or DBLINK as Data transfer medium.
- ZDM supports both online and offline logical migration from an ADB (Oracle Autonomous AI Database Serverless (ADB-S) /Oracle Autonomous AI Database (ADB-D) source.

Source ADB connection handling is described as follows:

- The value of `SOURCEDATABASE_ENVIRONMENT_DBTYPE` must be `ADBS` or `ADBD`.
- You can either provide ADB connection details with the existing `SOURCEDATABASE_CONNECTIONDETAILS` properties or use the `SOURCEDATABASE_OCID` a new response file parameter.
- For online logical migration place the wallets for the source and target databases in OGG hub location `/u02/deployments/Marketplace/etc`. The wallet of Autonomous database extracted as `Wallet_<dbname>` in `/u02/deployments/Marketplace/etc/`. The `dbname` case must match with the case found in the `'SELECT * from GLOBAL_NAME'` query output.

Ensure to ignore the following errors during an offline logical migration from an Autonomous source database to an Autonomous target database by using the `IGNOREIMPORTERERRORS` parameter:

```
IGNOREIMPORTERERRORS=ORA-31685,ORA-39083,ORA-01919,ORA-01924,ORA-27486,ORA-31684,ORA-39111
```

Related Topics

- [Data Pump Error Handling](#)

5.18 Configuring Per-PDB Extract Using Oracle GoldenGate 21c

ZDM configures PDB extract for the following use cases:

- On-premises Oracle PDB of version 21c or higher.
- OCI Autonomous Database of version 19c or higher.
- OCI non-Autonomous PDB of version 21c or higher.
- AWS RDS Oracle PDB of version 21c or higher.

Note

Oracle GoldenGate 21c and higher versions support the PDB Extract feature.

Note

The per-PDB Extract is the default for source databases version higher or equal to Oracle Database 19c (19.23).

To create and register the Extract specific to a PDB, connect to the local `ggadmin` user in a specific pluggable database.

Note

The CDB label details are not required to collect extract of PDB. This feature is applicable for Oracle Database 19c (19.23) and higher versions..

5.19 Simplifying Object Reload for Online Logical Migration

ZDM minimizes the number of tables which need to be reloaded by using Oracle GoldenGate's `reload_query_advisor` results for the unsupported source tables. Also, ZDM allows you to update an ongoing migration job and Oracle GoldenGate Replicat process to exclude the tables causing replication issues and reload the tables during switchover.

With this functionality, ZDM:

- Leverages Oracle GoldenGate Extract's `migration_mode` parameter which automatically skips capturing changes for the unsupported source tables (automatically includes all the supported tables and exclude the unsupported ones such as AQ tables, materialized views, text indexes, and so on).
- Uses Oracle GoldenGate's `reload_query_advisor` to identify highly active tables lacking row uniqueness and excludes such tables from replication.

Note

Small and/or less active tables are still replicated even if the tables lack row uniqueness.

- Automatically reloads tables identified by Oracle GoldenGate's `reload_query_advisor` during switchover.
- Automatically reloads the unsupported objects during the switchover.

ZDM performs the following tasks:

1. Executes Oracle GoldenGate's `reload_query_advisor` for the source database during the `ZDM_VALIDATE_SRC` phase and reports the results.
2. Uses Oracle GoldenGate's `reload_query_advisor` results to automatically configure Oracle GoldenGate Extract process to exclude tables for replication.
 - a. Tables are instantiated in the target database during the initial load using Data Pump.
 - b. Subsequently, the tables are automatically reloaded using Data Pump during switchover. ZDM skips reloading the tables that have not been modified in the source database after initial load.
3. Introduces the following new parameters so that you can override the default table selections for replication:

- GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS
- GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS
- GOLDENGATESETTINGS_EXCLUDERELOAD
- GOLDENGATESETTINGS_SKIPRELOADQUERYADVISOR

6

Performing a Hybrid Offline Migration

ZDM introduces hybrid, cross-platform Transportable Tablespace (XTTS) database migration support for cross-platform and cross-version migration using RMAN transportable tablespaces and Data Pump metadata import/export.

You can perform a hybrid offline migration to Oracle Base Database Service, Oracle Exadata Database Service on Dedicated Infrastructure, Oracle Exadata Database Service on Cloud@Customer Service, and Oracle Exadata Database Machine On-Premises Databases.

6.1 Overview

Hybrid migration follows ZDM's proven methodology of pre-check, data transfer, synchronization, and post-check. While there are manually several phases that ZDM goes through for a hybrid Migration, the overall workflow is summarized as follows:

1. ZDM connects to the source database and target database and performs the following validations:
 - a. ZDM_VALIDATE_TGT phase: ZDM connects to the target database and performs validations.
 - b. ZDM_VALIDATE_SRC phase: ZDM connects to the source database and performs validations.
 - c. ZDM_SETUP_XTTS_SRC phase: ZDM configures required helper modules at the source level.
 - d. ZDM_SETUP_XTTS_TGT phase: ZDM configures required helper modules at the target level.
2. ZDM orchestrates the tablespace-level backups:
 - a. Performs a full backup of the tablespaces.
 - b. Performs an incremental backup of the tablespaces.
 - c. Copies the wallet files as required.
3. ZDM performs a full restore of tablespaces as foreign tablespaces.
4. ZDM sets the source tablespaces as read-only and performs the following steps:
 - a. Performs an incremental backup of the tablespaces and metadata export of the tablespaces using RMAN.
 - b. Copies the wallet files as required.
5. ZDM exports the metadata via Data Pump. The export includes:
 - Metadata
 - PL/SQL objects
 - Non-tablespaces data
6. ZDM imports the metadata and performs an incremental restore as follows:
 - a. Import of the user metadata from Data Pump.

- b. Incremental restore with RMAN + import of tablespace metadata generated by RMAN.
 - c. Import of all the other metadata (objects and non-tablespace data).
7. ZDM performs post actions, cleans up, and finalizes.

6.2 Pre-requisites

Zero Downtime Migration Service Host Requirements

For ZDM's service host requirements, installation, and overall configuration related information, refer to the [Setting Up Zero Downtime Migration Software](#) topic.

6.3 Source Database Requirements

- The source and target databases must have the same time zone.
- The source and target databases must have the same character set and NLS character set.
- The source compatible version must be set to the same or a lower version than the target database.

6.4 Target Database Requirements

- The target container database must not have any tablespaces sharing the same name as tablespaces at the source database. If a source database tablespace exists at the target level, then Data Pump will throw an error. Following are the other pre-requisites:
 - The source database must be at least Oracle Database 11.2.0.4.
 - This feature will only be available in Oracle Database 19c (19.24).
For the target database, ensure that it contains the fix available in 35564253.
Any source tablespace to be migrated should not exist on the target database, otherwise the Data Pump import will fail.
- SYSDBA is needed for hybrid migration source and target database users. This is because ZDM uses RMAN to run tablespace metadata import/export.

6.5 Encryption Requirements

- For TDE encrypted source databases, with encrypted tablespaces, configure TDE at the target level as well.
- To provide the source and target TDE passwords, you can::
 - Use the ZDMCLI command line with `zdmcli migrate database`
 - * `-tdekeystorepasswd` for the source database
 - * `-tgttdekeystorepasswd` for the target database
 - Use the following response file parameters:
 - * * [WALLET_TDEKEYSTORE](#) for the source database.
 - * * [WALLET_TGTTDEKEYSTORE](#) for the target database.
- Migrated unencrypted source databases will not result in an encrypted target database, you must perform the encryption at the target level post migration.

6.6 Intermediate Storage Requirements

The NFS or shared storage between the source and the target database should have sufficient storage to hold all the RMAN backups and Data Pump dump files. You can specify the compression for the RMAN backups which should result in space reduction, however, conservatively, ensure that the space should be at-least as large as the size of the source database. You can specify the RMAN compression using the [RMANSETTINGS_COMPRESSIONALGORITHM](#) parameter.

6.7 Connectivity Requirements

The connectivity requirements for hybrid migration are same as physical and logical migration. You must have SSH connectivity for the source and target databases. You must have the SQL*Net connectivity between ZDM server and the source and the target database.

For SSH setup, refer to the following topics:

- [Setting Up SSH Key Based Authentication](#)
- [Physical and Logical Migration with SSH Access](#)

For SQL*Net setup, refer to the [Physical and Logical Migration with SSH Access](#) topic.

6.8 Preparing for a Hybrid Offline Migration

Create a response file after following the pre-requisites. Following is a sample file with the minimum required parameters. You can replace the parameters with values pertaining to your environment:

```
MIGRATION_METHOD=OFFLINE_XTTS
DATA_TRANSFER_MEDIUM=NFS
SOURCEDATABASE_ADMINUSERNAME= source database admin username
SOURCEDATABASE_CONNECTIONDETAILS_HOST= hostname or ip address
SOURCEDATABASE_CONNECTIONDETAILS_SERVICENAME= source service name or alias
SOURCEDATABASE_CONNECTIONDETAILS_PORT= listener port number
TARGETDATABASE_ADMINUSERNAME= source database admin username
TARGETDATABASE_CONNECTIONDETAILS_HOST= hostname or ip address
TARGETDATABASE_CONNECTIONDETAILS_PORT= listener port number
TARGETDATABASE_CONNECTIONDETAILS_SERVICENAME= target service name or alias
DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_NAME= name of the directory object
DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_PATH= path of the directory object
DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_NAME= name of the directory object
DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_PATH= path of the directory object
WALLET_TARGETADMIN= wallet path
WALLET_SOURCEADMIN= wallet path
```

Related Topics

- [Zero Downtime Migration Hybrid Migration Response File Parameters Reference](#)

6.9 Migrating the Database

After following the pre-requisites and after creating a response file, follow this sample migration command with the minimum required options and replace it with the values pertaining to your environment:

```
$ZDM_HOME/bin/zdmcli migrate database
-sourcesid source_oracle_sid
    (use this parameter if the source is a single instance DB without Grid
    Infrastructure)
otherwise use
-sourcedb source_db_unique_name_value (use this
    parameter if the source is configured with Grid Infrastructure)
-sourcenode
    source-db-host-name
-srcauth zdmauth
-srcarg1 user:source_database_server_login_user_name
-srcarg2 identity_file:ZDM_installed_user_private_key_file_location
-srcarg3 sudo_location:/bin/sudo
-targetnode target-db-host-name
-rsp /home/zdmuser/hybrid_online.rsp
-tgtauth zdmauth
-tgtarg1 user:target_database_server_login_user_name
-tgtarg2 identity_file:ZDM_installed_user_private_key_file_location
-tgtarg3 sudo_location:/usr/bin/sudo
```

6.10 Troubleshooting

For troubleshooting, review the following logs:

- ZDM Server Logs: `$ZDM_BASE/crsdata//rhp/zdmserver.log.XYZ`
- ZDM perl logs on source: `$ORACLE_BASE/zdm_<db_unique_name_<zdm job id>/log/`
- ZDM perl logs on target: `$ORACLE_BASE/zdm_<db_unique_name_<zdm job id>/log/`
- Export log file from the location specified for the entry
`DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_PATH` in the response file
- Import log file from the location specified for the entry
`DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_PATH` in the response file

Following are the workflow phases as well as their brief description in order of their execution:

Phase name	Description
ZDM_VALIDATE_TGT	Performs validations at the target
ZDM_VALIDATE_SRC	Perform validations at the source
ZDM_SETUP_XTTS_SRC	Sets up Zero Downtime Migration helper modules on the source server
ZDM_SETUP_XTTS_TGT	Sets up Zero Downtime Migration helper modules on the target server

Phase name	Description
ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC	Validates the export directory object (if applicable), and checks for sufficient space and permission for specified user in the source database to export dumps.
ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT	Verifies that the Data Pump import directory object exists.
ZDM_VALIDATE_XTTS_SRC	Performs XTTS related validations at the source such as self-containment of tablespaces
ZDM_VALIDATE_XTTS_TGT	Performs XTTS related validations at the target such as ensuring tablespaces names are not in use already which are part of migration
ZDM_XTTS_BACKUP_FULL_SRC	Performs full backup of the sourcetablespace (Initial L0)
ZDM_XTTS_BACKUP_INCR_SRC	Second backup of the source tablespaces (First L1)
ZDM_XTTS_COPYFILES	Copies files needed to perform restore at target such as source discovery file, transport xml, any TDE wallets.
ZDM_XTTS_RESTORE_FULL_TGT	Performs Initial restore of the tablespaces at the target
ZDM_XTTS_BACKUP_INCR_RO_SRC	Sets the tablespaces to read only and takes the third & final backup of the tablespaces (Second L1). Additionally RMAN exports the datapump dump of the metadata of tablespaces
ZDM_XTTS_COPYFILES_RO	Copies files needed to perform restore at target such as the latest transport xml and TDE wallets to account for any changes to the wallet
ZDM_PREPARE_DATAPUMP_SRC	Creates a new directory object for Data Pump, if required.
ZDM_PREPARE_DATAPUMP_TGT	Creates a new directory object for Data Pump, if required.
ZDM_DATAPUMP_EXPORT_METADATA_SRC	Performs export any additional source meta data other than the tablespace meta data exported by RMAN datapump execution such as Users, PL/SQL, Triggers, and so on.
ZDM_TRANSFER_DUMPS_METADATA_SRC	
ZDM_DATAPUMP_IMPORT_USER_TGT	Imports Users and Profiles as the first import so that the subsequent tablespace import can succeed
ZDM_XTTS_RESTORE_INCR_TGT	Executes RMAN to perform the final restore and import of the tablespace metadata exported by RMAN during ZDM_XTTS_BACKUP_INCR_RO_SRC phase
ZDM_DATAPUMP_IMPORT_TGT	Imports any additional metadata other than users, profiles & tablespaces not performed in previous imports
ZDM_POST_DATAPUMP_SRC	Removes any Data Pump directory object created by Zero Downtime Migration
ZDM_POST_DATAPUMP_TGT	Fixes any invalid objects in the target database.
ZDM_REFRESH_MVIEW_TGT	
ZDM_POST_ACTIONS	
ZDM_CLEANUP_SRC	Performs clean up at the source such as removing helper modules copied during the setup phase

Phase name	Description
ZDM_CLEANUP_TGT	Performs clean up at the target such as removing helper modules copied during the setup phase

See the [Zero Downtime Migration Hybrid Migration Response File Parameters Reference](#) topic for details related to these parameters. The following parameters are applicable for hybrid migration:

- MIGRATION_METHOD=OFFLINE_XTTS
- DATA_TRANSFER_MEDIUM=NFS
- SOURCEDATABASE_CONNECTIONDETAILS_HOST
- SOURCEDATABASE_CONNECTIONDETAILS_PORT
- SOURCEDATABASE_CONNECTIONDETAILS_SERVICENAME
- SOURCEDATABASE_ADMINUSERNAME
- TARGETDATABASE_CONNECTIONDETAILS_HOST
- TARGETDATABASE_CONNECTIONDETAILS_PORT
- TARGETDATABASE_CONNECTIONDETAILS_SERVICENAME
- TARGETDATABASE_ADMINUSERNAME
- DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_NAME
- DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_PATH
- DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_NAME
- DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_PATH
- DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXPORTPARALLELISMDEGREE
- DATAPUMPSETTINGS_DATAPUMPPARAMETERS_IMPORTPARALLELISMDEGREE
- DATAPUMPSETTINGS_DATAPUMPPARAMETERS_NOCLUSTER=FALSE
- DATAPUMPSETTINGS_EXPORTVERSION
- DUMPTRANSFERDETAILS_PUBLICREAD=FALSE
- IGNOREEXPORTERERRORS
- IGNOREIMPORTERERRORS
- RMANSETTINGS_BACKUPTAG
- RMANSETTINGS_COMPRESSIONALGORITHM=MEDIUM
- RMANSETTINGS_PUBLICREAD=FALSE
- RMANSETTINGS_RETENTIONWINDOW
- RMANSETTINGS_SECTIONSIZE=64G
- RMANSETTINGS_SRCCHANNELS=10
- RMANSETTINGS_TGTCHANNELS=10
- SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE
- SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP
- SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT

- SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP
- SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME
- SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME
- SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT
- SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL
- SOURCEDATABASE_ENVIRONMENT_DBTYPE=ORACLE
- SOURCEDATABASE_ENVIRONMENT_NAME=ORACLE
- TABLESPACEDETAILS_EXCLUDE=
- TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE
- TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP
- TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT
- TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP
- TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME
- TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME
- TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT
- TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL
- TARGETDATABASE_DBTYPE
- WALLET_DATAPUMPENCRYPTION
- WALLET_SOURCEADMIN
- WALLET_TARGETADMIN
- WALLET_TDEKEYSTORE
- WALLET_TGTTDEKEYSTORE
- WALLET_USERACTION

Performing Migration Using the Instant Deploy Feature

ZDM introduces migration using the instant deploy feature. The instant deploy feature mode in ZDM simplifies the migration of database from on-premises to OCI or EXADATA systems by skipping the need for dedicated compute for ZDM service.

The instant deploy feature has the following features:

- The Instant Deploy is a lightweight, downloadable software package that lets you run Zero Downtime Migration (ZDM) directly, without having to install or maintain a separate ZDM server.
- You use the same `zdmcli` commands and user experience as standard ZDM, however without installing or starting a persistent service.
- The CLI launches the migration and provides live progress updates.
- You can run the ZDM instant deploy tool in the same database host that is being migrated.
- The instant deploy feature enables Oracle to facilitate database migrations for you with minimal infrastructure requirements.

Key benefits

- No ZDM server setup: download and run; no separate service to install or maintain.
- Familiar CLI: use the same `zdmcli` commands you already know.
- Run where it is convenient: on the ZDM host, on the source DB node, or on the non-ADB target DB node.
- Flexible data movement: Direct, OCI Object Storage, or NFS.
- Minimal infrastructure: suitable for constrained or single-host scenarios.

Before you start

- **Permissions:** You need OS-level access and, when applicable, sudo privileges on source/target nodes.
- **Connectivity:** Ensure network connectivity between nodes (for remote execution) and required firewall rules/ports. - SSH: If running across nodes, ensure SSH trust or provide SSH user/keyoptions.
- **Storage:** - Object Storage: Have bucket name and tenancy URL, and a user with permissions to upload/download.
- **NFS:** Have a shared path accessible from source and target.
- **Direct:** Ensure connectivity and bandwidth for direct transfer.
- **Space:** Ensure adequate free space for backups/dumps and logs on involved hosts.

Install and update

- Instant Deploy is ready to use after download; no installation step is required.
- To update the kit in instant deploy mode: `./zdminstall.sh update oraclehome=<zdm_home> ziploc=<path_to_zdm_zip>-serverless`

Check the mode

To confirm you are in instant deploy mode:

```
zdm service status
```

Note

The start or stop commands are not applicable in instant deploy mode.

Logical migrations

- Run with a response file (required). Non-response workflow is not supported for logical migrations.
- You can run the command on the ZDM host, the source DB node, or the non-ADB target DB node.

Basic command

```
zdmcli migrate database -rsp /path/to/logical_migration.rsp
```

Note

- If you run on the source node and want to run CPAT locally, set `RUNCPATREMOTELY=TRUE` in the response file or use `-skipadvisor` on the command.
- For Object Storage, ensure the side that needs to transfer files (source for uploads, target for downloads) has an appropriate method configured in the response file. If not configured, ZDM provides a manual upload link when needed.

Examples

Target is Autonomous Database (ADB), run from any allowed node:

```
zdmcli migrate database -rsp /home/opc/logical_migration.rsp
```

Target is non-ADB, run from source node with SSH to target:

```
zdmcli migrate database -rsp /home/opc/logical_migration.rsp -targetnode  
<target_node_ip>  
-tgtauth zdmauth  
-tgtarg1 user:<user>  
-tgtarg2identity_file:/home/<user>/.ssh/id_rsa  
-tgtarg3  
sudo_location:/usr/bin/sudo
```

Target is non-ADB, run from source node without SSH (local operations only on the source; target retrieves from Object Storage or shared storage as configured):

```
zdmcli migrate database -rsp /home/opc/logical_migration.rsp
```

Target is non-ADB; run from the target node with SSH access to the source:

```
./zdmcli migrate database
-rsp /home/opc/logical_migration.rsp
-sourcenode <source_node_ip>
-srcauth zdmauth
-srcarg1 user:<user>
-srcarg2 identity_file:/home/<user>/.ssh/id_rsa
-srcarg3 sudo_location:/usr/bin/sudo
```

Target is non-ADB; run from the target node without SSH access to the source (local operations only on the target; source uploads dump files to Object Storage as configured in the response file):

```
./zdmcli migrate database -rsp /home/opc/logical_migration.rsp
```

Physical migrations

- Response file is optional for physical migrations. If you omit `-rsp`, specify the key parameters inline.
`[-migrationmethod]` : Specifies the migration method. Values can be `OFFLINE_PHYSICAL` or `ONLINE_PHYSICAL`.
`[-targetdb]` : Target database name, mandatory parameter if the response file is not used.
 If `-migrationmethod` is not specified, `ONLINE PHYSICAL` migration method is chosen by default.
 OSS (Object Storage Service):
`-backupuser`: Username for OSS backup.
`-ossbucket`: Name of the OSS bucket.
`-ossurl`: URL of the OSS host.
 NFS (Network File System):
`-backuppath`: Shared NFS path between the source and target databases.
- If you run on a node that is also participating in the migration (source or target), ZDM handles local execution automatically; you do not need to specify special plugins for local nodes.
- For remote nodes, provide SSH details using `-sourcenode/-targetnode withuser/key/sudo` args.

Note

If you want to modify the default RSP details, there are template response files, located at the `<zdmkit_dir>/template/<version>` directory.

Select a data transfer method

1. Direct (no extra parameters required apart from the basic ones)

```
zdmcli migrate database -sourcedb <src_db_name> -targetdb <tgt_db_name> -
targetnode
<target_node_ip>
```

2. Object Storage

```
zdmcli migrate database -sourcedb <src_db_name> -targetdb <tgt_db_name> -
targetnode <target_node_ip> -backupuser<obj_storage_user> -ossbucket
<bucket_name> -ossurl https://objectstorage.<region>.oraclecloud.com
```

3. NFS

```
zdmcli migrate database -sourcedb <src_db_name> -targetdb <tgt_db_name> -
targetnode <target_node_ip> -backuppath/mnt/shared/backup
```

Running locations and SSH options

- From ZDM host: Works as standard ZDM; physical migration supports both response-file and non-response workflows.
- From source node:
With default SSH configured to target:

```
zdmcli migrate database -sourcedb <src_db_name> -targetdb <tgt_db_name> -
targetnode <target_node_ip>
```

With custom SSH:

```
zdmcli migrate database
-sourcedb <src_db_name>
-targetdb <tgt_db_name>
-targetnode <target_node_ip>
-tgtauth zdmauth
-tgtarg1 user:<user>
-tgtarg2 identity_file:/path/to/key
-tgtarg3
sudo_location:/usr/bin/sudo
```

Note

On the source local node, migration can be performed using either a DB user or a non-DB user. The same user will be used to execute local commands on the source database, as well as to establish the remote target connection, unless custom SSH details are provided. If you just want to change the remote target connection user, you can specify it using `-tgtuser <target_user>` in the command.

The target user must have sudo privileges on the target system to execute commands as the database user and the Grid home user.

- From non-ADB target node:
With default SSH configured to source:

```
zdmcli migrate database -sourcedb <src_db_name> -targetdb <tgt_db_name> -
sourcenode<source_node_ip>
```

With custom SSH:

```
zdmcli migrate database
-sourcedb <src_db_name>
-targetdb <tgt_db_name>-sourcenode <source_node_ip>
-srcauth zdmauth
```

```
-srcarg1 user:<user>  
-srcarg2 identity_file:/path/to/key  
-srcarg3sudo_location:/usr/bin/sudo
```

Note

On the target local node, the migration user must have sudo privileges. You will be responsible for executing local commands on the target database and for connecting to the remote source, unless you specify custom SSH details.

Hybrid migration:

From the ZDM host: This works the same as a standard ZDM migration and supports only the response-file-based workflow. Hybrid migration from the local source or target node is not supported.

Templates and automation

- The kit includes template response files for both logical and physical migrations. You can copy and modify these templates to suit your environment.
- For physical migrations, you can also run without a response file by specifying parameters inline.
- The kit provides pre/post action templates you can populate with your scripts to automate checks or custom steps across migration phases.

Tips and limitations

- Logical migration requires a response file; physical migration supports non-response workflow.
- If using Object Storage, ensure the correct side has upload/download configured; otherwise you may be prompted to upload manually.
- `zdm service start` and `zdm service stop` are not used in instant deploy mode; use `zdm service status` to confirm the mode.

8

Customizing a Migration Job

You can customize the Zero Downtime Migration work flow with scripts which can be run at the beginning or end of a specified migration job phase. In Zero Downtime Migration, these customizations are called **custom plug-ins with user actions**.

The following topics describe how to customize a migration job.

8.1 About Custom Plug-ins with User Actions

In Zero Downtime Migration, a custom script, or bundle of scripts, that you want to plug in and run as part of a migration job is called a **custom plug-in with user action**.

A custom plug-in with user action, which is also referred to as a **user action**, is associated with an operational phase in the migration job and can be run before the phase or after it.

A **pre-action** is a user action performed at the beginning of the associated phase. Likewise, a **post-action** is performed at the end of the associated phase.

Once a user action is associated with a migration phase, Zero Downtime Migration copies it to the respective node (for non-Autonomous Databases) and runs the user action locally. Zero Downtime Migration supplies the user action script execution with a set of parameters for developers to use the DBNAME, DBHOME, DB SCAN and ZDM log locations, and many more parameters.

For Autonomous Database, Zero Downtime Migration allows SQL to be registered as a user action and executes the SQL in an Autonomous Database instance from the Zero Downtime Migration server through a JDBC connection.

8.2 Parameters Supplied for Custom Plug-ins with Shell Script User Actions

At run time, Zero Downtime Migration invokes the user action script and supplies it with set of auto-populated environment variables that can be used to program the logic.

These variables are supplied as environment variables with values so you can program the custom plug-in using these values.

For example, the value of `ZDM_SRCDBHOME` specifies the database home associated with the current migration job source database, and similarly `SRC_SCAN_NAME` indicates the scan listener information for the source database that you can use to connect to the database.

The following is a listing of the user action parameters with expected values. See the footnotes for more details.

```
ZDM_OPTYPE=MIGRATE_DATABASE
ZDM_PHASE=PRE
ZDM_SRCDB=src_db_name
ZDM_SRCDBHOME=src_db_home
ZDM_TARGETDB=tgt_db_name
```

```

ZDM_TARGETDBHOME=tgt_db_home
ZDM_PROGRESSLISTENERHOST=zdm_node_name
ZDM_PROGRESSLISTENERPORT=zdm_progress_listener_port
SRC_SCAN_NAME=src_scan_name
SRC_SCAN_PORT=src_scan_port
TGT_SCAN_NAME=tgt_scan_name
TGT_SCAN_PORT=tgt_scan_port
ZDM_USERACTIONDATA=user_action_data1
ZDM_OP_PHASE=current_job_phase2
RHP_UA_CHAIN_LIST=list_of_useractions3
ZDM_SRCDBSID=src_db_sid
ZDM_TGTDBSID=tgt_db_sid
ZDM_VERSION=zdm_version
ZDM_CLI=zdm_command
TGT_LOG_PATH= tgt_log_path4
SRC_LOG_PATH=src_log_path5
TGT_DB_SERVICE=tgt_db_service
SRC_DB_SERVICE=src_db_service
ZDM_DATAPUMP_EXPORT_DIR_NAME=DATA_PUMP_DIR_NAME
ZDM_DATAPUMP_EXPORT_DIR_PATH=data_pump_dir_path
ZDM_DATAPUMP_DUMP_PREFIX=data_pump_prefix
ZDM_SRCDBPDB= <the pdb name of the source database>
ZDM_TGTDBPDB=<the pdb name of the target database> Note: This is populated
using: SQL> 'SELECT * FROM DBA_PDBS'

```

¹ZDM_USERACTIONDATA specifies the useraction argument that was specified in `zdmcli migrate database` command option `-useractiondata user_action_data`

²ZDM_OP_PHASE specifies the current phase of the migration job, for example, ZDM_VALIDATE_SRC.

³ZDM_UA_CHAIN_LIST is passed to every user action execution call. This parameter holds the list of user actions chained to the executing user action. Chained user actions are the user actions whose output will be supplied to the executing user action.

⁴ TGT_LOG_PATH specifies the target node Zero Downtime Migration log path for the custom plug-in to store any log files for future reference.

⁵ SRC_LOG_PATH specifies the source node Zero Downtime Migration log path for the custom plug-in to store any log files for future reference.

8.3 Variables Supplied for Custom Plug-ins with SQL Based User Actions

SQL based user actions are used for databases where the database node is not accessible, for example, Oracle Autonomous AI Database (ADB).

For SQL based user actions, the following variables are supplied:

- **AS_USER:** The user action will be executed by this database user. This user is set while creating the user action using the `-asuser` option.
- **ORACLE_HOME:** The home path of the database.
- **ACTION_OUTPUT_DIR:** Directory where the output of all user actions will be stored for the ongoing migration.

- `OUTPUT_FILE` - This gives the full path to the output file on which the user action output will be stored in the following format of the variable value: `<ACTION_OUTPUT_DIR>/<USER_ACTION_NAME>.out`

You can access the above variables with the SQL user action by specifying the variable with a `:` before it. For example, `:ACTION_OUTPUT_DIR` in the SQL will be replaced by the actual `ACTION_OUTPUT_DIR`.

8.4 User Action Scripts

You can use the following example user action scripts to help you create your own scripts.

For an on-premises source and Cloud target with node access, Zero Downtime Migration requires that the user action be a script. The script file is copied over to the respective node and is executed locally.

You can specify the service name alias to be used for executing the specific user action. If you do not specify the service name alias, then ZDM will connect with the service specified in the response parameter file. You can specify the required service alias as a first line comment in the user action script as follows:

```
--USERACTION_SERVICE=<SERVICE NAME ALIAS from tnsnames for example TP or
TP_TLS>
```

For example :

```
--USERACTION_SERVICE=TP or
--USERACTION_SERVICE=LOW
```

This is followed by the actual SQLs.

For Autonomous Database targets, Zero Downtime Migration requires that the user action script be a SQL file (.sql), which is executed in the Autonomous Database target using a JDBC connection.

Example 8-1 action.sh

Shown here is a sample user action script that discovers the supplied parameters.

```
#!/bin/sh

for var in $@
do
  if [[ ${var} == *"ZDM_SRCDB="* ]]
  then
    IFS=' ' read -ra DBARR <<< "${var}"
    SRCDBNAME=${DBARR[1]}
  fi
  if [[ ${var} == *"ZDM_TARGETDB="* ]]
  then
    IFS=' ' read -ra DBARR <<< "${var}"
    TARGETDBNAME=${DBARR[1]}
  fi
  if [[ $var == *"ZDM_SRCDBHOME="* ]]
  then
    IFS=' ' read -ra PATHARR <<< "$var"
```

```

SRCDBHOME=${PATHARR[1]}
fi
if [[ $var == *"ZDM_TARGETDBHOME="* ]]
then
IFS=' ' read -ra PATHARR <<< "$var"
TARGETDBHOME=${PATHARR[1]}
fi
if [[ $var == *"ZDM_OP_PHASE="* ]]
then
IFS=' ' read -ra PHASEARR <<< "$var"
ZDMPHASE=${PHASEARR[1]}
fi
if [[ $var == *"eval"* ]]
then
IFS=' ' read -ra PATHARR <<< "$var"
EVALRUN=${PATHARR[1]}
fi
if [[ $var == *"LOG_PATH"* ]]
then
IFS=' ' read -ra PATHARR <<< "$var"
LOGPATH=${PATHARR[1]}
fi
done

echo "`date` Starting CUSTOM_USERACTION" >> $LOG_PATH/
CUSTOM_USERACTION.log
echo $@ >> $LOG_PATH/CUSTOM_USERACTION.log

```

Example 8-2 Running SQL*Plus in a user action

```

#!/bin/sh

for var in $@
do
if [[ ${var} == *"ZDM_SRCDB="* ]]
then
IFS=' ' read -ra DBARR <<< "${var}"
SRCDBNAME=${DBARR[1]}
fi
if [[ ${var} == *"ZDM_TARGETDB="* ]]
then
IFS=' ' read -ra DBARR <<< "${var}"
TARGETDBNAME=${DBARR[1]}
fi
if [[ $var == *"ZDM_SRCDBHOME="* ]]
then
IFS=' ' read -ra PATHARR <<< "$var"
SRCDBHOME=${PATHARR[1]}
fi
if [[ $var == *"ZDM_TARGETDBHOME="* ]]
then
IFS=' ' read -ra PATHARR <<< "$var"
TARGETDBHOME=${PATHARR[1]}
fi
if [[ $var == *"ZDM_OP_PHASE="* ]]

```

```

then
IFS=' ' read -ra PHASEARR <<< "$var"
ZDMPHASE=${PHASEARR[1]}
fi
if [[ $var == *"eval"* ]]
then
IFS=' ' read -ra PATHARR <<< "$var"
EVALRUN=${PATHARR[1]}
fi
if [[ $var == *"LOG_PATH"* ]]
then
IFS=' ' read -ra PATHARR <<< "$var"
LOGPATH=${PATHARR[1]}
fi
done

check_dv_staus()
{
    export ORACLE_HOME=${2}
    export PATH=${ORACLE_HOME}/bin:$PATH
    export LOGFILE=${3}
    export currenthostname=`hostname -a` >> $LOGFILE
    echo "Current DB Host=$currenthostname" >> $LOGFILE
    CURRENTNODE=`srvctl status database -db ${1} | grep $currenthostname
| cut -d" " -f2` >> $LOGFILE
    SQLRETURN=?
    echo "Curent DB Node=${CURRENTNODE}" >> $LOGFILE
    if [ "$SQLRETURN" -ne "0" ]; then
        return 1
    fi
    export ORACLE_SID=${CURRENTNODE}
    echo "`date` Checking Database Vault Status" >> $LOGFILE
    $ORACLE_HOME/bin/sqlplus -s / as sysdba 2>> $LOGFILE << EOF > /dev/
null
    whenever sqlerror exit 1
    SET PAGESIZE 60
    SET LINESIZE 1300
    SET VERIFY OFF TRIMSPOOL ON HEADING OFF TERMOUT OFF FEEDBACK OFF
    spool ${LOGFILE} append;

    SELECT 'Check Status : ' || PARAMETER FROM V$OPTION WHERE PARAMETER =
'Oracle Database Vault' AND VALUE='TRUE';
    SELECT 'Check Grant : ' || GRANTED_ROLE from dba_role_privs where
GRANTED_ROLE in ('DV_PATCH_ADMIN') and grantee='SYS';
    select distinct ('Check TDE enabled ' || ENCRYPTED) from
dba_tablespace where ENCRYPTED='YES';
    spool off
    EOF
    SQLRETURN=?
    if [ "$SQLRETURN" -ne "0" ]; then
        return 1
    fi

    if grep -q "Check Status : Oracle Database Vault" $LOGFILE;
    then
        echo "`date`: ${ORACLE_SID}:Database Vault is enabled " >> $LOGFILE

```

```

        if grep -q "Check Grant : DV_PATCH_ADMIN" $LOGFILE;
        then
            return 3 # sys privs already granted
        else
            return 4 # sys privs are not granted
        fi
    else
        echo "`date`: $ORACLE_SID: DV is not enabled" >> $LOGFILE
        return 2
    fi
}

if [[ $ZDMPHASE == "ZDM_VALIDATE_SRC" || $ZDMPHASE == "ZDM_VALIDATE_TGT" ]]
then
    export LOGFILE=$LOG_PATH/${SRCDBNAME}_${ZDMPHASE}_datavault.log
    echo "`date` Start User Action for Phase: $ZDMPHASE " > $LOGFILE
    echo $@ >> $LOGFILE
    check_dv_staus $SRCDBNAME $SRCDBHOME $LOGFILE
    CHECKDV_STATUS_RETURN_CODE=$?
    if [ "$CHECKDV_STATUS_RETURN_CODE" -eq "1" ]; then
        echo "`date`: ${SRCDBNAME}: Unable to check DataVault status" >> $LOGFILE
        exit 1
    fi

    if [ "$CHECKDV_STATUS_RETURN_CODE" -eq "2" ]; then
        echo "`date`: ${SRCDBNAME}: DataVault is not enabled " >> $LOGFILE
        exit 0
    fi

    if [ "$CHECKDV_STATUS_RETURN_CODE" -eq "3" ];
    then
        echo "`date`: ${SRCDBNAME}: Database Vault SYS privileges granted"
    >> $LOGFILE
        exit 0
    fi
fi

```

Example 8-3 Action file archive extractor action_extract.sh

If you bundle more than one user action into an action file, as described in [Registering User Actions](#), you must also supply a script that unzips the action file, as shown in this example.

```

#!/bin/sh
MKDIR=/bin/mkdir
DATE=/bin/date
UNZIP=/usr/bin/unzip
#get the current location, extract path from it and then from the same
directory perform unzip to /tmp directory
script_path=$0
script_dir=${script_path%/*}
timestamp=$( $DATE +%s)
unzip_dir=/tmp/rhp_${timestamp}
$MKDIR $unzip_dir
$UNZIP ${script_dir}/pack.zip -d $unzip_dir

```

```
echo "/bin/sh ${unzip_dir}/pack/main.sh $@"
/bin/sh ${unzip_dir}/pack/main.sh "$@"
```

Once the archive is extracted, `action_extract.sh` runs `main.sh`, which in turn runs any user action scripts.

```
#!/bin/sh
script_path=$0
script_dir=${script_path%/*}
#extract args and execute all scripts
echo "/bin/sh ${script_dir}/wc_add_pre.sh $@"
/bin/sh ${script_dir}/wc_add_pre.sh "$@"
```

`action_phase_pre.sh`

```
#!/bin/sh
touch /tmp/SAMPLE_PRE_OUT.txt;
echo $* >> /tmp/SAMPLE_PRE_OUT.txt;
```

8.5 User Action for Oracle Autonomous AI Database Target and Amazon Web Services RDS Source

You can create user action scripts with SQL commands when the source database is Oracle Database from Amazon Web Services (AWS) RDS and the target database is Oracle Autonomous AI Database (ADB).

Oracle Database from Amazon Web Services (AWS) RDS source and Oracle Autonomous AI Database (ADB) target do not support shell script user actions. They support SQL-only user actions.

The SQL action is performed as user specified for accessing the Amazon Web Services RDS Source.

8.6 Registering User Actions

User actions must be registered with the Zero Downtime Migration service host to be plugged in as customizations for a particular operational phase.

Use the Zero Downtime Migration software installed user (for example, `zmduser`) to add user actions to a database migration job.

The `ZDMCLI` command `add useraction` registers a custom action script. The user action script, and any work flow options specified for when to run it, are copied to the Zero Downtime Migration metadata.

In the `add useraction` command, specify the following options.

- **-useraction *user_action_name*** (required)
Assign the user action a name.
- **-actionsript *script_name*** (required)
Provide the full path and script file name, for example, `/home/zmduser/useract.sh`.

- **-optype MIGRATE_DATABASE** (required)
Define the operation for which the user action is configured as `MIGRATE_DATABASE`.
- **-phase**
To run the script at the proper phase of the migration job work flow, specify the migration job phase that the action must be associated with. You can register custom plug-ins for phases after `ZDM_SETUP_TGT` in the migration job work flow.
See [Zero Downtime Migration Process Phases](#)
- **-pre and -post**
Indicate whether the user action should run before or after the specified phase.
- **-onerror**
You can specify a behavior if the user action encounters an error at runtime, which you can set to either `ABORT`, to end the process, or `CONTINUE`, to continue the migration job even if the custom plug-in exits with an error.
- **-asuser**
Allows you to specify the database user to run the SQL commands in the user action.
See [WALLET_USERACTION](#)

The following example shows you how to add user actions `zdmvaltgt` and `zdmvalsrc`.

```
zdmuser> $ZDM_HOME/bin/zdmcli add useraction
-useraction zdmvaltgt
-actionscript /home/zdmuser/useract.sh
-optype MIGRATE_DATABASE
-phase ZDM_VALIDATE_TGT
-pre
-onerror ABORT
-asuser dbuser
```

```
zdmuser> $ZDM_HOME/bin/zdmcli add useraction
-useraction zdmvalsrc
-actionscript /home/zdmuser/useract1.sh
-optype MIGRATE_DATABASE
-phase ZDM_VALIDATE_SRC
-pre
-onerror CONTINUE
-asuser dbuser
```

In the above commands, the scripts `useract.sh` and `useract1.sh`, specified in the `-actionscript` option, are copied to the Zero Downtime Migration service host repository meta data, and they are run if they are associated with any migration job run using an action template.

Running Multiple Scripts in One Action

If you need to run multiple scripts as a single user action, all of the action scripts can be bundled as an **action file** archive and supplied along with an action script, as shown in the following example. The action script should unzip the action file and invoke the scripts within.

```
zdmuser> $ZDM_HOME/bin/zdmcli add useraction
-useraction reconfigure_services
```



```
-actionsript /home/zdmuser/action_extract.sh
-actionfile /home/zdmuser/pack.zip
-optype MIGRATE_DATABASE
-phase ZDM_RECOVER_TGT
-post
-onerror ABORT
```

For example scripts and script requirements, see [User Action Scripts](#).

For information about other options you can use with the ZDMCLI command `add useraction` see `add useraction`

8.7 Creating an Action Template

After the `useraction` plug-ins are registered, you create an action template that combines a set of action plug-ins which can be associated with a migration job.

An action template is created using the ZDMCLI command `add imagetype`, where the image type, `imagetype`, is a bundle of all of the `useractions` required for a specific type of database migration. Create an image type that associates all of the `useraction` plug-ins needed for the migration of the database. Once created, the image type can be reused for all migration operations for which the same set of plug-ins are needed.

The base type for the image type created here must be `CUSTOM_PLUGIN`, as shown in the example below.

For example, you can create an image type `ACTION_ZDM` that bundles both of the `useractions` created in the previous example, `zdmvalsrc` and `zdmvaltgt`.

```
zdmuser> $ZDM_HOME/bin/zdmcli add imagetype -imagetype ACTION_ZDM -basetype
CUSTOM_PLUGIN -useractions zdmvalsrc,zdmvaltgt
```

8.8 Associating an Action Template with a Migration Job

When you run a migration job you can specify the image type that specifies the plug-ins to be run as part of your migration job.

As an example, run the migration command specifying the action template `ACTION_ZDM` created in previous examples, `-imagetype ACTION_ZDM`, including the image type results in running the `useract.sh` and `useract1.sh` scripts as part of the migration job workflow.

By default, the action plug-ins are run for the specified operational phase on all nodes of the cluster. If the access credential specified in the migration command option `-tgtarg2` is unique for a specified target node, then an additional `auth` argument should be included to specify the `auth` credentials required to access the other cluster nodes. For example, specify `-tgtarg2 nataddrfile:auth_file_with_node_and_identity_file_mapping`.

A typical `nataddrfile` for a 2 node cluster with `node1` and `node2` is shown here.

```
node1:node1:identity_file_path_available_on_zdm_service_node
node2:node2:identity_file_path_available_on_zdm_service_node
```

8.9 Querying Action Plug-ins

You can query action plug-ins registered with the Zero Downtime Migration service host.

To display the configuration of a user action:

```
zdmuser> $ZDM_HOME/bin/zdmcli query useraction -useraction user_action_name
```

See [query useraction](#) for usage information.

8.10 Updating Action Plug-ins

You can update a registered Zero Downtime Migration user action plug-in configuration.

The following example shows you how to modify the user action `zdmvalsrc` to run the user action script after phase `ZDM_VALIDATE_SRC` instead of before it.

```
zdmuser> $ZDM_HOME/bin/zdmcli modify useraction
-useraction zdmvalsrc
-phase ZDM_VALIDATE_SRC
-optype MIGRATE_DATABASE
-post
```

This change is propagated to all of the associated action templates, so you do not need to update the action templates.

To modify a user action script and update the user action, follow the instructions in [Modifying User Action Scripts](#).

8.11 Modifying User Action Scripts

You can edit a user action script locally and use the ZDMCLI command `modify useraction` to update the script in the user action metadata.

1. If you do not have a local copy of the script, you can locate the cached user action script in the user action metadata using the ZDMCLI command `query useraction`.

```
zdmuser> $ZDM_HOME/bin/zdmcli query useraction
-useraction zdmvalsrc
```

The full base path to the script is displayed.

Note

Do not directly modify the script in the location shown in the command output.

2. Copy the script to a temporary location and edit it.

3. Update the script in the user action metadata using the ZDMCLI command `modify useraction`.

```
zdmuser> $ZDM_HOME/bin/zdmcli modify useraction
-useraction zdmvalsrc
-actionscript /home/zdmuser/useract1.sh
```

8.12 Modifying an Action Template

You can modify an action template to change the set of action plug-ins associated with a migration job.

An action template is modified using the ZDMCLI command `modify imagetype`. This command is useful if you register a new user action script and you want to add it to an existing template.

For example, to add a new user action named `zdmclonetgt` to image type `ACTION_ZDM`, run `modify imagetype` with the new complete list of user actions as shown here:

```
zdmuser> $ZDM_HOME/bin/zdmcli modify imagetype -imagetype ACTION_ZDM
-useractions zdmvalsrc,zdmvaltgt,zdmclonetgt
```

8.13 Chained User Action Output

You can get data from one or more user actions and use that data to run another user action. For example, you can perform an action on the source database and use that data to perform an action on the target database.

When adding a user action, you can use the `-outputfrom` option to provide the list of user actions whose output will be supplied to the user action being added.

In the following example there are two user actions already registered in Zero Downtime Migration, `USERAC1` and `USERAC2`, both of which generate some output. This output can be used by a third user action, `USERAC3`, by listing them with the `-outputfrom` option, as shown here.

```
$ZDM_HOME/bin/zdmcli add useraction
-useraction USERAC3
-actionscript useractionscrip.sh
-outputfrom USERAC1,USERAC2
```

Accessing the Data

The output file is copied to the same location where the useraction file runs from, so the content of the output file can be accessed from the same location.

- On an Autonomous Database system:

To access the output file in an Autonomous Database system user action SQL script, use

```
@:ACTION_OUTPUT_DIR/useraction_name.out
```

Note that `ACTION_OUTPUT_DIR` indicates the directory where outputs will be stored, and `@` will replace this variable with the actual directory path.

For example, to use output from the `get_ddl1` user action, specify

```
@:ACTION_OUTPUT_DIR/get_ddl1.out;.
```

- On a Co-Managed database system:

To access the output file in a user action script run on a co-managed database system, use

```
OUTPUTFILE=$CURR_DIR/useraction_name.out;
```

Where CURR_DIR is the current directory where the target user action file and the output from the other user actions are placed.

For example, to use output from the get_ddl1 user action, specify

```
OUTPUTFILE=$CURR_DIR/get_ddl1.out;
```

The user action script must also contain the parameter RHP_UA_CHAIN_LIST which gives the list of chained user action names.

Example User Actions in an Autonomous Database Migration

The following example shows how to get DDL output from the source database, and runs it on the target database.

User action get_ddl1 runs on the source database and generates DDL output.

```
$ZDM_HOME/bin/zdmcli add useraction
-useraction get_ddl1
-phase ZDM_VALIDATE_SRC
-pre
-optype MIGRATE_DATABASE
-runscope ONENODE
-onerror ABORT
-actionscript /home/useraction1.sh
```

User action table_fromddl runs on the target database, and uses the output from user action get_ddl1.

```
$ZDM_HOME/bin/zdmcli add useraction
-useraction table_fromddl
-phase ZDM_VALIDATE_TGT
-pre
-optype MIGRATE_DATABASE
-runscope ONENODE
-onerror ABORT
-actionscript /home/useraction2.sh
-outputfrom get_ddl1
```

Adding both user actions to an imagetype:

```
$ZDM_HOME/bin/zdmcli add imagetype
-imagetype OUTPUTIMG1
-basetype CUSTOM_PLUGIN
-useractions get_ddl1,table_fromddl
```

Content of useraction1.sh:

```
#!/bin/sh

for var in $@
do
```

```

if [[ $var == *"ZDM_SRCDBHOME="* ]]
then
IFS=' ' read -ra PATHARR <<< "$var"
SRCDBHOME=${PATHARR[1]}
fi

if [[ $var == *"LOG_PATH"* ]]

then

IFS=' ' read -ra PATHARR <<< "$var"

LOGPATH=${PATHARR[1]}

fi
done

echo $SRCDBHOME;

ORACLE_HOME=$SRCDBHOME;
export ORACLE_HOME;
ORACLE_SID=zdm1121;
export ORACLE_SID;
export TMPLOG=/tmp/tmptmp.log;
true>$TMPLOG;
export PATH=$ORACLE_HOME/bin:$PATH
#echo "home is $ORACLE_HOME";
$ORACLE_HOME/bin/sqlplus -s / as sysdba 2>> $TMPLOG << EOF > /tmp/testlog
whenever sqlerror exit 1
SET PAGESIZE 60
SET LINESIZE 1300
SET VERIFY OFF TRIMSPOOL ON HEADING OFF TERMOUT OFF FEEDBACK OFF
spool ${TMPLOG} append;

select dbms_metadata.get_ddl('TABLE', 'TEST1') from DUAL;
spool off
EOF

SQLRETURN=$?
if [ "$SQLRETURN" -ne "0" ]; then
echo "Failed to run $SQLRETURN";
fi
sed -i 's/PCTFREE 10 PCTU//g' $TMPLOG;
echo "$(cat $TMPLOG)";

```

Content of useraction2.sh:

```

select name from v$database;
@:ACTION_OUTPUT_DIR/ZDM_VALIDATE_SRC_PRE_get_ddl1.out;
select name from v$database;

```

Example User Actions in a Co-Managed Database Migration

For this example, the add useraction and add imagetype commands are same as above in the Autonomous Database use case, but the script contents are different.

Content of useraction1.sh

```
#!/bin/sh

for var in $@
do
if [[ $var == *"ZDM_SRCDBHOME="* ]]
then
IFS=' ' read -ra PATHARR <<< "$var"
SRCDBHOME=${PATHARR[1]}
fi
done

ORACLE_HOME=$SRCDBHOME;
export ORACLE_HOME;
ORACLE_SID=zdmsrc1;
export ORACLE_SID;
export TMPLOG=/tmp/tmptmp.log;
true>$TMPLOG;
export PATH=$ORACLE_HOME/bin:$PATH
#echo "home is $ORACLE_HOME";
$ORACLE_HOME/bin/sqlplus -s / as sysdba 2>> $TMPLOG << EOF > /tmp/testlog
whenever sqlerror exit 1
SET PAGESIZE 60
SET LINESIZE 1300
SET VERIFY OFF TRIMSPOOL ON HEADING OFF TERMOUT OFF FEEDBACK OFF
spool ${TMPLOG} append;

select dbms_metadata.get_ddl('TABLE', 'TEST1') from DUAL;
spool off
EOF

SQLRETURN=$?
if [ "$SQLRETURN" -ne "0" ]; then
echo "Failed to run $SQLRETURN";
fi
echo "$(cat $TMPLOG)";
```

Content of useraction2.sh:

```
#!/bin/sh

for var in $@
do
if [[ $var == *"ZDM_TARGETDBHOME="* ]]
then
IFS=' ' read -ra PATHARR <<< "$var"
TARGETDBHOME=${PATHARR[1]}
fi
done

CURR_DIR=$(dirname "$(readlink -f "$0")")
export OUTPUTFILE=$CURR_DIR/get_ddl1.out;
# export ORACLE_HOME=/u01/app/oracle/product/19.0.0.0/dbhome_1;
ORACLE_HOME=$TARGETDBHOME;
```

```
export ORACLE_HOME;
ORACLE_SID=zdmnov19;
export ORACLE_SID;
export TMPLOG=/tmp/tmptmp.log;
sed -i 's/PCTFREE 10 PCTUS//g' $OUTPUTFILE;
export OUTPUT=$(cat $OUTPUTFILE);
echo $OUTPUT;
echo ">$TMPLOG;
$ORACLE_HOME/bin/sqlplus -s / as sysdba 2>> $TMPLOG << EOF > /tmp/testlog
whenever sqlerror exit 1
SET PAGESIZE 60
SET LINESIZE 1300
SET VERIFY OFF TRIMSPOOL ON HEADING OFF TERMOUT OFF FEEDBACK OFF
spool ${TMPLOG} append;

$OUTPUT;
spool off
EOF

echo "$(cat $TMPLOG)";
#SELECT 'NAME: ' || NAME FROM V\\$DATABASE;
```

8.14 Customizing Job to Setup Standby

Use the `-stopafter` option to create a standby on Cloud and stop the ZDM flow.

The `-stopafter` option truncates the work flow by the specified phase, and upon completion of the specified phase, the migration job is marked with status completed.

See [migrate database](#) for usage information.

9

Migrating Your Database with Zero Downtime Migration

Evaluate the database migration job, run the job, and perform other operations during and after a database migration.

See the Zero Downtime Migration Release Notes for the latest information about known issues, My Oracle Support notes, and runbooks.

9.1 Evaluate the Migration Job

Zero Downtime Migration provides options and tools for evaluating the migration job before you run it against the production database.

Ensure that you have met all of the prerequisites and completed the required preparations described in [Preparing for a Physical Database Migration](#) before you begin the migration procedures in this topic.

In addition be sure the following tasks are done:

- Obtain the necessary access credentials required.

If Oracle Cloud Infrastructure Object Storage is used as the backup medium, obtain the Object Storage access credential. The user ID for the Oracle Cloud Infrastructure Console user and an auth token for Object Storage is required. If you are not using an existing auth token, a new auth token can be generated using the Oracle Cloud Infrastructure Console.

If the source database server is accessed with the root user, then you need the root user password. If the source and target database servers are accessed with a private key file, then you need the private key file. The SYS password for the source database environment is also required.

If Zero Data Loss Recovery Appliance is used as the backup medium, get the Zero Data Loss Recovery Appliance virtual private catalog (VPC) user credentials.

- Prepare the Zero Downtime Migration response file.

The database migration is driven by a response file that captures the essential parameters for accomplishing the task.

Use the sample RSP templates in `$ZDM_HOME/rhp/zdm/template/` file for example entries needed to set up the response file for your particular source, target, and backup environments.

The `ZDMCLI migrate database` command has options to let you test the migration before you run it in production. The options are highlighted in the following syntax examples.

`ZDMCLI migrate database` syntax for an Autonomous Database migration:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-rsp file_path
-sourcedb source_db_unique_name_value
-sourcenode host
-srcauth zdmauth
```



```
-srcarg1 user:username
-srcarg2 identity_file:ssh_key_path
-srcarg3 sudo_location:sudo_path
-eval [-advisor [-ignoreadvisor] | -skipadvisor]]
```

ZDMCLI migrate database syntax for a co-managed database migration:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-rsp file_path
-sourcedb source_db_unique_name_value
-sourcenode host
-srcauth zdmauth
-srcarg1 user:username
-srcarg2 identity_file:ssh_key_path
-srcarg3 sudo_location:sudo_path
-targetnode host
-tgtauth zdmauth
-tgtarg1 user:username
-tgtarg2 identity_file:ssh_key_path
-tgtarg3 sudo_location:sudo_path
-eval [-advisor [-ignoreadvisor] | -skipadvisor]]
```

See the following topics for information about using the ZDMCLI migrate database options to evaluate your migration.

9.1.1 Using the ZDMCLI MIGRATE DATABASE -eval Option

Before submitting the database migration job for the production database, perform a test migration to determine how the process might fare with your configuration and settings.

It is highly recommended that for each migration job, you first run `migrate database` in evaluation mode. Evaluation mode allows you to correct any potential problems in the setup and configuration before performing the actual migration on a production database.

In evaluation mode, the migration process runs without effecting the changes. It is safe to run a migration job in evaluation mode as many times as needed before running the actual migration job.

The `migrate database` output indicates the migration job ID, which you can use to query the status of the job.

To run an evaluation of the migration job, run the ZDMCLI command `migrate database` with the `-eval` option, as shown in the following example.

Log in to the Zero Downtime Migration service host and switch to the `zdmuser` installed user.

```
su - zdmuser
```

If connectivity to the source database server is done through root credentials then the command would be the following:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database -sourcedb
source_db_unique_name_value
-sourcenode source_database_server_name -srcroot
-targetnode target_database_server_name
```

```
-backupuser Object_store_login_user_name
-rsp response_file_location
-tgtauth zdmauth
-tgtarg1 user:target_database_server_login_user_name
-tgtarg2 identity_file:ZDM_installed_user_private_key_file_location
-tgtarg3 sudo_location:/usr/bin/sudo -eval
```

For the prompts, specify the source database SYS password and the source database server root user password. If the backup destination is Object Store (Bucket), then specify user swift authentication token. If the backup destination is Storage Classic (Container) then specify your tenancy login password.

For example,

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database -sourcedb zdmsdb -sourcenode
ocidb1
-srcroot -targetnode ocidb1 -backupuser backup_user@example.com
-rsp /u01/app/zdmhome/rhp/zdm/template/zdm_template_zdmsdb.rsp -tgtauth
zdmauth
-tgtarg1 user:opc -tgtarg2 identity_file:/home/zdmuser/.ssh/
zdm_service_host.ppk -tgtarg3
sudo_location:/usr/bin/sudo -eval
```

```
Enter source database zdmsdb SYS password:
Enter source user "root" password:
Enter user "backup_user@example.com" password:
```

If connectivity to the source database server is through SSH key, then the command would be:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database -sourcedb
source_db_unique_name_value
-sourcenode source_database_server_name -srcauth zdmauth
-srcarg1 user:source_database_server_login_user_name
-srcarg2 identity_file:ZDM_installed_user_private_key_file_location
-srcarg3 sudo_location:/usr/bin/sudo -targetnode target_database_server_name
-backupuser Object_store_login_user_name -rsp response_file_location
-tgtauth zdmauth -tgtarg1 user:target_database_server_login_user_name
-tgtarg2 identity_file:ZDM_installed_user_private_key_file_location
-tgtarg3 sudo_location:/usr/bin/sudo -eval
```

For the prompts, specify the source database SYS password. If the backup destination is Object Store (Bucket), then specify user swift authentication token. If the backup destination is Storage Classic (Container), then specify your tenancy login password.

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database -sourcedb zdmsdb -sourcenode
ocidb1 -srcauth zdmauth
-srcarg1 user:opc -srcarg2 identity_file:/home/zdmuser/.ssh/
zdm_service_host.ppk
-srcarg3 sudo_location:/usr/bin/sudo -targetnode ocidb1 -backupuser
backup_user@example.com
-rsp /u01/app/zdmhome/rhp/zdm/template/zdm_template_zdmsdb.rsp -tgtauth
zdmauth -tgtarg1 user:opc
-tgtarg2 identity_file:/home/zdmuser/.ssh/zdm_service_host.ppk -tgtarg3
sudo_location:/usr/bin/sudo -eval
```

```
Enter source database zdmfdb SYS password:  
Enter user "backup_user@example.com" password:
```

Note that if a source single instance database is deployed without a Grid Infrastructure home, then in the above command use `-sourcesid` in place of `-sourcedb`.

Also, if a source database is configured for a `PASSWORD` based wallet, then add the `-tdekeystorepasswd` option to the command above, and for the prompt, specify the source database TDE keystore password value.

Note that the `-backupuser` argument takes the Object Storage access user or Zero Data Loss Recovery Appliance VPC user, and is skipped if NFS is the backup medium. For NFS, the source database user should have 'rwx' access to the NFS path provided.

The migration command checks for patch compatibility between the source and target home patch level, and expects the target home patch level to be equal to or higher than the source. If the target home patch level is not as expected, then the migration job is stopped and missing patches are reported. You can either patch the target home with the necessary patches or you can force continue the migration by appending the `-ignore PATCH_CHECK` or `-ignore ALL` option to the migration command.

If there is no SSH connectivity to the source database server and the target is Oracle Cloud Infrastructure co-managed database then, run the following command:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database  
-rsp response_file_location  
-targetnode target_database_server_name  
-tgtauth zdmauth  
-tgtarg1 user:target_database_server_login_user_name  
-tgtarg2 identity_file:ZDM_installed_user_private_key_file_location  
-tgtarg3 sudo_location:/usr/bin/sudo  
-eval
```

When you run `migrate database` with `-eval`, Zero Downtime Migration only runs a subset of the migration job phases. For example, a logical migration job run with `-eval` would only run the following phases:

```
ZDM_VALIDATE_SRC  
ZDM_VALIDATE_TGT  
ZDM_SETUP_SRC  
ZDM_PRE_MIGRATION_ADVISOR  
ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC  
ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT  
ZDM_PREPARE_DATAPUMP_SRC  
ZDM_DATAPUMP_ESTIMATE_SRC  
ZDM_CLEANUP_SRC
```

The `migrate database` output indicates the job ID for the migration job, which you can use to query the status of the job.

If you want to run the command without providing passwords at the command line, see [Providing Passwords Non-Interactively Using a Wallet](#).

9.1.2 Zero Downtime Migration Schema Analysis with Cloud Premigration Advisor Tool

For logical migration jobs, Zero Downtime Migration is integrated with the Cloud Premigration Advisor Tool (CPAT) to analyze the source database during a migration job, and advise you about database features and constructs that are problematic.

CPAT provides the following benefits to your migration evaluation:

- Warns you about any features used by your database that aren't supported in the target environment
- Makes suggestions for remedial changes and/or parameters to use for the Data Pump export and import operations
- Optionally generates remedial scripts for failing checks that you can run against the source database

Note

For Autonomous databases, ZDM does not have the traditional DBA role, hence, CPAT might report that the admin role is not present for the specified user. In such case, grant the required admin roles to the user as follows:

```
connect ADMIN;  
GRANT OCPROLE TO <username>;  
GRANT DWROLE TO <username>;
```

When you run a logical migration using `ZDMCLI migrate database`, CPAT is run by default as phase `ZDM_PRE_MIGRATION_ADVISOR`. Checks are customized based on response file input parameter settings.

See Cloud Premigration Advisor Tool Support for CPAT use cases supported by Zero Downtime Migration.

The following are options you can use with `ZDMCLI migrate database` to customize how CPAT runs, or to skip the CPAT phase.

- **-advisor** only runs the following minimum migration job phases required for exclusively running Cloud Premigration Advisor Tool (CPAT) on the migration.

`ZDM_VALIDATE_SRC`

`ZDM_VALIDATE_TGT`

`ZDM_SETUP_SRC`

`ZDM_PRE_MIGRATION_ADVISOR`

`ZDM_CLEANUP_SRC`

- **-ignoreadvisor** ignores any problems or errors reported by CPAT.
- **-skipadvisor** skips the CPAT phase in a migration job.

- `-genfixup {YES | NO}` generates remedial scripts for failing checks that you can run if you choose.

The migration job output displays the checks performed, descriptions of any problems, and actions you can take to resolve the issues, as shown in this example.

```
Cloud Premigration Advisor Tool Version 21.1.0-10
Cloud Premigration Advisor Tool completed with overall result: Action Required
Cloud Premigration Advisor Tool generated report location:
/scratch/app/u02/base/zdm/zdm_db12151_1/out/premigration_advisor_report.json
RESULT: Action Required
```

```
Schemas Analyzed (2): HR01,HR02
A total of 29 checks were performed
There were 0 checks with Failed results
There were 1 checks with Action Required results: nls_character_set_conversion
(0 relevant objects)
There were 3 checks with Review Required results:
timezone_table_compatibility_higher
(0 relevant objects), has_role_privileges (0 relevant objects),
has_sys_privileges (0 relevant objects)
There were 1 checks with Review Suggested results:
has_default_tablespace_not_data
(2 relevant objects) nls_character_set_conversion
RESULT: Action Required
DESCRIPTION: Check for issues caused by conversion of character data
from the source to the target database character set, such as expansion of
character values beyond column length or loss of invalid character codes.
ACTION: Scan the schemas to be migrated using Database Migration
Assistant for Unicode (DMU) and analyze all possible convertibility issues.

FIXUP SCRIPT:
/scratch/app/u02/base/zdm/zdm_db12151_1/zdm/lib/cpatfixups/
gg_force_logging.sql
```

See [migrate database](#) for more information about the command options, and see [Cloud Premigration Advisor Tool \(CPAT\) Analyzes Databases for Suitability of Cloud Migration \(Doc ID 2758371.1\)](#) for more information about Cloud Premigration Advisor Tool.

Note

Excluding TABLES in the migration response file does not exclude it from CPAT analysis. SCHEMAS can be excluded from CPAT if the entire schema was excluded. The presence of an Oracle Cloud unsupported table can lead to Action Required status in the CPAT report. You can submit a new migration job with `-ignoreadvisor` to ignore the Action Required error and proceed to migration, provided that all other CPAT Action Required errors are addressed.

9.1.3 Configuring Migrations for Remote CPAT Invocation

Zero Downtime Migration handles running Cloud Premigration Advisor Tool (CPAT) based on the specified source database access. In some cases, such as Amazon RDS Oracle as a source, Zero Downtime Migration ensures that CPAT is run remotely in a secure manner.

To have Zero Downtime Migration run CPAT validation remotely, set the response file parameter `RUNCPATREMOTELY=true`.

A connect string is constructed with your settings from the following parameters:

- `SOURCEDATABASE_ADMINUSERNAME`
- `SOURCEDATABASE_CONNECTIONDETAILS_HOST`
- `SOURCEDATABASE_CONNECTIONDETAILS_SERVICENAME`
- `SOURCEDATABASE_CONNECTIONDETAILS_PORT`
- `SOURCEDATABASE_CONNECTIONDETAILS_TLSDETAILS_DISTINGUISHEDNAME`

For more information about CPAT, see [Cloud Premigration Advisor Tool \(CPAT\) Analyzes Databases for Suitability of Cloud Migration \(Doc ID 2758371.1\)](#)

9.2 Migrate the Database

Perform the database migration with Zero Downtime Migration using the `ZDMCLI migrate database` command.

Ensure that you have met all of the prerequisites and completed the required preparations described in [Preparing for a Physical Database Migration](#) before you begin the migration procedures in this topic.

In particular be sure the following tasks are done:

- Obtain the necessary access credentials required.

If Oracle Cloud Infrastructure Object Storage is used as the backup medium, obtain the Object Storage access credential. The user ID for the Oracle Cloud Infrastructure Console user and an auth token for Object Storage is required. If you are not using an existing auth token, a new auth token can be generated using the Oracle Cloud Infrastructure Console.

If the source database server is accessed with the root user, then you need the root user password. If the source and target database servers are accessed with a private key file, then you need the private key file. The SYS password for the source database environment is also required.

If Zero Data Loss Recovery Appliance is used as the backup medium, get the Zero Data Loss Recovery Appliance virtual private catalog (VPC) user credentials.

- Prepare the Zero Downtime Migration response file.

The database migration is driven by a response file that captures the essential parameters for accomplishing the task.

Use the sample `$ZDM_HOME/rhp/zdm/template/zdm_template.rsp` file for example entries needed to set up the response file for your particular source, target, and backup environments.

- Determine if the migration process needs to be paused and resumed before you start the database migration. Once the migration job is initiated the job system runs the job as configured.

If the migration job needs to pause and resume at a particular point, then see the topics [List Migration Job Phases](#) and [Pause and Resume Migration Job](#) (cross references below) for more details.

Physical Migration with Root Credentials

The database migration job is submitted from the Zero Downtime Migration service host by the `zdmuser` user using the `ZDMCLI` command `migrate database`.

For a physical migration, if connectivity to the source database server is through root credentials, then the command would be:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-sourcedb source_db_unique_name_value
-sourcenode source_database_server_name
-srcroot
-targetnode target_database_server_name
-backupuser Object_store_login_user_name
-rsp response_file_location
-tgtauth zdmauth
-tgtarg1 user:target_database_server_login_user_name
-tgtarg2 identity_file:ZDM_installed_user_private_key_file_location
-tgtarg3 sudo_location:/usr/bin/sudo
```

For the prompts, specify the source database SYS password and source database server root user password. If the backup destination is Object Store (Bucket), then specify user swift authentication token. If the backup destination is Storage Classic (Container), then specify your tenancy login password.

For example:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-sourcedb zdmsdb
-sourcenode ocicdb1
-srcroot
-targetnode ocicdb1
-backupuser backup_user@example.com
-rsp /u01/app/zdmhome/rhp/zdm/template/zdm_template_zdmsdb.rsp
-tgtauth zdmauth
-tgtarg1 user:opc
-tgtarg2 identity_file:/home/zdmuser/.ssh/zdm_service_host.ppk
-tgtarg3 sudo_location:/usr/bin/sudo
```

Enter source database `zdmsdb` SYS password:

Enter source user "root" password:

Enter user "backup_user@example.com" password:

Physical Migration with SSH Key

For a **physical migration**, if connectivity to the source database server is through **SSH key**, then the command would be:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-sourcedb source_db_unique_name_value
-sourcenode source_database_server_name
-srcauth zdmauth
-srcarg1 user:source_database_server_login_user_name
-srcarg2 identity_file:ZDM_installed_user_private_key_file_location
-srcarg3 sudo_location:/usr/bin/sudo
-targetnode target_database_server_name
-backupuser Object_store_login_user_name
-rsp response_file_location
```

```
-tgtauth zdmauth
-tgtarg1 user:target_database_server_login_user_name
-tgtarg2 identity_file:ZDM_installed_user_private_key_file_location
-tgtarg3 sudo_location:/usr/bin/sudo
```

For the prompts, specify the source database SYS password. If the backup destination is Object Store (Bucket), then specify user swift authentication token. If the backup destination is Storage Classic (Container), then specify your tenancy login password.

For example,

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-sourcedb zdmsdb
-sourcenode ocicdb1
-srcauth zdmauth
-srcarg1 user:opc
-srcarg2 identity_file:/home/zdmuser/.ssh/zdm_service_host.ppk
-srcarg3 sudo_location:/usr/bin/sudo
-targetnode ocicdb1
-backupuser backup_user@example.com
-rsp /u01/app/zdmhome/rhp/zdm/template/zdm_template_zdmsdb.rsp
-tgtauth zdmauth
-tgtarg1 user:opc
-tgtarg2 identity_file:/home/zdmuser/.ssh/zdm_service_host.ppk
-tgtarg3 sudo_location:/usr/bin/sudo
```

Enter source database zdmsdb SYS password:

Enter user "backup_user@example.com" password:

If a source single instance is deployed without a Grid Infrastructure home, then in the command above use `-sourcesid` in place of `-sourcedb`.

If the source database is configured for a `PASSWORD` based wallet, then add the `-tdekeystorepasswd` option to the command above, and for the prompt, specify the source database TDE keystore password value.

Note that the `-backupuser` argument takes the Object Storage access user or Zero Data Loss Recovery Appliance VPC user and is skipped if NFS is the backup medium. For NFS, the source database user should have 'rwx' access to the NFS path provided.

Logical Migration to Autonomous Database

For a **logical migration to Autonomous Database**, the command would be:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-rsp file_path
-sourcedb source_db_unique_name_value
-sourcenode host
-srcauth zdmauth
-srcarg1 user:username
-srcarg2 identity_file:ssh_key_path
-srcarg3 sudo_location:sudo_path
-eval [-advisor [-ignoreadvisor] | -skipadvisor]]
```

Logical Migration to a Co-Managed Database

For a logical migration to a co-managed system, the command would be:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-rsp file_path
-sourcedb source_db_unique_name_value
-sourcenode host
-srcauth zdmauth
-srcarg1 user:username
-srcarg2 identity_file:ssh_key_path
-srcarg3 sudo_location:sudo_path
-targetnode host
-tgtauth zdmauth
-tgtarg1 user:username
-tgtarg2 identity_file:ssh_key_path
-tgtarg3 sudo_location:sudo_path
[-ignoreadvisor | -skipadvisor]
```

Logical Migration to a Co-Managed Database without SSH access

If there is no SSH connectivity to the source database server and the target is Oracle Cloud Infrastructure co-managed database then, run the following command:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-rsp response_file_location
-targetnode target_database_server_name
-tgtauth zdmauth
-tgtarg1 user:target_database_server_login_user_name
-tgtarg2 identity_file:ZDM_installed_user_private_key_file_location
-tgtarg3 sudo_location:/usr/bin/sudo
```

Patch Compatibility

The migration command checks for patch compatibility between the source and target home patch level, and expects the target home patch level to be equal to or higher than the source. If the target home patch level is not as expected, then the migration job is stopped and missing patches are reported. You can either patch the target home with the necessary patches or you can force continue the migration by appending the `-ignore PATCH_CHECK` or `-ignore ALL` option to the migration command.

Job ID Value

The command result output indicates the job ID for the migration job, which you can use to query the status of the job.

Running Migrations Non-Interactively

If you want to run the command without providing passwords at the command line, see [Providing Passwords Non-Interactively Using a Wallet](#).

9.3 Post-Migration Tasks

When the migration job completes, make sure to complete any relevant post-migration tasks.

Update the `global_name`

The `global_name` refers to the full name of a database (including its domain) which uniquely identifies it from any other database. During migration the `global_name` of the source system is retained. This is fine as long as it does not contain the `domain_name`.

If the `domain_name` is part of the `global_name`, update the `global_name` manually on the target system to include the new domain name.

Configure TDE wallet after migration from Oracle Database 11.2 and 12.1 sources

For Oracle Database 11.2 and 12.1 sources, TDE wallet configuration is not required. If the source does not have a TDE wallet configured, any TDE configuration on the target is removed. After the migration, you must configure the TDE wallet at the target before creating any new tablespaces.

Review the target for invalids post the migration

You must review the target for invalids post the migration and fix the underlying dependencies causing these objects to go invalid. ZDM already attempts to fix these objects twice - which allows the interdependent objects to get valid on second run. If there are invalids beyond that, then it needs further review and action from you to address the underlying reason.

9.4 Query Migration Job Status

You can query the migration job status while the job is running.

Query the status of a database migration job using the ZDMCLI `query job` command, specifying the job ID. The job ID is shown in the command output when the database migration job is submitted.

```
zdmuser> $ZDM_HOME/bin/zdmcli query job -jobid job-id
```

You can find the console output of the migration job in the file indicated (Result file path:) in the `query job` command output. You can see migration progress messages in the specified file

9.5 List Migration Job Phases

You can list the operation phases involved in the migration job.

To list the operation phases involved in the migration job, add the `-listphases` option in the ZDMCLI `migrate` command. This option will list the phases involved in the operation.

For example,

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database -sourcedb zdmsdb -sourcenode
ocidb1 -srcauth zdmauth
-srcarg1 user:opc -srcarg2 identity_file:/home/zdmuser/.ssh/
zdm_service_host.ppk -srcarg3 sudo_location:/usr/bin/sudo
-targetnode ocidb1 -backupuser backup_user@example.com -rsp /u01/app/
zdmhome/rhp/zdm/template/zdm_template_zdmsdb.rsp
-tgtauth zdmauth -tgtarg1 user:opc -tgtarg2 identity_file:/home/zdmuser/.ssh/
zdm_service_host.ppk
-tgtarg3 sudo_location:/usr/bin/sudo -listphases
```

9.6 Pause a Migration Job

You can pause a migration job at any point after the `ZDM_SETUP_TGT` phase, and resume the job at any time.

To pause a migration job, specify the `-pauseafter` option in the `ZDMCLI migrate` command with a valid phase to be paused after.

In the following example, if you specify `-pauseafter ZDM_SETUP_TGT`, the migration job will pause after completing the `ZDM_SETUP_TGT` phase.

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database -sourcedb zdmsdb -sourcenode
ocidbl
-srcauth zdmauth -srcarg1 user:opc
-srcarg2 identity_file:/home/zdmuser/.ssh/zdm_service_host.ppk
-srcarg3 sudo_location:/usr/bin/sudo -targetnode ocidbl
-backupuser backup_user@example.com -rsp /u01/app/zdmhome/rhp/zdm/template/
zdm_template_zdmsdb.rsp -tgtauth zdmauth
-tgtarg1 user:opc -tgtarg2 identity_file:/home/zdmuser/.ssh/
zdm_service_host.ppk
-tgtarg3 sudo_location:/usr/bin/sudo -pauseafter ZDM_SETUP_TGT
```

Choosing a Migration Job Phase to Pause After

Choose a valid phase after `ZDM_CONFIGURE_DG_SRC` that is listed in the `migrate database ... -listphases` command output.

Note that the `-pauseafter` option allows only one phase to be specified.

The following are some cases where you may need to pause a migration job, and resume after some manual steps:

- Convert the Standby Database to TDE. If the source is not encrypted, or if ZDLRA is used as the data transfer medium, or the Oracle Database version is earlier than 12.2, you need to encrypt the target Cloud database.
- Enable Active Data Guard (optional)
- Monitor Data Guard Configuration Health, before the switchover
- Test the Cloud database (optional). You can convert the standby to the primary without doing the application switchover, which can be used to duplicate the source database for testing in the Cloud.

Best Practices for Pausing a Physical Migration Job

In a physical migration, if you use `-pauseafter` at phase `ZDM_CONFIGURE_DG_SRC`, then at the end of the execution of the phase, a standby is created at the target database and synchronization occurs between source and target databases.

Pausing the migration job after `ZDM_CONFIGURE_DG_SRC` is recommended so that you can do the following:

- Perform the application switchover to the cloud
- Manually encrypt the cloud database if ZDLRA is the backup method or your database release is earlier than Oracle Database 12.2

- Perform a failover to test the cloud database without making changes to the on-premises database

Preserving Log Files During a Paused Migration Job

To prevent source and target database log files from getting cleaned up between pausing and resuming a migration job, log files are written to `$ORACLE_BASE/zdm/zdm_db_unique_name_zdm_job_id/zdm/log` in their respective source and target database servers.

Ensure that all of the archive logs generated during and after the `ZDM_BACKUP_INCREMENTAL_SRC` phase are available, preferably until switchover, or at least until the target and source databases are in sync. Older archive logs, the archive logs generated prior to `ZDM_BACKUP_INCREMENTAL_SRC` are not needed.

9.7 Resume a Migration Job

A paused job can be resumed any time by running the `ZDMCLI resume job` command, specifying the respective job ID.

```
zdmuser> $ZDM_HOME/bin/zdmcli resume job -jobid Job_ID
[-pauseafter valid-phase | -rsp zdm_logical_template]
[-rerun {BACKUP|RESTORE}]
[-ignore
{IMPORT_ERRORS | EXPORT_ERRORS}]
-skip SWITCHOVER
```

Scheduling Another Pause on Resume

To schedule another pause, specify the `-pauseafter` option in the `resume job` command with a valid phase to be paused after, as shown in the example below.

Choose a valid phase later than that at which the phase is currently paused. Phases are listed in the `migrate database ... -listphases` command output.

```
zdmuser> $ZDM_HOME/bin/zdmcli resume job -jobid Job_ID
-pauseafter valid-phase
```

Rerunning RMAN Backup or Restore Operation on Resume

In a physical migration job, the `-rerun` option allows you to trigger the related migration job phases to rerun when you resume the job.

The `RESTORE` option value specifies that Zero Downtime Migration should re-run of the restore-related phases, which includes dropping the existing target database, restoring spfile, and restoring controlfile and datafiles.

The `BACKUP` option value specifies that Zero Downtime Migration should re-run phases starting from the `ZDM_BACKUP_INCREMENTAL_SRC` phase. As part of the re-run of the backup phase, an RMAN crosscheck is first run to ensure that the source controlfile is consistent with any backups present on the backup media.

The main reason you might want the phases to re-run is to retry backup or restore procedures on migration job failure. A possible use case for re-running the backup would be if the backups are accidentally deleted before the restore is attempted or completed. Another reason could be that if the TDE wallet is changed after Zero Downtime Migration has already copied the wallet to the target, then the differential backup source would encrypt the backup with the new wallet,

but the incremental restore will fail because the target will not have the latest wallet. In this case rerunning triggers a re-copy of the wallet and subsequently rerun of restore including dropping and recreating the target database.

Additional ZDM Job Specific Export or Import Error Ignore Option

To ignore Data Pump errors, specify the `-ignore` option in the `resume job` command.

```
zdmcli resume job -jobid <num> [-ignore {IMPORT_ERRORS | EXPORT_ERRORS}]
```

This option lets the job proceed to next action in the respective phase and further proceed to follow-on phases in the job without re-executing Data Pump. You can ignore job specific export or import errors without ignoring all errors using the `IGNOREEXPORTERRORS` and the `IGNOREIMPORTERRORS` parameters. This ignores the specified errors and attempts a re-import or re-export action.

Note

Include the default errors and append additional errors if any. If the `IGNOREEXPORTERRORS` and `IGNOREIMPORTERRORS` parameters are updated for resume action, then updated response file is required to be supplied to resume job as follows: `zdmcli resume job -jobid <job number> -rsp <updated response file>`.

The phase status that `FAILED` is marked with status `IGNORED_ON_FAILURE`.

`-ignore EXPORT_ERRORS` ignores all error seen in Data Pump export and ZDM job proceeds to the next workflow actions.

`-ignore IMPORT_ERRORS` ignores all error seen in Data Pump import and ZDM job proceeds to the next workflow actions.

Skipping switchover

In case of failure during the switchover phase, you can fix any issues and perform a manual switchover. To avoid any issues with the ZDM flow, you can specify that a manual switchover has been performed and that ZDM should skip the switchover phase. Resume the migration job with:

```
zdmcli resume job -jobid <jobid> -skip SWITCHOVER
```

Modifying Migration Parameters on Resume

In a logical migration job, some parameters can be modified upon either pausing the job or a job failure. When you are ready to resume the job, specify the modified response file in the command `resume job`, and the changes are picked up by Zero Downtime Migration when the job is resumed.

To modify parameters on resume, specify the `-rsp` option in the `resume job` command with the path to the logical migration response file containing the modified parameters, as shown below.

```
zdmuser> $ZDM_HOME/bin/zdmcli resume job -jobid Job_ID  
-rsp modified_zdm_logical_template
```

The following considerations and limitations apply:

- Only certain properties can be modified
- Any property modification is rejected if the phase in which it is used is already completed
- Removing or adding properties to the file is considered a modification, and Zero Downtime Migration performs a validation to determine if those adds/deletes can be included.
- Terminated (aborted) jobs and evaluation jobs cannot be resumed.

The response file parameters references identify which parameters are modifiable and until which phase they can be changed. Note that the phases before which they can be set will differ if `DATA_TRANSFER_MEDIUM` is set to `DBLINK`.

Table 9-1 Migration Parameters Modifiable on Resume

Parameter	When can it be modified?
<code>SOURCEDATABASE_CONNECTIONDETAILS_HOST</code>	Modify at any phase
<code>SOURCEDATABASE_CONNECTIONDETAILS_PORT</code>	Modify at any phase
<code>OCIAUTHENTICATIONDETAILS_*</code>	Modify at any phase
<code>TARGETDATABASE_CONNECTIONDETAILS_HOST</code>	Modify at any phase
<code>TARGETDATABASE_CONNECTIONDETAILS_PORT</code>	Modify at any phase
<code>TARGETDATABASE_CONNECTIONDETAILS_TLSDETAILS_*</code>	Modify at any phase
<code>TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_*</code>	Modify at any phase
<code>TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_*</code>	Modify at any phase
<code>SOURCEDATABASE_CONNECTIONDETAILS_TLSDETAILS_*</code>	Modify at any phase
<code>SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_*</code>	Modify at any phase
<code>SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_*</code>	Modify at any phase
<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_HOST</code>	Modify at any phase
<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PORT</code>	Modify at any phase
<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_TLSDETAILS_*</code>	Modify at any phase
<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_*</code>	Modify at any phase
<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_*</code>	Modify at any phase
<code>GOLDENGATEHUB_*</code>	Until <code>ZDM_PREPARE_GG_HUB</code> phase is COMPLETED
<code>GOLDENGATESETTINGS_EXTRACT_*</code>	Until <code>ZDM_CREATE_GG_EXTRACT_SRC</code> phase is COMPLETED
<code>GOLDENGATESETTINGS_REPLICAT_*</code>	Until <code>ZDM_CREATE_GG_REPLICAT_TGT</code> phase is COMPLETED
<code>GOLDENGATESETTINGS_ACCEPTABLELAG</code>	Until <code>ZDM_MONITOR_GG_LAG</code> phase is COMPLETED
<code>DATAPUMPSETTINGS_DELETEDUMPSIN OSS</code>	Until <code>ZDM_POST_DATAPUMP_TGT</code> phase is COMPLETED
<code>DATAPUMPSETTINGS_FIXINVALIDOBJECTS</code>	Until <code>ZDM_POST_DATAPUMP_TGT</code> phase is COMPLETED
<code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_TABLE EXISTS ACTION</code>	Until <code>ZDM_DATAPUMP_IMPORT_TGT</code> phase is COMPLETED
<code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_USERMETADATA</code>	Until <code>ZDM_DATAPUMP_EXPORT_SRC</code> phase is COMPLETED, or until <code>ZDM_DATAPUMP_IMPORT_TGT</code> phase when using <code>DATA_TRANSFER_MEDIUM=DBLINK</code>

Table 9-1 (Cont.) Migration Parameters Modifiable on Resume

Parameter	When can it be modified?
DATAPUMPSETTINGS_DATAPUMPPARAMETERS_IMPORTPARALLELISMDEGREE	Until ZDM_DATAPUMP_IMPORT_TGT phase is COMPLETED
DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXPORTPARALLELISMDEGREE	Until ZDM_DATAPUMP_EXPORT_SRC phase is COMPLETED
DATAPUMPSETTINGS_DATAPUMPPARAMETERS_SKIPCURRENT	Until ZDM_DATAPUMP_IMPORT_TGT phase is COMPLETED
DATAPUMPSETTINGS_DATAPUMPPARAMETERS_ESTIMATEBYSTATISTICS	Until ZDM_DATAPUMP_ESTIMATE_SRC phase is COMPLETED
DATAPUMPSETTINGS_DATAPUMPPARAMETERS_RETAININDEX	Until ZDM_DATAPUMP_EXPORT_SRC phase is COMPLETED, or until ZDM_DATAPUMP_IMPORT_TGT phase when using DATA_TRANSFER_MEDIUM=DBLINK
DATAPUMPSETTINGS_METADATAREMAPS-LIST_ELEMENT_NUMBER	Until ZDM_DATAPUMP_EXPORT_SRC phase is COMPLETED, or until ZDM_DATAPUMP_IMPORT_TGT phase when using DATA_TRANSFER_MEDIUM=DBLINK
DATAPUMPSETTINGS_DATABASELINKDETAILS_NAME	Until ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT phase is COMPLETED
DATAPUMPSETTINGS_DATABASELINKDETAILS_WALLETBUCKET_*	Until ZDM_PREPARE_DATAPUMP_TGT phase is COMPLETED
DATAPUMPSETTINGS_DATABUCKET_*	Until ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC phase is COMPLETED
DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_*	Until ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC phase is COMPLETED
DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_*	Until ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT phase is COMPLETED
DATAPUMPSETTINGS_CREATEAUTHTOKEN	Until ZDM_PREPARE_DATAPUMP_TGT phase is COMPLETED
INCLUDEOBJECTS-LIST_ELEMENT_NUMBER	Until ZDM_DATAPUMP_EXPORT_SRC phase is COMPLETED, or until ZDM_DATAPUMP_IMPORT_TGT phase when using DATA_TRANSFER_MEDIUM=DBLINK
EXCLUDEOBJECTS-LIST_ELEMENT_NUMBER	Until ZDM_DATAPUMP_EXPORT_SRC phase is COMPLETED, or until ZDM_DATAPUMP_IMPORT_TGT phase when using DATA_TRANSFER_MEDIUM=DBLINK
OCIPROXY_*	Modify at any phase
DUMPTRANSFERDETAILS_*	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED
TABLESPACEDETAILS_AUTOCREATE	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED
TABLESPACEDETAILS_USEBIGFILE	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED
TABLESPACEDETAILS_EXTENTSIZEMB	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED
TABLESPACEDETAILS_AUTOREMAP	Until ZDM_DATAPUMP_IMPORT_TGT phase is COMPLETED
TABLESPACEDETAILS_REMAPTARGET	Until ZDM_DATAPUMP_IMPORT_TGT phase is COMPLETED
TABLESPACEDETAILS_EXCLUDE	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED
WALLET_*	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED
IGNOREEXPORTERRORS	Until ZDM_DATAPUMP_EXPORT_SRC phase is COMPLETED
IGNOREIMPORTERRORS	Until ZDM_DATAPUMP_IMPORT_TGT phase is COMPLETED

9.8 Suspend and Resume a Migration Job

You can suspend a migration job at any point, and resume the job at any time.

To suspend a migration job run the following command.

```
zdmuser> $ZDM_HOME/bin/zdmcli suspend job -jobid job_id
```

What is the difference between Pause and Suspend?

A migration job "pause" is an event you schedule when you start the migration job, and "suspend" is an unscheduled event that you can employ while the migration job is running.

Resuming a Suspended Migration Job

A suspended job can be resumed any time by running the `ZDMCLI resume job` command, specifying the respective job ID.

```
zdmuser> $ZDM_HOME/bin/zdmcli resume job -jobid Job_ID  
[-pauseafter valid-phase]
```

You can optionally schedule a pause, by specifying the `-pauseafter` option in the `resume` command with a valid phase to be paused after. Choose a valid phase later than phase currently paused at, that is listed in the `migrate database ... -listphases` command output.

When will the suspend interrupt a job?

Some migration job phases are interruptible and some are not.

A logical migration, when suspended, either interrupts the ongoing job phase, if the phase is interruptible, or it suspends the job after completion of the ongoing phase before the job is suspended, if the phase is not interruptible.

Following phases are interruptible for Oracle Data Pump:

- `ZDM_DATAPUMP_EXPORT_SRC`
- `ZDM_TRANSFER_DUMPS_SRC`
- `ZDM_DATAPUMP_IMPORT_TGT`

The following phases are interruptible for Oracle GoldenGate:

- `ZDM_CREATE_GG_EXTRACT_SRC`
- `ZDM_CREATE_GG_REPLICAT_TGT`
- `ZDM_MONITOR_GG_LAG`
- `ZDM_SWITCHOVER_APP`

Once the suspend operation is completed, the job status is updated to `SUSPENDED`

9.9 Rerun a Migration Job

If there are any unexpected errors in the migration workflow, you can correct them and rerun the migration job.

The errors are recorded in the job output, which can be queried using the `ZDMCLI query job` command. Upon resolving the error, the failed job can be continued from the point of failure.

Rerun the migration job by running the `ZDMCLI resume job` command, specifying the job ID of the job to be rerun, as shown here.

```
zdmuser> $ZDM_HOME/bin/zdmcli resume job -jobid Job_ID
```

9.10 Terminate a Running Migration Job

If you want to resubmit a database migration job for a specified database, you must first terminate the running migration job.

Zero Downtime Migration blocks attempts to rerun the `MIGRATE DATABASE` command for a specified database if that database is already part of an ongoing migration job.

If you want to resubmit a database migration job for a specified database, you must first terminate the running migration job in either `EXECUTING` or `PAUSED` state using the `ZDMCLI ABORT JOB` command.

```
zdmuser> $ZDM_HOME/bin/zdmcli abort job -jobid job-id
```

9.11 Modify Oracle GoldenGate Processes During a Migration Job

You can modify the Oracle GoldenGate Replicat and Extract process parameters during a running (in-flight) migration job.

To modify a running migration job run the following command.

```
zdmuser> $ZDM_HOME/bin/zdmcli modify job -jobid job_id -rsp response_file_path
```

This modify command will affect the migration job only if the specified response file contains at least one of the following parameters related to Oracle GoldenGate configuration:

- `GOLDENGATESETTINGS_EXTRACT_PERFORMANCEPROFILE`
- `GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE`

Note

Starting with Oracle Zero Downtime Migration 21c (21.4) release, the following properties are deprecated and will be desupported in a future release:

- GOLDENGATESETTINGS_REPLICAT_MAPPARALLELISM
- GOLDENGATESETTINGS_REPLICAT_APPLYPARALLELISM
- GOLDENGATESETTINGS_REPLICAT_MAXAPPLYPARALLELISM
- GOLDENGATESETTINGS_REPLICAT_MINAPPLYPARALLELISM

These parameters are replaced by the

GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE parameter. If you configure the GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE parameter, then you do not have to configure these deprecated parameters. However, if you do configure these deprecated parameters, then the GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE parameter will not be valid.

Extract parameters can only be updated between the migration job phases ZDM_CREATE_GG_EXTRACT_SRC (exclusive) and ZDM_MONITOR_GG_LAG (inclusive).

Replicat parameters can only be updated between the migration job phases ZDM_CREATE_GG_REPLICAT_TGT (exclusive) and ZDM_MONITOR_GG_LAG (inclusive).

After Zero Downtime Migration updates the parameters for a GoldenGate process, it restarts the process, unless the migration job is suspended, in which case the GoldenGate process will remain stopped.

9.12 Handling Application Switchover in a Logical Migration

The following procedure ensures zero data loss during a read-write application switchover.

Both the source and target databases are opened read-write during the logical migration work flow. The following conditions apply:

- For **read-only** applications, switchover can happen immediately after GoldenGate Replicat has applied all outstanding source transactions, allowing for zero application downtime for those services.
- **Read-write** applications require assurance that all transactions have been applied on the target before switching the application over to ensure zero data loss.

If your application is read-write, you must do the following to ensure zero data loss:

1. Pause the Zero Downtime Migration job after phase ZDM_MONITOR_GG_LAG.

This phase monitors Oracle GoldenGate Extract and Replicat operations until Replicat has caught up on the target database--end to end (E2E) replication lag should be less than 30 seconds.

2. After phase ZDM_MONITOR_GG_LAG completes and the migration job pauses, stop the workload on the source database (start of downtime).

If applications are configured to use database services, then you can use `srvctl stop service` command to stop services using `-drain_timeout`. See [Ensuring Application Continuity](#) for more information.

Note

The application must be aware that upon the expiry of drain timeout, the database services will be stopped and sessions using those services will be terminated.

3. Resume the migration job, scheduling another pause after phase `ZDM_PREPARE_SWITCHOVER_APP`.
This phase does the following:
 - a. Ensures replication E2E lag is still less than 30 seconds
 - b. Ensures that Extract has captured outstanding transaction on the source database
 - c. Stops Extract
 - d. Ensures Replicat has applied all remaining trail file data
 - e. Stops Replicat
4. After phase `ZDM_PREPARE_SWITCHOVER_APP` completes and the migration job pauses, resume the migration job as follows:
 - a. (Optional) If one or more objects were excluded from replication, then the objects need to be reloaded in the target database at this time. Resume the migration job, scheduling another pause after phase `ZDM_RELOAD_PARALLEL_EXPORT_IMPORT`. This phase will execute Data Pump Export and Import to reload the necessary objects.
 - b. Resume the migration job, scheduling another pause after phase `ZDM_SWITCHOVER_APP`.
5. ZDM now automatically advances the sequence values in the target database during switchover. For more details refer to the `ZDM_ADVANCE_SEQUENCES` phase in Zero Downtime Migration Process Phases.
6. After phase `ZDM_SWITCHOVER_APP` completes and the migration job pauses, you can verify the consistency of data between the source and target databases. You must ensure that the sequences in the target database have the correct value. If required, increment the sequences in the target database until the next value is high enough. You can run the following query in the source database to generate a SQL script.

```
select 'alter sequence '||SEQUENCE_OWNER||'.'||SEQUENCE_NAME||' restart
start with '|| LAST_NUMBER||';'
from dba_sequences
where SEQUENCE_OWNER in (
  select username
  from dba_users
  where nvl(oracle_maintained, 'N') = 'N');
```

Run the above SQL script in target database to advance the sequences. Resume the migration job, scheduling another pause after the `ZDM_POST_SWITCHOVER_TGT` phase.

7. After the `ZDM_POST_SWITCHOVER_TGT` phase completes and the migration job pauses, you can start the workload on the target database (end of downtime).

Note

Refer to the `GOLDENGATESETTINGS_RELOADUNREPLICATEDOBJECTS` and `RELOADOBJECTS-n` parameters for enabling the reload feature.

9.13 Zero Downtime Migration Centralized Fleet Migration Management

Zero Downtime Migration allows you to centrally monitor fleet level migration using the Object Storage Service PAR URL.

Zero Downtime centralized fleet migration management gives you the following capabilities.

- Fleet level migration monitoring
- Fleet level log aggregation for easy troubleshooting and data mining
- Centralized migration per job metrics collection, which can be leveraged for executive-level migration status dash-boards and future migration forecasting

Centralized fleet migration management also lets you to prohibit the operation team from accessing the source or target database server for migration failures. The operation team can be allowed to troubleshoot the failure with the logs available in the specified `ZDM_LOG_OSS_PAR_URL` or logs further staged to a different Oracle Cloud storage bucket for operation troubleshooting.

Centralized fleet migration management is only supported for physical migration jobs, and is enabled by setting the parameter `ZDM_LOG_OSS_PAR_URL` to a pre-authenticated URL, for example:

`https://objectstorage.us-region.oraclecloud.com/.../DEV_ZDM_LOGS_RGN/o/`

Zero Downtime Migration uploads the job specific data, shown in the table below, to the specified OSS PAR URL at regular interval while a migration job is in progress.

Table 9-2 Centralized Fleet Migration Job Data

Category	URL Name space Suffix (Appended to value of <code>ZDM_LOG_OSS_PAR_URL</code>)	Content
Job Metrics	<code>PAR_URL/1/POD_NAME/ZDM_HOST/JOB_ID/METRICS.txt</code> For example, <code>/1/PRD_TEST_MIGRATION/s16izp/1/METRICS.txt</code>	Job Metrics details the source and target database vitals and backup and restore statistics per phase involved in the work flow and error. This data can be used for fleet level migration statistics for executive dashboards.
Job Status	<code>PAR_URL/1POD_NAME/ZDM_HOST/JOB_ID/CURRENT_PHASE.txt</code> For example, <code>/1/PRD_TEST_MIGRATION/s16izp/1/CURRENT_PHASE.txt</code>	Status entries are listed in the format <code>Phase Name:Phase Status</code> For example, <code>ZDM_BACKUP_FULL_SRC:EXECUTING</code> Phase Status values are EXECUTING, PAUSED, FAILED, or COMPLETED

Table 9-2 (Cont.) Centralized Fleet Migration Job Data

Category	URL Name space Suffix (Appended to value of ZDM_LOG_OSS_PAR_URL)	Content
Phase Log	<p><i>PAR_URL/2/TIMESTAMP/POD_NAME/ZDM_HOST/JOB_ID/ACTION HOST/PHASE_NAME.log</i></p> <p>For example, 2/2011-11-07T17:58:34.049000/ PRD_TEST_MIGRATION/2-zdm-01/1/ cldx01/ZDM_BACKUP_FULL_SRC.log</p>	Zero Downtime Migration uploads the phase-specific logs at the end of each phase with a UTC time-stamped name space. On job rerun, the time stamp would change and the rerun-specific log would be identified by latest time stamp.
Phase Status	<p><i>PAR_URL/1/POD_NAME/ZDM_HOST/JOB_ID/PHASE_NAME.txt</i></p> <p>For example, /1/PRD_TEST_MIGRATION/s16izp/1/ ZDM_VALIDATE_TGT.txt</p>	<p>The file contents will be COMPLETED if the phase is completed or PENDING if it has yet to start.</p> <p>At the start of a migration job, Zero Downtime Migration creates all of the phase-named files with PENDING status, then updates them to COMPLETED as each phase is completed.</p> <p>Use the creation time of <i>PHASE_NAME.txt</i> to measure the phase elapsed time.</p>
Progress Message	<p><i>PAR_URL/1/POD_NAME/ZDM_HOST/JOB_ID/CONSOLE.out</i></p> <p>For example, 1/PRD_TEST_MIGRATION/s16izp/1/ CONSOLE.out</p>	<p>Zero Downtime Migration updates CONSOLE.out for each <i>n</i> chunk of console messages received (for example, every 10 lines) normally, or instantly in case of errors.</p> <p>Progress messages are formatted like this:</p> <p><i>node name : UTC Time : Progress message</i></p> <p>For example, hxvdbfz03: 2021-02-10T09:51:11.851Z : Retrieving information from source node "hfzb06" ...</p>

10

Managing the Zero Downtime Migration Service

Perform Zero Downtime Migration service life cycle operations using `zdm` service.

10.1 Starting and Stopping the Zero Downtime Migration Service

You must start the Zero Downtime Migration service before you can migrate your databases using Zero Downtime Migration.

Start the Zero Downtime Migration service, `zdm` service, as user `zdmuser`, with the following command.

```
zdmuser> $ZDM_HOME/bin/zdm service start
```

If you must stop the Zero Downtime Migration service, run the following command.

```
zdmuser> $ZDM_HOME/bin/zdm service stop
```

10.2 Checking Zero Downtime Migration Service Status

Check the status of the Zero Downtime Migration to see if it is running, and other service details.

To check the Zero Downtime Migration service status use the following command.

```
zdmuser> $ZDM_HOME/bin/zdm service status
-----
Service Status
-----
Running: false
Transferport:
Conn String: jdbc:derby:/scratch/zdmuser/ZDM/base/derbyRepo;create=true
Repo Path: /scratch/zdmuser/ZDM/base/derbyRepo
RMI port: 8897
HTTP port: 8898
SSH port: 22
Wallet path: /scratch/zdmuser/ZDM/base/crsdata/phoenix/security
```

10.3 Updating Zero Downtime Migration Software

If you already have Zero Downtime Migration software installed on a host, you should always make sure it is the latest available release. Zero Downtime Migration software updates give

you the latest features and fixes while retaining existing job information, metadata, and log files.

Before you begin the software update, review the following requirements.

- Updating Zero Downtime Migration to the latest software can only be done from the latest Zero Downtime Migration kit. The current version is 26.1, and update can be done from version 21.5. Verify your software kit version using the following command:

```
zdmcli -build
full version: "26.1.0"
patch version: ""
label date: 260119
ZDM kit build date: Jan 28 2026 18:32:33 UTC
CPAT build version: 25.11.0
```

- Verify that your existing Zero Downtime Migration software install location has at least 15GB free space.
- Verify that you have enough space to back up the existing Zero Downtime Migration home (ZDM_HOME) and ZDM_BASE to the software download location.
- **Important:** Run the update script from outside of the currently installed Zero Downtime Migration home.

Running the script from within a Zero Downtime Migration home results in home install and uninstall failures and leaves the service in an inconsistent state.

- The path specified in `ziploc` should have read/write access for `zdmuser`.
 - All of the commands in the following procedure should be run as the existing Zero Downtime Migration software owner. For example, run as `zdmuser` in the examples that follow.
1. Download the Zero Downtime Migration software kit from <https://www.oracle.com/database/technologies/rac/zdm-downloads.html> to the Zero Downtime Migration service host.
 2. Change to the directory to where Zero Downtime Migration software is downloaded and unzip the software.

```
zdmuser> cd zdm_download_directory
zdmuser> unzip zdmversion.zip
```

3. Run the `zdminstall.sh` script as the exiting Zero Downtime Migration home owner to update the software from the software download location.

```
zdmuser> ./zdminstall.sh update oraclehome=existing_zdm_oracle_home
ziploc=zdm_software_location
```

- `zdminstall.sh` is the installation and update script
- `oraclehome` is the absolute path to the Oracle Home where the existing Zero Downtime Migration software is installed
- `ziploc` is the location of the compressed software file (zip) included in the Zero Downtime Migration kit

For example,

```
zdmuser> /u01/app/oracle/zdm/shiphome/update/zdminstall.sh update
oraclehome=/u01/app/zdmhome
ziploc=/u01/app/oracle/zdm/shiphome/update/zdm_home.zip
```

The update script does the following operations.

- a. Backs up the existing Zero Downtime Migration home (ZDM_HOME) and ZDM_BASE into software download location
- b. Stops the currently running Zero Downtime Migration service
- c. Removes the currently installed Zero Downtime Migration home
- d. Installs the new binaries in the Zero Downtime Migration home
- e. Restores the configuration data.

The new Zero Downtime Migration home will retain all of the details of any migrations run with the previous Zero Downtime Migration home.

4. The Zero Downtime Migration service must be manually started after the upgrade. Start the Zero Downtime Migration service as user `zdmuser`.

```
zdmuser> $ZDM_HOME/bin/zdmservice start
```

You must start `zdmservice` before you can migrate your databases using Zero Downtime Migration.

If you must stop the Zero Downtime Migration service, run the following command.

```
zdmuser> $ZDM_HOME/bin/zdmservice stop
```

5. Verify that the Zero Downtime Migration service installation is successful.

When you run the following command, the output should be similar to that shown here.

```
zdmuser> $ZDM_HOME/bin/zdmservice status
-----
Service Status
-----
Running: false
Transferport:
Conn String: jdbc:derby:/scratch/zdmuser/ZDM/base/derbyRepo;create=true
Repo Path: /scratch/zdmuser/ZDM/base/derbyRepo
RMI port: 8897
HTTP port: 8898
SSH port: 22
Wallet path: /scratch/zdmuser/ZDM/base/crsdata/phoenix/security
```

10.4 Uninstalling Zero Downtime Migration Software

Remove Zero Downtime Migration software from the Zero Downtime Migration service host.

All commands are run as `zdmuser`.

1. Stop the Zero Downtime Migration service.

```
zdmuser> $ZDM_HOME/bin/zdmservice stop
```

2. Run the following command to uninstall the software.

```
zdmuser> $ZDM_HOME/bin/zdmservice deinstall
```

10.5 Performing a Silent Update or Deinstallation

You can skip the confirmation prompt during Zero Downtime Migration software update or deinstallation to ensure these operations run smoothly.

A `-silent` option is available for `zdminstall.sh update` or `deinstall` operations to avoid being asked for confirmation, as shown in the following examples.

Example of silent update:

```
zdmuser> cd zdm_download_directory
zdmuser> unzip zdmversion.zip
...
zdmuser> ./zdminstall.sh update -silent oraclehome=absolute_path_to_zdm_home
ziploc=zdm_software_location
```

Example of silent deinstall:

```
zdmuser> $ZDM_HOME/bin/zdmservice deinstall -silent
```

10.6 Viewing the Cloud Premigration Advisor Tool Version

There are two ways to display the current version for the Cloud Premigration Advisor Tool (CPAT).

- Run the Cloud Premigration Advisor Tool script with the `--version` option.

```
$ZDM_HOME/rhp/zdm/lib/cpat/premigration.sh --version
```

- Run ZDMCLI with the `-build` option.

```
zdmuser> $ZDM_HOME/bin/zdmcli -build
```

10.7 Updating the Cloud Premigration Advisor Tool

Keep the Cloud Premigration Advisor Tool up to date to get the latest migration remedies, as well as any bug fixes in the tool.

Note

Schedule Cloud Premigration Advisor Tool updates when no migrations are running.

1. Download the latest version of the tool from [Cloud Premigration Advisor Tool \(CPAT\) Analyzes Databases for Suitability of Cloud Migration \(Doc ID 2758371.1\)](#).
2. Check the version of the tool that is currently installed in your Zero Downtime Migration home.

```
./ZDM_home/rhp/zdm/lib/cpat/premigration.sh --version
```

3. Back up the currently installed tool by making a copy of the contents of directory `$ZDM_HOME/rhp/zdm/lib/cpat`.
4. Delete all of the files in directory `$ZDM_HOME/rhp/zdm/lib/cpat`.
5. Unzip the new Cloud Premigration Advisor Tool release file to `$ZDM_HOME/rhp/zdm/lib/cpat`.
6. If needed, change the permissions on the unzipped files to remove unauthorized access.
7. Verify that the new version of the tool is installed in your Zero Downtime Migration home.

```
./ZDM_home/rhp/zdm/lib/cpat/premigration.sh --version
```

Troubleshooting Zero Downtime Migration

This section describes how to handle migration job failures.

For more information about troubleshooting Zero Downtime Migration and known issues in the current release, see the Zero Downtime Migration Release Notes.

11.1 Handling Migration Job Failures

If your migration job fails, the following logs can help you discover the issue.

Migration Job Output Logs

If your migration job encounters an error, refer to the migration job output logs, Zero Downtime Migration service logs, and server-specific operational phase logs present at the respective source or target database servers.

If the migration job encounters an exception (that is, fails) then the logs can provide some indication of the nature of the fault. The logs for the migration procedures executed in the source and target environments are stored on the servers in the respective source and target environments. The Zero Downtime Migration command output location is provided to you when the migration job is run with the ZDMCLI command `migrate database`. You can also find the log file location (Result file path) in the output of the ZDMCLI command `query job -jobid job-id`.

Zero Downtime Migration Service Host Log

Determine which operational phase the migration job was in at the time of failure, and whether the phase belongs to the source (phase name contains SRC) or target (phase name contains TGT) . Check the Zero Downtime Migration service host log at `$ZDM_BASE/crsdata/zdm_service_host/rhp/zdmserver.log.0`, and access the respective source or target server to check the log associated with the operational phase in `$ORACLE_BASE/zdm/zdm_db_unique_name_job-id/zdm/log`.

If the Zero Downtime Migration service does not start, then check the Zero Downtime Migration service logs for process start-up errors to determine the cause of the error reported. The Zero Downtime Migration service log can be found at `$ZDM_BASE/crsdata/zdm_service_host/rhp/zdmserver.log.0`.

Data Pump Log

For logical migration jobs on co-managed target databases, refer to the Data Pump log in the specified `DATA_PUMP_DIR`. For Autonomous Database targets, the Data Pump logs are uploaded to a data bucket specified with `DATAPUMPSETTINGS_DATABUCKET_*` in the response file. If the data bucket is not specified, then you will need to upload the dump from Autonomous Database to Object Storage to access it. See [How To View Import Log Generated For ADW/ATP \(Doc ID 2448060.1\)](#).

If a migration job fails, you can fix the cause of the failure and then re-run the job while monitoring the logs for progress.

The best practice for troubleshooting a migration job is to query the job `tail -f absolute_path_to_log_file` and then, select the logs shown, and tail them. You can tail the job and server logs to get a real time information about the migration jobs.

Tailing the job output file, displayed in the output of the query job with label `Result file path`, is the preferred way of monitoring the progress of a specific job. This avoids excessive tracing in ZDM server logs caused by the `query job` command.

However, it is not recommended to run the query command in a loop, as this command only provides a high level overview on a stage by stage basis, for more detailed analysis, proceed as described above.

A

Database Server Connectivity Using a Bastion Host

Zero Downtime Migration lets you configure connectivity to the source and target database servers through a bastion host for both physical and logical migration work flows.

Note that a bastion host cannot be used to connect to an Autonomous Database, except for JDBC connections.

Use the following sections to configure the appropriate parameters for physical and logical migrations that must connect to the source or target database server through a bastion host.

SSH Connection to Database Servers

Connecting database servers through a bastion host requires the following information:

- **Bastion Host IP Address and Source Database Server IP Address:** To connect to the database server through a bastion host, the bastion host IP address and the source node IP address are required.
- **Bastion Port Number:** The port number defaults to 22 if not specified.
- **Bastion User:** The bastion host user is only required if the user specified for the argument `zdmauth` plug-in is different from the user of the bastion host. The bastion user defaults to the user specified for the source `zdmauth` plug-in if the property is not specified.
- **Bastion Identity File:** If the `SRC/TGT_BASTION_IDENTITY_FILE` parameter is not specified, the value defaults to the value specified for the `identity_file` argument of the `zdmauth` plug-in argument.

Physical Migration Response File Parameters

Configure the following response file parameters for a physical migration.

Source Database Server

`SRC_BASTION_HOST_IP=`

`SRC_BASTION_PORT=`

`SRC_BASTION_USER=`

`SRC_BASTION_IDENTITY_FILE=`

`SRC_HOST_IP=`

Target Database Server

`TGT_BASTION_HOST_IP=`

`TGT_BASTION_PORT=`

`TGT_BASTION_USER=`

`TGT_BASTION_IDENTITY_FILE=`

TGT_HOST_IP=

Logical Migration Response File Parameters

Configure the following response file parameters for a logical migration.

Source Database Server

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP=

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT=

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE=

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME=

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP=

Target Database Server (including Autonomous Database)

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP=

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT=22

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE=

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME=

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP=

B

Zero Downtime Migration Encryption Requirements

Zero Downtime Migration does not always require encryption at the source. However, it is recommended to encrypt all tablespaces in the Cloud. Any new tablespaces created in the Cloud is encrypted by default.

- To verify the encryption state of the tablespaces, use the following query: `SQL> select tablespace_name, encrypted from dba_tablespaces;`
- To encrypt the tablespaces post migration: For encrypting existing tablespaces, see [Encryption Conversions for Tablespaces and Databases](#) for more information.

The following tables list specific cases when encryption is not required.

Table B-1 On-Premises Unencrypted Primary and Cloud Encrypted Standby

Operation	On-Premises Primary 11g R2	Cloud Standby 11g R2	On-Premises Primary 12c R1	Cloud Standby 12c R1	On-Premises Primary 12c R2	Cloud Standby 12c R2 and later	Notes
Data Guard initial setup for on-premises primary and cloud standby	Unencrypted	Encrypted	Unencrypted	Encrypted	Unencrypted	Encrypted	In these cases the standby database is manually encrypted after instantiation
New tablespace creation on-premises primary	Unencrypted	Unencrypted	Unencrypted	Unencrypted	Unencrypted	Unencrypted	Requires manual TDE conversion for standby database
Redo generated in on-premises primary	Unencrypted	Unencrypted	Unencrypted	Unencrypted	Unencrypted	Unencrypted	
Archived logs	Unencrypted	Unencrypted	Unencrypted	Unencrypted	Unencrypted	Unencrypted	
New and changed blocks	Unencrypted	Encrypted	Unencrypted	Encrypted	Unencrypted	Encrypted	Redo shipped from the on-premises primary to the cloud is not encrypted
Recovery in the cloud standby	N/A	Encrypted	N/A	Encrypted	N/A	Encrypted	Redo shipped from the on-premises primary to the cloud is not encrypted

Table B-2 Cloud Encrypted Primary and On-Premises Unencrypted Standby

Operation	Cloud Primary 11g R2	On-Premises Standby 11g R2	Cloud Primary 12c R1	On-Premises Standby 12c R1	Cloud Primary 12c R2	On-Premises Standby 12c R2 and later	Notes
New tablespace creation in cloud primary	Encrypted	Encrypted	Encrypted	Encrypted	Encrypted	Encrypted	ASO required for on-premises to decrypt
Redo generated in cloud primary	Encrypted	Encrypted	Encrypted	Encrypted	Encrypted	Encrypted	ASO required for on-premises to decrypt
Archived logs	Encrypted	Encrypted	Encrypted	Encrypted	Encrypted	Encrypted	ASO required for on-premises to decrypt
New and changed blocks for existing unencrypted tablespace on standby	Encrypted	Encrypted*	Encrypted	Encrypted*	Encrypted	Unencrypted	ASO is required on-premises to decrypt and encrypt * For 11g R2 and 12c R1 redo apply will encrypt only if redo is encrypted
Recovery in the on-premises standby	N/A	Encrypted	N/A	Encrypted	N/A	Unencrypted data depends on whether the datafile is encrypted	ASO required for on-premises database

C

Providing Passwords Non-Interactively Using a Wallet

You can avoid entering passwords in the command line and run the ZDMCLI migrate database command without user interaction, such as when you do automation using Rundeck.

Currently, whenever you submit the `$ZDM_HOME/bin/zdmcli migrate database` command, it prompts for the source database SYS password, Object Store user swift authentication token, and the source database Transparent Data Encryption (TDE) keystore password (if the wallet was configured as a PASSWORD-based TDE wallet).

Wallet Creation Examples

The following examples show how to create auto-login wallets for the source database SYS user, the Object Store user, the source database TDE keystore, and the target CDB database TDE keystore password.

Note

The wallet creation steps mentioned here are indicative for one use case and are applicable for all the wallets accepted through the `WALLET_*` response file parameters.

Run the following commands on the Zero Downtime Migration service host as Zero Downtime Migration software owner (for example, `zdmuser`).

To create an auto-login wallet for the source database SYS user:

1. Create a directory where you want to create and store the wallet.

```
zdmuser> mkdir sys_wallet_path
```

For example:

```
/u01/app/zdmhome> mkdir sysWallet
```

2. Create a wallet.

```
zdmuser> $ZDM_HOME/bin/orapki wallet create -wallet sys_wallet_path  
-auto_login_only
```

For example

```
/u01/app/zdmhome> $ZDM_HOME/bin/orapki wallet create -wallet sysWallet  
-auto_login_only  
Oracle PKI Tool Release 19.0.0.0.0 - Production  
Version 19.4.0.0.0  
Copyright (c) 2004, 2019, Oracle and/or its affiliates. All rights
```

reserved.

Operation is successfully completed.

3. Add a SYS user login credentials to wallet.

```
zdmuser> $ZDM_HOME/bin/mkstore -wrl sys_wallet_path  
-createCredential store sysuser
```

At the prompt, enter the source database SYS password.

For example

```
/u01/app/zdmhome> $ZDM_HOME/bin/mkstore -wrl ./sysWallet  
-createCredential store sysuser  
Oracle Secret Store Tool Release 19.0.0.0.0 - Production  
Version 19.4.0.0.0  
Copyright (c) 2004, 2019, Oracle and/or its affiliates. All rights  
reserved.
```

```
Your secret/Password is missing in the command line  
Enter your secret/Password:  
Re-enter your secret/Password:
```

4. Verify that the wallet files were created.

```
zdmuser> ls -l sys_wallet_path
```

For example

```
/u01/app/zdmhome> ls -l sysWallet/  
total 4  
-rw-----. 1 opc opc 581 Jun  2 08:00 cwallet.sso  
-rw-----. 1 opc opc  0 Jun  2 08:00 cwallet.sso.lck
```

To create an auto-login wallet for the Object Store user:

1. Create a directory where you want to create and store the wallet.

```
zdmuser> mkdir oss_wallet_path
```

For example

```
/u01/app/zdmhome> mkdir ossWallet
```

2. Create a wallet

```
zdmuser> $ZDM_HOME/bin/orapki wallet create -wallet oss_wallet_path  
-auto_login_only
```

For example

```
/u01/app/zdmhome> $ZDM_HOME/bin/orapki wallet create
-wallet ./ossWallet -auto_login_only
Oracle PKI Tool Release 19.0.0.0.0 -Production
Version 19.4.0.0.0
Copyright (c) 2004, 2019,
Oracle and/or its affiliates. All rights reserved.
```

Operation is successfully completed.

3. Add the Object Store user login credentials to the wallet.

```
zdmuser> $ZDM_HOME/bin/mkstore -wrl oss_wallet_path
-createCredential store ossuser
```

For the prompt,

- If the backup destination is Object Store (Bucket), then enter the user swift authentication token.
- If the backup destination is Storage Classic (Container), then enter your tenancy login password.

For example

```
/u01/app/zdmhome> $ZDM_HOME/bin/mkstore -wrl ./ossWallet
-createCredential store ossuser
Oracle Secret Store Tool Release 19.0.0.0.0 - Production
Version 19.4.0.0.0
Copyright (c) 2004, 2019, Oracle and/or its affiliates. All rights
reserved.
```

```
Your secret/Password is missing in the command line
Enter your secret/Password:
Re-enter your secret/Password:
```

4. Verify that the wallet files were created.

```
zdmuser> ls -l oss_wallet_path
```

For example

```
/u01/app/zdmhome> ls -l ./ossWallet
total 4
-rw-----. 1 opc opc 597 Jun  2 08:02 cwallet.sso
-rw-----. 1 opc opc   0 Jun  2 08:01 cwallet.sso.lck
```

To create an auto-login wallet for the source database TDE keystore:

1. Create a directory where you want to create and store the wallet.

```
zdmuser> mkdir tde_wallet_path
```

For example

```
/u01/app/zdmhome> mkdir tdeWallet
```

2. Create a wallet.

```
zdmuser> $ZDM_HOME/bin/orapki wallet create -wallet tde_wallet_path
-auto_login_only
```

For example

```
/u01/app/zdmhome> $ZDM_HOME/bin/orapki wallet create -wallet ./tdeWallet
-auto_login_only
Oracle PKI Tool Release 19.0.0.0.0 - Production
Version 19.4.0.0.0
Copyright (c) 2004, 2019, Oracle and/or its affiliates. All rights
reserved.
```

Operation is successfully completed.

3. Add the source database TDE keystore credentials to the wallet.

```
zdmuser> $ZDM_HOME/bin/mkstore -wrl tde_wallet_path
-createCredential store tdeuser
```

At the prompt, enter the TDE keystore password.

For example

```
/u01/app/zdmhome> $ZDM_HOME/bin/mkstore -wrl ./tdeWallet
-createCredential store tdeuser
Oracle Secret Store Tool Release 19.0.0.0.0 - Production
Version 19.4.0.0.0
Copyright (c) 2004, 2019, Oracle and/or its affiliates. All rights
reserved.
```

```
Your secret/Password is missing in the command line
Enter your secret/Password:
Re-enter your secret/Password:
```

4. Verify that the wallet files were created.

```
zdmuser> ls -l tde_wallet_path
```

For example

```
/u01/app/zdmhome> ls -l tdeWallet
total 4
-rw-----. 1 opc opc 581 Jun  2 08:06 cwallet.sso
-rw-----. 1 opc opc   0 Jun  2 08:04 cwallet.sso.lck
```

To create an auto-login wallet for the target CDB database TDE keystore password:

1. Create a directory where you want to create and store the wallet.

```
zdmuser> mkdir cdb_tde_wallet_path
```

For example

```
/u01/app/zdmhome> mkdir cdbtdeWallet
```

2. Create a wallet.

```
zdmuser> $ZDM_HOME/bin/orapki wallet create -wallet cdb_tde_wallet_path  
-auto_login_only
```

For example

```
/u01/app/zdmhome> $ZDM_HOME/bin/orapki wallet create -wallet ./  
cdbtdeWallet  
-auto_login_only  
Oracle PKI Tool Release 19.0.0.0.0 - Production  
Version 19.4.0.0.0  
Copyright (c) 2004, 2019, Oracle and/or its affiliates. All rights  
reserved.
```

Operation is successfully completed.

3. Add the source database TDE keystore credentials to the wallet.

```
zdmuser> $ZDM_HOME/bin/mkstore -wrl cdb_tde_wallet_path  
-createCredential store cdbtdeuser
```

At the prompt, enter the TDE keystore password.

For example

```
/u01/app/zdmhome> $ZDM_HOME/bin/mkstore -wrl ./cdbtdeWallet  
-createCredential store cdbtdeuser  
Oracle Secret Store Tool Release 19.0.0.0.0 - Production  
Version 19.4.0.0.0  
Copyright (c) 2004, 2019, Oracle and/or its affiliates. All rights  
reserved.
```

Your secret/Password is missing in the command line

Enter your secret/Password:

Re-enter your secret/Password:

To create an auto-login wallet to store the set of passwords for dbuser:

1. Create an auto login wallet to store the set of passwords for dbuser using the following command:

```
./orapki wallet create -wallet <wallet_path> -auto_login_only
```

2. Create the entries for the usernames used by the `-asuser` option, in step 1:

```
./mkstore -wrl <wallet_path> -createEntry <non_admin_user>
```

Accessing the Wallets in a Logical Migration Job

In a logical migration you configure the wallet parameters using the RSP `WALLET_*` parameters appropriate for your migration use case. See the following links for details about the individual parameters.

- [WALLET_AMAZONS3SECRET](#): Amazon S3 Secret Key wallet path
- [WALLET_SOURCEGGADMIN](#): Source database administrative user `ggadmin` password wallet path
- [WALLET_SOURCECONTAINER](#): Source database administrative user password wallet path
- [WALLET_SOURCECGGADMIN](#): Source database administrative user `c##ggadmin` password wallet path
- [WALLET_TARGETADMIN](#): Target database administrative user password wallet path
- [WALLET_TARGETGGADMIN](#): Target database administrative user `ggadmin` password wallet path
- [WALLET_OGGADMIN](#): Oracle GoldenGate hub administrative password wallet path
- [WALLET_DATAPUMPENCRYPTION](#): Oracle Data Pump encryption password wallet path
- [WALLET_OCIAUTHTOKEN](#): OCI Auth Token password wallet path
- `WALLET_USERACTION`: Auto-login wallet to store the set of passwords for `dbuser`

Accessing the Wallets in a Physical Migration Job

In a physical migration you configure the wallet parameters as options in the `ZDMCLI` database migration command. See [migrate database](#) for information about the database migration options.

- `-sourcesyswallet sys_wallet_path`: Source database `sys` password wallet path
- `-osswallet oss_wallet_path`: Object Storage Service (OSS) backup user wallet path
- `-dvwallet dv_wallet_path`: Oracle Database Vault owner wallet path
- `-tdekeystorewallet tde_wallet_path`: Transparent Data Encryption (TDE) keystore password wallet path
- `-tgttdekeystorewallet tde_wallet_path`: Target container database TDE keystore password wallet path
- `-backupwallet backup_wallet_path`: RMAN backup password wallet path

Note that if you are converting a non-multitenant source database to a multitenant architecture on the target, that is a pluggable database (PDB), then you can also create an auto-login wallet for the target container database (CDB) TDE keystore password.

Setting Command Options to Access the Wallets

To specify wallet information in the `ZDMCLI MIGRATE DATABASE` command, set the `-sourcesyswallet`, `-osswallet`, `-tdekeystorewallet`, and `-tgttdekeystorewallet` options as shown here.

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-sourcedb source_db_unique_name_value
-srcenode source_database_server_name
-srcauth zdmauth
-srcarg1 user:source_database_server_login_user_name
-srcarg2 identity_file:zdm_installed_user_private_key_file_location
-srcarg3 sudo_location:/usr/bin/sudo
-targetnode target_database_server_name
-backupuser object_store_login_user_name
-rsp response_file_location
-tgtauth zdmauth
-tgtarg1 user:target_database_server_login_user_name
-tgtarg2 identity_file:zdm_installed_user_private_key_file_location
-tgtarg3 sudo_location:/usr/bin/sudo
-sourcesyswallet sys_wallet_path
-osswallet oss_wallet_path
-tdekeystorewallet tde_wallet_path
-tgttdekeystorewallet cdb_tde_wallet_path
-eval
```

- `-sourcesyswallet sys_wallet_path` specifies the full path for the auto-login wallet file on the Zero Downtime Migration host containing the `sys` password of the source database
- `-osswallet oss_wallet_path` specifies the full path for the auto-login wallet file on the Zero Downtime Migration host containing credentials for the Object Storage Service backup user
- `-tdekeystorewallet tde_wallet_path` specifies the full path for the auto-login wallet file on the Zero Downtime Migration host containing the TDE keystore password
- `-tgttdekeystorewallet cdb_tde_wallet_path` specifies the full path for the auto-login wallet file on the Zero Downtime Migration host containing the target CDB TDE keystore password

Evaluation Mode Example

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-sourcedb zdmsdb
-srcenode ocicdb1
-srcauth zdmauth
-srcarg1 user:opc
-srcarg2 identity_file:/home/zdmuser/.ssh/zdm_service_host.ppk
-srcarg3 sudo_location:/usr/bin/sudo
-targetnode ocicdb1
-backupuser backup_user@example.com
-rsp /u01/app/zdmhome/rhp/zdm/template/zdm_template_zdmsdb.rsp
-tgtauth zdmauth
-tgtarg1 user:opc
-tgtarg2 identity_file:/home/zdmuser/.ssh/zdm_service_host.ppk
-tgtarg3 sudo_location:/usr/bin/sudo
-sourcesyswallet /u01/app/zdmhome/sysWallet
-osswallet /u01/app/zdmhome/ossWallet
-eval
```

Operation "zdmcli migrate database" scheduled with the job ID "1".

Migration Mode Example

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
-sourcedb zdmsdb
-sourcenode ocidb1
-srcauth zdmauth
-srcarg1 user:opc
-srcarg2 identity_file:/home/zdmuser/.ssh/zdm_service_host.ppk
-srcarg3 sudo_location:/usr/bin/sudo
-targetnode ocidb1
-backupuser backup_user@example.com
-rsp /u01/app/zdmhome/rhp/zdm/template/zdm_template_zdmsdb.rsp
-tgtauth zdmauth
-tgtarg1 user:opc
-tgtarg2 identity_file:/home/zdmuser/.ssh/zdm_service_host.ppk
-tgtarg3 sudo_location:/usr/bin/sudo
-sourcesyswallet /u01/app/zdmhome/sysWallet
-osswallet /u01/app/zdmhome/ossWallet
```

Operation "zdmcli migrate database" scheduled with the job ID "2".

D

Zero Downtime Migration Process Phases

The migration job process in Zero Downtime Migration runs in operational phases as a work flow. The tables below describe the phases for physical and logical migrations.

Example D-1 Listing Zero Downtime Migration Process Phases

Run the ZDMCLI `migrate database` command with the `-listphases` option to list the operational phases for your migration job, as shown here.

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database -sourcedb zdmsdb
-sourcenode ocidb1 -srcauth zdmauth -srcarg1 user:opc
-srcarg2 identity_file:/home/zdmuser/.ssh/zdm_service_host.ppk
-srcarg3 sudo_location:/usr/bin/sudo -targetnode ocidb1
-backupuser backup_user@example.com
-rsp /u01/app/zdmhome/rhp/zdm/template/zdm_template_zdmsdb.rsp
-tgtauth zdmauth -tgtarg1 user:opc
-tgtarg2 identity_file:/home/zdmuser/.ssh/zdm_service_host.ppk
-tgtarg3 sudo_location:/usr/bin/sudo -listphases
```

Table D-1 Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
		S
		e
		r
		a
		c
		t
		i
		o
		n
		s
		c
		o
		p
		e
ZDM_GET_SRC_INFO	Both	SGets information about the source database
		O
		U
		R
		C
		E
ZDM_GET_TGT_INFO	Both	TGets information about the target database
		A
		R
		G
		E
		T

Table D-1 (Cont.) Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
		S e r v e r a c t i o n s c o p e
ZDM_SETUP_SRC	Both	SSets up Zero Downtime Migration helper modules On the source server
		U R C E
ZDM_SETUP_TGT	Both	TSets up Zero Downtime Migration helper modules On the target server
		R G E T
ZDM_SETUP_STBY	Online	TSets up Zero Downtime Migration helper modules On the target standby server.
		R G E T
ZDM_GET_STBY_INFO	Online	TGets information about the source database.
		A R G E T
ZDM_PRECHECKS_STBY	Online	TPerforms preliminary validation at the target Astandby such as connectivity validation to source Rscan, db_name, character set validation.
		G E T
ZDM_PREUSERACTIONS_STBY	Online	TRuns migration pre-user actions, if any, at the Atarget standby
		R G E T

Table D-1 (Cont.) Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
		Series of actions to complete
ZDM_OBC_INST_STBY	Online	Installs Oracle Database Cloud Backup Module at the target standby
ZDM_VALIDATE_STBY	Online	Performs validations at the target standby.
ZDM_BACKUP_INCREMENTAL_STBY_SRC	Online	Performs incremental backup of the source database before performing target standby full restore.
ZDM_COPYFILES_TGT_STBY	Online	Offline Copies Oracle password file and TDE wallets from source to target standby.
ZDM_PREPARE_STBY	Online	Prepares target standby for Data Guard standby creation
ZDM_SETUP_TDE_STBY	Online	Copies TDE wallet files from the source to the target standby keystore location.

Table D-1 (Cont.) Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
		Series of operations
ZDM_CLONE_STBY	Online	Instantiates Target Standby and creates Data Guard standby.
ZDM_DUPLICATE_TGT_STBY	Online	Duplicates Source database at Target Standby and creates Data Guard standby.
ZDM_RESTORE_TGT_STBY	Online	Restores from service Target Standby to create Data Guard standby.
ZDM_RECOVER_TGT_STBY	Online	Recovers from service Target Standby to create Data Guard standby.
ZDM_FINALIZE_STBY	Online	Finalizes Data Guard standby preparation of the target standby. Converts the target standby database to RAC if originally provisioned as Oracle RAC.
ZDM_POST_MIGRATE_TGT_STBY	Online	Performs any post database migration tasks such as restoring DBA directories at target standby.

Table D-1 (Cont.) Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_POSTUSERACTIONS_STBY	Online	Performs any post-migration user actions at the target standby.
ZDM_CLEANUP_STBY	Online	Performs clean up at the target standby.
ZDM_GET_STBY_INFO	Online	Standby - Gets information about the target standby database.
ZDM_DUPLICATE_TGT	Online	Instantiates the target database using RMAN Active duplicate.
ZDM_PREUSERACTIONS	Both	Runs migration pre-user actions, if any, at the Source
ZDM_PREUSERACTIONS_TGT	Both	Runs migration pre-user actions, if any, at the Target

Table D-1 (Cont.) Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_VALIDATE_TGT	Both	Performs validations at the target
ZDM_OBC_INST_SRC	Both	Installs Oracle Database Cloud Backup Module at the source
ZDM_OBC_INST_TGT	Both	Installs Oracle Database Cloud Backup Module at the target
ZDM_BACKUP_FULL_SRC	Both	Performs full backup of the source database
ZDM_BACKUP_INCREMENTAL_SRC	Both	Performs incremental backup of the source database
ZDM_DISCOVER_SRC	Both	Performs database discovery at the source for setting up Data Guard

Table D-1 (Cont.) Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_COPYFILES	Both	SCopies Oracle password file and TDE wallets from Source to target URCE
ZDM_SETUP_TDE_TGT	Both	TCopies TDE wallet files from the source to the Target keystore location RGET
ZDM_RESTORE_TARGET	Online	TARGET
ZDM_RECOVER_TARGET	Online	TARGET
ZDM_OSS_RESTORE_TGT	Offline	TPerforms full database restore ARGET
ZDM_BACKUP_DIFFERENTIAL_SRC	Offline	SPerforms differential backup of the source Database URCE

Table D-1 (Cont.) Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_OSS_RECOVER_TGT	Offline	TPerforms incremental restore, recovery database, and opens database with reset logs R G E T
ZDM_PREPARE_TGT	Both	TPrepares target for Data Guard standby creation A R G E T
ZDM_CLONE_TGT	Online	TCreates Data Guard standby from the Cloud backup R G E T
ZDM_CLONE_PDB_TGT	Both	TClones PDB using the DBLink. A R G E T
ZDM_FINALIZE_TGT	Both	TFinalizes Data Guard standby preparation of the target. Converts the target database to RAC if originally provisioned as Oracle RAC. G E T
ZDM_CONFIGURE_DG_SRC	Online	SRegisters the Cloud standby with the source O U R C E

Table D-1 (Cont.) Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_MONITOR_APPLY_LAG	Online	<p>When the job pauses at ZDM_CONFIGURE_DG_SRC phase, ZDM monitors apply lag periodically in this phase at specified interval.</p> <div> <p>Note</p> <p>This phase is applicable only when value of ZDM_APPLY_LAG_MONITORING_INTERVAL is not None.</p> </div>
ZDM_SWITCHOVER_SRC	Online	Initiates switchover actions at the source
ZDM_SWITCHOVER_TGT	Online	Completes switchover actions at the target
ZDM_POST_DATABASE_OPEN_TGT	Both	Performs activities after database is opened, such as restore pluggable database state, DBA Directories, RMAN configuration
ZDM_DATAPATCH_TGT	Both	Runs datapatch at the target

Table D-1 (Cont.) Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_SHUTDOWN_SRC	Both	Shuts down source database at the end of the migration
ZDM_POSTUSERACTIONS	Both	Performs any post-migration user actions at the source
ZDM_POSTUSERACTIONS_TGT	Both	Performs any post-migration user actions at the target
ZDM_CLEANUP_SRC	Both	Performs clean up at the source
ZDM_CLEANUP_TGT	Both	Performs clean up at the target

Table D-1 (Cont.) Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
TIMEZONE_UPGRADE_PRE PARE_TGT	Both	<p>TPerforms prepare upgrade operation when the Atimezone version of the source database is less Rthan the timezone version of the target database. CSkip this phase if the timezone version is same. E T</p>
TIMEZONE_UPGRADE_TGT	Both	<p>TPerforms timezone upgrade operation when the Atimezone version of the source database is less Rthan the timezone version of the target database. CSkip this phase if the timezone version is same. E T</p>
ZDM_RESTORE_TGT	Offline	<p>TPerforms full restore of the database. A R G E T</p>

Note

This phase is applicable only when value of the ZDM_TGT_UPGRADE_TIMEZONE parameter is TRUE.

Note

This phase is applicable only when value of the ZDM_TGT_UPGRADE_TIMEZONE parameter is TRUE.

Table D-1 (Cont.) Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_RECOVER_TGT	Offline	Performs incremental restore of the database.
ZDM_MANIFEST_TO_CLOUD	Both (ExaCS/ExaCC only)	Updates dbaas wallet to update TDE wallet password and sys password that dbaas tooling depends on for any lifecycle operation.
ZDM_NONCDBTOPDB_PRECHECK	Both (non-cdb to pdb conversion use case only)	For the migrations involving conversion to CDB, this phase executes \$DB_HOME/rdbms/admin/Rnoncdb_to_pdb.sql in precheck mode to identify any incompatibility between non-cdb and target CDB.
ZDM_NONCDBTOPDB_CONVERSION	Both (non-cdb to pdb conversion use case only)	Performs unplug/plugin of the non-cdb migrated from the source to convert it to a PDB in target CDB by executing \$DB_HOME/rdbms/admin/Rnoncdb_to_pdb.sql.
ZDM_POST_MIGRATE_TGT	Both	Performs any post database migration tasks such as restoring PDB state, DBA directories.
ZDM_COPYFILES_DIFFERENTIAL	Offline	Offline Copies Oracle password file and TDE wallets from source to target. This is identical to ZDM_COPYFILES, this is additional copy of the TDE wallet and password file done to ensure that the target has the latest encryption keys in case if the keys got updated at the source before differential backup

Table D-1 (Cont.) Physical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_PRECHECKS_SRC	Both	<p>S</p> <p>e</p> <p>r</p> <p>a</p> <p>c</p> <p>t</p> <p>i</p> <p>o</p> <p>n</p> <p>s</p> <p>c</p> <p>o</p> <p>p</p> <p>e</p> <p>Performs preliminary validation at the source such as connectivity validation to target scan .</p>
ZDM_PRECHECKS_TGT	Both	<p>U</p> <p>R</p> <p>C</p> <p>E</p> <p>Performs preliminary validation at the target such as connectivity validation to source scan, db_name, character set validation.</p>
		<p>G</p> <p>E</p> <p>T</p>

Table D-2 Logical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_VALIDATE_TGT	Both	<p>S</p> <p>e</p> <p>r</p> <p>a</p> <p>c</p> <p>t</p> <p>i</p> <p>o</p> <p>n</p> <p>s</p> <p>c</p> <p>o</p> <p>p</p> <p>e</p> <p>Verifies that the target database exists, discovers the database type, and validates access credentials, security, and connectivity.</p> <p>For an Autonomous Database target, sets up the access to the target database from the Zero Downtime Migration node by downloading the target database access wallet with OCI REST services and discovers the target OCPU.</p> <p>Online only: verifies ggadmin user privileges.</p>

Table D-2 (Cont.) Logical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_VALIDATE_SRC	Both	<p>Validates the source database access credentials, database parameter settings.</p> <p>Online only: verifies <code>ggadmin</code> user privileges and GoldenGate capture support for objects in source database.</p> <p>Online only: ZDM now ensures that same GoldenGate schema name is used for source and configuration file <code>GLOBALS</code>.</p>
ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC	Both	<p>Validates the export directory object (if applicable), and checks for sufficient space and permission for specified user in the source database to export dumps. Checks if the specified Oracle Cloud Object Store buckets, data bucket, and wallet bucket are accessible from the source. Also validates the proxy configuration if applicable.</p>
ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT	Both	<p>Verifies that the Data Pump import directory object exists.</p> <p>If a pre-existing DBLINK was specified, checks if it exists and is valid, and ensures that the Autonomous Database requirements for the DBLINK and wallet files are met.</p> <p>For a co-managed target database, ensures that the OCI OSS data bucket and wallet bucket are valid and accessible from the target server.</p> <p>Ensures that the local path to download the dump is valid and has sufficient space.</p>
ZDM_PREPARE_DATAPUMP_SRC	Both	<p>Creates a new directory object for Data Pump, if required. Creates OCI Auth Token to access OCI OSS bucket if required.</p>
ZDM_DATAPUMP_ESTIMATE_SRC	Both	<p>Performs Data Pump export dump size estimation.</p> <p>See also, <code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_ESTIMATEBYSTATISTICS</code>.</p> <p>Not used with DBLINK</p>

Table D-2 (Cont.) Logical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_PREPARE_DATAPUMP_TGT	Both	<p>Creates a new directory object for Data Pump, if required. Stores OCI Auth token in the database for secure OSS access.</p> <p>If migrating via DBLINK, and a DBLINK must be created, creates the necessary database credentials to access the source and create a new DBLINK.</p> <p>Ensures Autonomous Database security requirements are met using DBLINK over SSL.</p>
ZDM_PARALLEL_EXPORT_IMPORT	Both	<p>When using parallel schema migration, this phase, is cumulative of the ZDM_DATAPUMP_EXPORT_SRC, ZDM_UPLOAD_DUMPS_SRC, and ZDM_DATAPUMP_IMPORT_TGT phases, and handles all three actions for a sublist of schemas per thread, that is export, transfer, and import the sublist of schemas in parallel.</p>
ZDM_DATAPUMP_EXPORT_SRC	Both	<p>Starts and monitors the Data Pump Export on the Source database.</p>
ZDM_UPLOAD_DUMPS_SRC	Both	<p>Uploads Data Pump dump files from the source to OCI OSS.</p>
ZDM_DATAPUMP_IMPORT_TGT	Both	<p>Starts import of Data Pump Dumps to the target database, either from the OCI OSS bucket or via DBLINK, and monitors the Data Pump import progress.</p>

Table D-2 (Cont.) Logical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_DATAPUMP_IMPORT_METADATA_TGT	Both	Imports the generated METADATA_ONLY Dumps in the target database. REGEST
ZDM_DATAPUMP_IMPORT_DATA_TGT	Both	Imports the generated DATA_ONLY Dumps in the target database. REGEST
ZDM_DATAPUMP_IMPORT_OPTIMISE_TGT	Both	Imports INDEX and CONSTRAINT by using the AMETADATA_ONLY dumps. REGEST
ZDM_POST_DATAPUMP_SRC	Both	Removes any Data Pump directory object created by Zero Downtime Migration. URCE
ZDM_POST_DATAPUMP_TARGET	Both	Fixes any invalid objects in the target database. Removes the database access and OCI OSS Access credentials that were created for the migration. Removes any DBLINK created by Zero Downtime Migration. Optionally, removes source database dumps stored in OCI OSS bucket.
ZDM_POST_ACTIONS	Both	Removes Autonomous Database access wallet from the Zero Downtime Migration node.
ZDM_PRE_MIGRATION_ADVISOR	Both	Runs the Oracle Database Premigration Advisor Tool on the migration job.
ZDM_VALIDATE_GG_HUB	Online	Verifies GoldenGate Microservices REST endpoints, software configuration, health, and connectivity to the source and target databases.
ZDM_PREPARE_GG_HUB	Online	Registers database connection details and credentials with GoldenGate Microservices.

Table D-2 (Cont.) Logical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_ADD_HEARTBEAT_SRC	Online	Creates GoldenGate heartbeat table in the source database. If the table already exists, sets update frequency to 60 seconds.
ZDM_ADD_SCHEMA_TRAN_DATA_SRC	Online	Prepares the source database schemas for instantiation by enabling schema level supplemental logging.
ZDM_CREATE_GG_EXTRACT_SRC	Online	Starts the GoldenGate Extract process at the source database
ZDM_ADD_HEARTBEAT_TARGET	Online	Creates the GoldenGate heartbeat table in the target database. If the table already exists, sets update frequency to 60 seconds.
ZDM_ADD_CHECKPOINT_TARGET	Online	Creates GoldenGate checkpoint table in the target database to track Replicat progress.
ZDM_CREATE_GG_REPLICAT_TARGET	Online	Creates GoldenGate Replicat process for the target database.

Table D-2 (Cont.) Logical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_START_GG_REPLICAT_TGT	Online	Starts GoldenGate Replicat process for the target database.
ZDM_MONITOR_GG_LAG	Online	Polls the GoldenGate checkpoint and heartbeat data to measure end-to-end apply lag until lag decreases below desired threshold.
ZDM_SWITCHOVER_APP	Online	Performs any manual validation of the target database if required and performs the switchover for the target database.
ZDM_POST_SWITCHOVER_TGT	Online	Performs post-switchover actions for the target database.
ZDM_REFRESH_MVIEW	Online and Offline	Refreshes the materialized views post migration.

Note

No action is performed by the Zero Downtime Migration workflow.

Table D-2 (Cont.) Logical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_PREPARE_SWITCHOVER_APP		<p>Performs the following functions:</p> <ol style="list-style-type: none"> 1. Monitors and wait for the ongoing workload on source database to be completed and the source database to become idle. 2. Stops GoldenGate Extract. 3. Waits for GoldenGate Replicat to complete the Replicat apply process. 4. Stops GoldenGate Replicat.
ZDM_ADVANCE_SEQUENCES		<p>Performs the following functions:</p> <ol style="list-style-type: none"> 1. Queries the sequence values in the source database. 2. Advances the sequences in the target database. All sequences are advanced as part of this phase except the sequences matching the following queries: <pre>select name '_SEQ' from sys.dba_queues select name '_SHSEQ' from sys.dba_queues sequences which have secondary = 'Y' in dba_objects sequences which starts with 'ISEQ\$\$_'</pre>
ZDM_RM_GG_EXTRACT_SRC	Online	<p>Deletes GoldenGate Extract process on source Database</p>

Table D-2 (Cont.) Logical Migration Phase Descriptions

Phase name	Online/Offline	Description
ZDM_RM_GG_REPLICAT_TGT	Online	Deletes GoldenGate Replicat process on target database.
ZDM_DELETE_SCHEMA_T RANDATA_SRC	Online	Disables schema level supplemental logging on source database.
ZDM_RM_HEARTBEAT_SRC	Online	Drops the GoldenGate heartbeat table in source database, if the table was created by Zero Downtime Migration. Otherwise, resets update frequency to original setting.
ZDM_RM_CHECKPOINT_TGT	Online	Drops the GoldenGate checkpoint table in the target database.
ZDM_RM_HEARTBEAT_TGT	Online	Drops the GoldenGate heartbeat table in the target database, if the table was created by Zero Downtime Migration. Otherwise, resets the update frequency to the original value.
ZDM_CLEAN_GG_HUB	Online	Deletes the database connection details and credentials saved with GoldenGate Microservices.

E

Zero Downtime Migration Physical Migration Response File Parameters Reference

The following topics describe the Zero Downtime Migration response file parameters used in physical migrations.

E.1 BACKUP_PATH

BACKUP_PATH specifies a valid path accessible at the source and target for migration backup type.

Property	Description
Syntax	BACKUP_PATH = {STORAGEPATH EXTBACKUP}
Default value	There is no default value.
Range of values	STORAGEPATH - NFS backup location EXTBACKUP - external backup location Leave this parameter value blank for other migration backup types

E.2 DATA_TRANSFER_MEDIUM

DATA_TRANSFER_MEDIUM specifies the media used for the source database backup, or you can specify a direct data transfer method.

Property	Description
Syntax	DATA_TRANSFER_MEDIUM = {OSS EXTBACKUP ZDLRA NFS DIRECT DBLINK}
Default value	OSS

Property	Description
Range of values	<ul style="list-style-type: none"> • OSS - When MIGRATION_METHOD=ONLINE_PHYSICAL, Oracle Data Guard using OSS for standby initialization, supported for Oracle Cloud Infrastructure(OCI) virtual machine or bare metal, Exadata Cloud Service (ExaCS) When MIGRATION_METHOD=OFFLINE_PHYSICAL, specifying OSS will perform the migration using backup and restore through OSS, supported for Oracle Cloud Infrastructure(OCI) virtual machine or bare metal, Exadata Cloud Service (ExaCS) and no SQL*Net connectivity needed between source and target • EXTBACKUP - Oracle Data Guard with existing backup in external location, supported for Exadata Cloud at Customer (ExaCC) • ZDLRA - Oracle Data Guard using ZDLRA for standby initialization, supported for Exadata Cloud at Customer (ExaCC) • NFS - When MIGRATION_METHOD=ONLINE_PHYSICAL, Oracle Data Guard using backup location such as NFS, supported for Exadata Cloud at Customer (ExaCC) When MIGRATION_METHOD=OFFLINE_PHYSICAL, specifying NFS performs the migration using backup and restore through NFS, supported for Exadata Cloud at Customer (ExaCC) and no SQL*Net connectivity needed between source and target • DIRECT - RMAN active database duplication or restore from service to transfer data directly from the source to the target, This transfer method also uses the ZDM_RMAN_DIRECT_METHOD and ZDM_SRC_DB_RESTORE_SERVICE_NAME parameters. See Direct Data Transfer Support and Setting Physical Migration Parameters for more information about using direct data transfer in a physical migration • DBLINK - Direct transfer of data over a database link. For the PDB clone technique (using any PDB clone method), only the database link is supported as the data transfer medium.

E.3 DATAPATCH_WITH_ONE_INSTANCE_RUNNING

DATAPATCH_WITH_ONE_INSTANCE_RUNNING specifies whether or not to stop all instances except one running on the target database server when the datapatch utility is run. When datapatch completes all of the stopped instances are started.

Property	Description
Syntax	<code>DATAPATCH_WITH_ONE_INSTANCE_RUNNING = {TRUE FALSE}</code>
Default value	FALSE
Range of values	TRUE - Stops all instances except one running on the target database server when running the datapatch utility. FALSE - Does not stop all instances except one running on the target database server when running the datapatch utility.

E.4 HOST

HOST specifies the cloud storage REST endpoint URL to access Oracle Cloud Object Storage.

Property	Description
Syntax	<code>HOST = rest_endpoint_url</code>
Default value	There is no default value.
Range of values	For Oracle Cloud Infrastructure storage the typical value format is <code>https://swiftobjectstorage.us-phoenix-1.oraclecloud.com/v1/ObjectStorageNamespace</code> For Oracle Cloud Infrastructure Classic storage the typical value format is <code>https://acme.storage.oraclecloud.com/v1/Storage-tenancy_name</code>

Usage Notes

To access Oracle Cloud Object Storage, you must set both the HOST and OPC_CONTAINER parameters.

E.5 MAX_DATAPATCH_DURATION_MINS

MAX_DATAPATCH_DURATION_MINS specifies a timeout value, in minutes, after which if the datapatch utility has failed to complete then the operation is stopped.

Property	Description
Syntax	<code>MAX_DATAPATCH_DURATION_MINS = minutes</code>
Default value	There is no default value. Zero Downtime Migration waits until datapatch completes by default.

E.6 MIGRATION_METHOD

MIGRATION_METHOD specifies whether the migration uses Oracle Data Guard (online) or backup and restore (offline).

Property	Description
Syntax	<code>MIGRATION_METHOD = { ONLINE_PHYSICAL OFFLINE_PHYSICAL }</code>
Default value	This is no default value
Range of values	<code>ONLINE_PHYSICAL</code> uses Data Guard switchover migration method <code>OFFLINE_PHYSICAL</code> uses backup and restore database migration method

E.7 NONCDBTOPDB_CONVERSION

`NONCDBTOPDB_CONVERSION` indicates whether to convert a source database from non-CDB to PDB or skip the conversion.

Property	Description
Syntax	<code>NONCDBTOPDB_CONVERSION = { TRUE FALSE }</code>
Default value	<code>FALSE</code>
Range of values	<code>TRUE</code> performs the conversion <code>FALSE</code> does not perform the conversion

E.8 NONCDBTOPDB_SWITCHOVER

`NONCDBTOPDB_SWITCHOVER`, for a physical migration using Data Guard switchover, indicates whether the switchover operations will be executed during a migration job with non-CDB to PDB conversion enabled.

Property	Description
Syntax	<code>NONCDBTOPDB_SWITCHOVER = { TRUE FALSE }</code>
Default value	<code>TRUE</code>
Range of values	<code>TRUE</code> performs the switchover <code>FALSE</code> does not perform the switchover

E.9 OPC_CONTAINER

`OPC_CONTAINER` specifies the Object Storage bucket (called the container on Oracle Cloud Infrastructure Classic), and is set to access Oracle Cloud Object Storage.

Property	Description
Syntax	<code>OPC_CONTAINER = <i>bucket</i></code>
Default value	There is no default value.

Usage Notes

To access Oracle Cloud Object Storage, you must set both the `HOST` and `OPC_CONTAINER` parameters.

The bucket is also referred to as a container for Oracle Cloud Infrastructure Classic storage.

E.10 FLASHBACK_ON

FLASHBACK_ON specifies to enable or disable flashback on the target database during post-migration phase.

Property	Description
Syntax	FLASHBACK_ON = {TRUE FALSE}
Default value	There is no default value.
Range of values	<ul style="list-style-type: none">TRUE = Enables FLASHBACK_ONFALSE = Disables FLASHBACK_ON.
Required	No
Modifiable on Resume	Yes

If you do not set the value for the FLASHBACK_ON parameter, then the source database's flashback status will remain on the target database after migration.

E.11 PLATFORM_TYPE

PLATFORM_TYPE specifies the target database platform.

Property	Description
Syntax	PLATFORM_TYPE = {VMDB EXACS EXACC NON_CLOUD}
Default value	VMDB
Range of values	<p>VMDB - indicates target platform is Oracle Cloud Infrastructure(OCI) virtual machine or bare metal</p> <p>EXACS - indicates target platform is Exadata Cloud Service</p> <p>EXACC - indicates target platform is Exadata Cloud at Customer</p> <p>You can use EXACS or EXACC for Oracle Exadata Database Service on Exascale Infrastructure</p> <p>NON_CLOUD - indicates the target is an on-premises environment</p>

E.12 SHUTDOWN_SRC

SHUTDOWN_SRC specifies whether or not to shut down the source database after migration completes.

Property	Description
Syntax	SHUTDOWN_SRC = {TRUE FALSE}
Default value	FALSE

Property	Description
Range of values	TRUE - Shut down the source database after migration completes. FALSE - Does not shut down the source database after migration completes.

E.13 SKIP_FALLBACK

SKIP_FALLBACK specifies whether or not to ship redo logs from the primary (target) database to the standby (source) database, either voluntarily or because there is no connectivity between the target and source database servers.

Property	Description
Syntax	SKIP_FALLBACK = {TRUE FALSE}
Default value	FALSE
Range of values	TRUE - do not ship redo logs from the primary (target) database to the standby (source) database. FALSE - ship redo logs from the primary (target) database to the standby (source) database.

E.14 SKIP_SRC_SERVICE_RETENTION

SKIP_SRC_SERVICE_RETENTION specifies whether or not to retain the source database services and run them on the target database. This parameter is only valid for MIGRATION_METHOD=OFFLINE_PHYSICAL . .

Property	Description
Syntax	SKIP_SRC_SERVICE_RETENTION = {TRUE FALSE}
Default value	FALSE
Range of values	TRUE - Do not retain the source database services. FALSE - Retain the source database services.

E.15 SRC_BASTION_HOST_IP

SRC_BASTION_HOST_IP specifies the bastion host IP address, if you want to connect to the source database server using a bastion host.

Property	Description
Syntax	SRC_BASTION_HOST_IP = IP_address
Default value	There is no default value.

Usage Notes

If you want to connect to the source database server using a bastion host, values for the bastion host IP address parameter, `SRC_BASTION_HOST_IP`, and the source database host IP address parameter, `SRC_HOST_IP`, are required in the Zero Downtime Migration response file.

If you do not want to use the default value, set the following parameters for bastion host connection.

`SRC_BASTION_PORT` - The port number defaults to 22 if not specified.

`SRC_BASTION_USER` - The bastion host source user is only required if the user specified for the source `zdmauth` plug-in is different from the user of the source bastion host. The bastion user defaults to the user specified for the source `zdmauth` plug-in if the parameter is not specified.

`SRC_BASTION_IDENTITY_FILE` - If not specified, the value defaults to the value specified for the `identity_file` argument of the source `zdmauth` plug-in.

E.16 SRC_BASTION_IDENTITY_FILE

`SRC_BASTION_IDENTITY_FILE` specifies the identity file to access the bastion host as the indicated user.

Property	Description
Syntax	<code>SRC_BASTION_IDENTITY_FILE = identity_file</code>
Default value	If not specified, the value defaults to the value specified for the <code>identity_file</code> argument of the source <code>zdmauth</code> plug-in.

Usage Notes

If you want to connect to the source database server using a bastion host, values for the bastion host IP address parameter, `SRC_BASTION_HOST_IP`, and the source database server IP address parameter, `SRC_HOST_IP`, are required in the Zero Downtime Migration response file.

If you do not want to use the default value, set the following parameters for bastion host connection.

`SRC_BASTION_PORT` - The port number defaults to 22 if not specified.

`SRC_BASTION_USER` - The bastion host source user is only required if the user specified for the source `zdmauth` plug-in is different from the user of the source bastion host. The bastion user defaults to the user specified for the source `zdmauth` plug-in if the parameter is not specified.

`SRC_BASTION_IDENTITY_FILE` - If not specified, the value defaults to the value specified for the `identity_file` argument of the source `zdmauth` plug-in.

E.17 SRC_BASTION_PORT

`SRC_BASTION_PORT` specifies the bastion host port number, if you want to connect to the source database server using a bastion host.

Property	Description
Syntax	<code>SRC_BASTION_PORT = port_number</code>
Default value	22

Usage Notes

If you want to connect to the source database server using a bastion host, values for the bastion host IP address parameter, `SRC_BASTION_HOST_IP`, and the source database server IP address parameter, `SRC_HOST_IP`, are required in the Zero Downtime Migration response file.

If you do not want to use the default value, set the following parameters for bastion host connection.

`SRC_BASTION_PORT` - The port number defaults to 22 if not specified.

`SRC_BASTION_USER` - The bastion host source user is only required if the user specified for the source `zdmauth` plug-in is different from the user of the source bastion host. The bastion user defaults to the user specified for the source `zdmauth` plug-in if the parameter is not specified.

`SRC_BASTION_IDENTITY_FILE` - If not specified, the value defaults to the value specified for the `identity_file` argument of the source `zdmauth` plug-in.

E.18 SRC_BASTION_USER

`SRC_BASTION_USER` specifies the bastion user, if you want to connect to the source database server using a bastion host.

Property	Description
Syntax	<code>SRC_BASTION_USER = bastion_user</code>
Default value	The bastion user defaults to the user specified for the source <code>zdmauth</code> plug-in if the parameter is not specified.

Usage Notes

If you want to connect to the source database server using a bastion host, values for the bastion host IP address parameter, `SRC_BASTION_HOST_IP`, and the source database server IP address parameter, `SRC_HOST_IP`, are required in the Zero Downtime Migration response file.

If you do not want to use the default value, set the following parameters for bastion host connection.

`SRC_BASTION_PORT` - The port number defaults to 22 if not specified.

`SRC_BASTION_USER` - The bastion host source user is only required if the user specified for the source `zdmauth` plug-in is different from the user of the source bastion host. The bastion user defaults to the user specified for the source `zdmauth` plug-in if the parameter is not specified.

`SRC_BASTION_IDENTITY_FILE` - If not specified, the value defaults to the value specified for the `identity_file` argument of the source `zdmauth` plug-in.

E.19 SRC_CONFIG_LOCATION

`SRC_CONFIG_LOCATION` specifies the SSH configuration file location on the Zero Downtime Migration service host (host where Zero Downtime Migration service is running).

Property	Description
Syntax	<code>SRC_CONFIG_LOCATION =</code> <code>SSH_config_file_path</code>
Default value	<code>User_home/.ssh/config</code>

Usage Notes

Set `SRC_CONFIG_LOCATION` to the full path of the SSH configuration file location on the Zero Downtime Migration service host, for example, `/home/crsuser/.ssh/config`.

E.20 SRC_DB_LISTENER_HOST

`SRC_DB_LISTENER_HOST` indicates the source database listener port. Set this property when the source database is a standalone database (no Grid Infrastructure) configured with non-default SCAN listener port other than 1521.

Note

Starting with Oracle Zero Downtime Migration 26.1 release, the `SRC_DB_LISTENER_HOST` parameter is deprecated and will be desupported in a future release. This parameter is replaced by the `SRC_DB_HOST` parameter.

Property	Description
Syntax	<code>SRC_DB_LISTENER_HOST =</code> <code>listener_port_number</code>
Default value	1521

E.21 SRC_DB_LISTENER_PORT

`SRC_DB_LISTENER_PORT` indicates the source database listener port. Set this property when the source database is a standalone database (no Grid Infrastructure) configured with non-default SCAN listener port other than 1521.

Note

Starting with Oracle Zero Downtime Migration 26.1 release, the `SRC_DB_LISTENER_PORT` parameter is deprecated and will be desupported in a future release. This parameter is replaced by the `SRC_DB_PORT` parameter.

Property	Description
Syntax	<code>SRC_DB_LISTENER_PORT = listener_port_number</code>
Default value	1521

E.22 SRC_DB_HOSTNAME

`SRC_DB_HOSTNAME` indicates the source database's SCAN name. For Oracle Clusterware managed databases, ZDM automatically discovers the value from the configuration.

Provide a valid SCAN name or a valid host name when you have configured the source database as a standalone database (no Grid Infrastructure) or when you need to override the value.

Property	Description
Syntax	<code>SRC_DB_HOSTNAME = scan_name</code>
Default value	There is no default value.

E.23 SRC_DB_PORT

`SRC_DB_PORT` indicates the source database's SCAN port. For Oracle Clusterware managed databases, ZDM automatically discovers the value from the configuration.

Provide a valid SCAN port or a valid host port when you have configured the source database as a standalone database (no Grid Infrastructure) or when you need to override the value.

Property	Description
Syntax	<code>SRC_DB_PORT = scan_listener_port_number</code>
Default value	1521

E.24 SRC_HOST_IP

`SRC_HOST_IP` specifies the IP to be used to connect to the source database host from the bastion host. This IP would not be reachable from the ZDM host. It is expected to be reachable from the bastion host.

Property	Description
Syntax	<code>SRC_HOST_IP = IP_address</code>
Default value	There is no default value.

Usage Notes

If you want to connect to the source database server using a bastion host, values for the bastion host IP address parameter, `SRC_BASTION_HOST_IP`, and the source database server IP address parameter, `SRC_HOST_IP`, are required in the Zero Downtime Migration response file.

If you do not want to use the default value, set the following parameters for bastion host connection.

SRC_BASTION_PORT - The port number defaults to 22 if not specified.

SRC_BASTION_USER - The bastion host source user is only required if the user specified for the source `zdmauth` plug-in is different from the user of the source bastion host. The bastion user defaults to the user specified for the source `zdmauth` plug-in if the parameter is not specified.

SRC_BASTION_IDENTITY_FILE - If not specified, the value defaults to the value specified for the `identity_file` argument of the source `zdmauth` plug-in.

E.25 SRC_HTTP_PROXY_PORT

SRC_HTTP_PROXY_PORT specifies the HTTPS proxy port number on the source database server if an SSH connection needs to connect using a proxy.

Property	Description
Syntax	<code>SRC_HTTP_PROXY_PORT = https_proxy_port_number</code>
Default value	There is no default value.

E.26 SRC_HTTP_PROXY_URL

SRC_HTTP_PROXY_URL specifies the HTTPS proxy URL on the source database server if an SSH connection needs to connect using a proxy.

Property	Description
Syntax	<code>SRC_HTTP_PROXY_URL = https_proxy_url</code>
Default value	There is no default value.

E.27 SRC_OSS_PROXY_HOST

SRC_OSS_PROXY_HOST specifies the Object Storage Service proxy host on the source database server if a proxy is needed for connecting to the Object Store.

Property	Description
Syntax	<code>SRC_OSS_PROXY_HOST = oss_proxy_host</code>
Default value	There is no default value.

Usage Notes

Set both the `SRC_OSS_PROXY_HOST` and `SRC_OSS_PROXY_PORT` parameters if a proxy is needed for connecting to the Object Store.

E.28 SRC_OSS_PROXY_PORT

SRC_OSS_PROXY_PORT specifies the Object Storage Service proxy port number on the source database server if a proxy is needed for connecting to the Object Store.

Property	Description
Syntax	<code>SRC_OSS_PROXY_PORT = oss_proxy_port_number</code>
Default value	There is no default value.

Usage Notes

Set both the `SRC_OSS_PROXY_HOST` and `SRC_OSS_PROXY_PORT` parameters if a proxy is needed for connecting to the Object Store.

E.29 SRC_RMAN_CHANNELS

`SRC_RMAN_CHANNELS` specifies the number of RMAN channels to be allocated at the source database server for performing RMAN backups.

Property	Description
Syntax	<code>SRC_RMAN_CHANNELS = number_of_channels</code>
Default value	10

E.30 SRC_SSH_RETRY_TIMEOUT

`SRC_SSH_RETRY_TIMEOUT` specifies a timeout value, in minutes, after which Zero Downtime Migration stops attempting SSH connections after an initial failure to connect.

Property	Description
Syntax	<code>SRC_SSH_RETRY_TIMEOUT = number_of_minutes</code>
Default value	There is no default value.

E.31 SRC_TIMEZONE

`SRC_TIMEZONE` specifies the source database server time zone, which is needed for Single Instance Source Databases where there is no Grid Infrastructure configured.

Property	Description
Syntax	<code>SRC_TIMEZONE = source_db_time_zone</code>
Default value	There is no default value.

E.32 SRC_ZDLRA_WALLET_LOC

`SRC_ZDLRA_WALLET_LOC` specifies the path of the Zero Data Loss Recovery Appliance wallet on the source database server.

Property	Description
Syntax	<p>SRC_ZDLRA_WALLET_LOC = <i>source_zdlra_wallet_location</i></p> <p>The expected format for the location is /u02/app/ oracle/product/12.1.0/dbhome_3/dbs/ zdlra</p>
Default value	There is no default value.

Usage Notes

When using Zero Data Loss Recovery Appliance as the migration backup medium, you must set the following parameters.

SRC_ZDLRA_WALLET_LOC

TGT_ZDLRA_WALLET_LOC

ZDLRA_CRED_ALIAS

E.33 TGT_BASTION_HOST_IP

TGT_BASTION_HOST_IP specifies the bastion host IP address, if you want to connect to the target database server using a bastion host.

Property	Description
Syntax	<p>TGT_BASTION_HOST_IP = <i>bastion_ip_address</i></p>
Default value	There is no default value.

Usage Notes

If you want to connect to the target database server using a bastion host, you are required to configure values for the bastion host IP address parameter, TGT_BASTION_HOST_IP, and the target database server IP address parameter, TGT_HOST_IP, in the Zero Downtime Migration response file.

If you do not want to use the default values for the remaining bastion connection parameters, set the following parameters to configure the bastion host connection.

TGT_BASTION_PORT - The port number defaults to 22 if not specified.

TGT_BASTION_USER - The bastion host target user is only required if the user specified for the target `zdmauth` plug-in is different from the user of the target bastion host. The bastion user defaults to the user specified for the target `zdmauth` plug-in if the parameter is not specified.

TGT_BASTION_IDENTITY_FILE - If not specified, the value defaults to the value specified for the `identity_file` argument of the target `zdmauth` plug-in.

E.34 TGT_BASTION_IDENTITY_FILE

TGT_BASTION_IDENTITY_FILE specifies the identity file to access the bastion host as the indicated user.

Property	Description
Syntax	TGT_BASTION_IDENTITY_FILE = <i>identity_file</i>
Default value	If not specified, the value defaults to the value specified for the <i>identity_file</i> argument of the target <i>zdmauth</i> plug-in.

Usage Notes

If you want to connect to the target database server using a bastion host, you are required to configure values for the bastion host IP address parameter, TGT_BASTION_HOST_IP, and the target database server IP address parameter, TGT_HOST_IP, in the Zero Downtime Migration response file.

If you do not want to use the default values for the remaining bastion connection parameters, set the following parameters to configure the bastion host connection.

TGT_BASTION_PORT - The port number defaults to 22 if not specified.

TGT_BASTION_USER - The bastion host target user is only required if the user specified for the target *zdmauth* plug-in is different from the user of the target bastion host. The bastion user defaults to the user specified for the target *zdmauth* plug-in if the parameter is not specified.

TGT_BASTION_IDENTITY_FILE - If not specified, the value defaults to the value specified for the *identity_file* argument of the target *zdmauth* plug-in.

E.35 TGT_BASTION_PORT

TGT_BASTION_PORT specifies the bastion host port number, if you want to connect to the target database server using a bastion host.

Property	Description
Syntax	TGT_BASTION_PORT = <i>port_number</i>
Default value	22

Usage Notes

If you want to connect to the target database server using a bastion host, you are required to configure values for the bastion host IP address parameter, TGT_BASTION_HOST_IP, and the target database server IP address parameter, TGT_HOST_IP, in the Zero Downtime Migration response file.

If you do not want to use the default values for the remaining bastion connection parameters, set the following parameters to configure the bastion host connection.

TGT_BASTION_PORT - The port number defaults to 22 if not specified.

TGT_BASTION_USER - The bastion host target user is only required if the user specified for the target *zdmauth* plug-in is different from the user of the target bastion host. The bastion user defaults to the user specified for the target *zdmauth* plug-in if the parameter is not specified.

TGT_BASTION_IDENTITY_FILE - If not specified, the value defaults to the value specified for the *identity_file* argument of the target *zdmauth* plug-in.

E.36 TGT_BASTION_USER

TGT_BASTION_USER specifies the bastion user, if you want to connect to the target database server using a bastion host.

Property	Description
Syntax	TGT_BASTION_USER = <i>bastion_user</i>
Default value	The bastion user defaults to the user specified for the target <code>zdmauth</code> plug-in if the parameter is not specified.

Usage Notes

If you want to connect to the target database server using a bastion host, you are required to configure values for the bastion host IP address parameter, TGT_BASTION_HOST_IP, and the target database server IP address parameter, TGT_HOST_IP, in the Zero Downtime Migration response file.

If you do not want to use the default values for the remaining bastion connection parameters, set the following parameters to configure the bastion host connection.

TGT_BASTION_PORT - The port number defaults to 22 if not specified.

TGT_BASTION_USER - The bastion host target user is only required if the user specified for the target `zdmauth` plug-in is different from the user of the target bastion host. The bastion user defaults to the user specified for the target `zdmauth` plug-in if the parameter is not specified.

TGT_BASTION_IDENTITY_FILE - If not specified, the value defaults to the value specified for the `identity_file` argument of the target `zdmauth` plug-in.

E.37 TGT_CONFIG_LOCATION

TGT_CONFIG_LOCATION specifies the SSH configuration file location on the Zero Downtime Migration service host (host where Zero Downtime Migration service is running).

Property	Description
Syntax	TGT_CONFIG_LOCATION = <i>SSH_config_file_path</i>
Default value	<i>User_home/.ssh/config</i>

Usage Notes

Set TGT_CONFIG_LOCATION to the full path of the SSH configuration file location on the Zero Downtime Migration service host, for example, `/home/crsuser/.ssh/config`.

E.38 TGT_DATAACFS

TGT_DATAACFS specifies the location for the data files ACFS volume (data) on the target database. Use only if required to override the values discovered automatically by Zero Downtime Migration.

Property	Description
Syntax	TGT_DATAACFS = <i>data_location</i>
Default value	There is no default value.

Usage Notes

Zero Downtime Migration discovers the location for ASM and ACFS data, redo, and reco storage volumes from the specified target database, making these target database storage properties optional.

If you need to override the values automatically discovered by Zero Downtime Migration, then you can set the following parameters. For example, TGT_DATADG=+DATAC3

For ASM use these parameters

TGT_DATADG

TGT_REDODG

TGT_RECODG

For ACFS use these parameters

TGT_DATAACFS

TGT_REDOACFS

TGT_RECOACFS

E.39 TGT_DATADG

TGT_DATADG specifies the location for the data files ASM disk group (data) on the target database. Use only if required to override the values discovered automatically by Zero Downtime Migration.

Property	Description
Syntax	TGT_DATADG = <i>data_location</i>
Default value	There is no default value.

Usage Notes

Zero Downtime Migration discovers the location for ASM and ACFS data, redo, and reco storage volumes from the specified target database, making these target database storage properties optional.

If you need to override the values automatically discovered by Zero Downtime Migration, then you can set the following parameters. For example, TGT_DATADG=+DATAC3

For ASM use these parameters

TGT_DATADG

TGT_REDODG

TGT_RECODG

For ACFS use these parameters

TGT_DATAACFS

TGT_REDOACFS

TGT_RECOACFS

E.40 TGT_DB_UNIQUE_NAME

TGT_DB_UNIQUE_NAME is used by Zero Downtime Migration to identify the target database.

Property	Description
Syntax	TGT_DB_UNIQUE_NAME = <i>value of target database DB_UNIQUE_NAME</i>
Default value	

Usage Notes

Set TGT_DB_UNIQUE_NAME to the target database DB_UNIQUE_NAME value.

If the target database is Oracle Cloud Infrastructure, Oracle Exadata Database Service on Dedicated Infrastructure, or Oracle Exadata Database Service on Cloud@Customer, the target database DB_UNIQUE_NAME parameter value must be unique to ensure that Oracle Data Guard can identify the target as a different database from the source database.

E.41 TGT_DB_HOSTNAME

TGT_DB_HOSTNAME indicates the target database's SCAN name. For Oracle Clusterware managed databases, ZDM automatically discovers the value from the configuration.

Provide a valid SCAN name or a valid host name when you have configured the target database as a standalone database (no Grid Infrastructure) or when you need to override the value.

Property	Description
Syntax	TGT_DB_HOSTNAME = <i>scan_name</i>
Default value	There is no default value.

E.42 TGT_DB_PORT

TGT_DB_PORT indicates the target database's SCAN port. For Oracle Clusterware managed databases, ZDM automatically discovers the value from the configuration.

Provide a valid SCAN port or a valid host port when you have configured the target database as a standalone database (no Grid Infrastructure) or when you need to override the value.

Property	Description
Syntax	TGT_DB_PORT = <i>scan_listener_port_number</i>
Default value	1521

E.43 TGT_HOST_IP

TGT_HOST_IP specifies the IP to be used to connect to the target database host from bastion host. This IP would not be reachable from ZDM host. It is expected to be reachable from bastion host.

Property	Description
Syntax	TGT_HOST_IP = <i>IP_address</i>
Default value	There is no default value.

Usage Notes

If you want to connect to the target database server using a bastion host, you are required to configure values for the bastion host IP address parameter, TGT_BASTION_HOST_IP, and the target database server IP address parameter, TGT_HOST_IP, in the Zero Downtime Migration response file.

If you do not want to use the default values for the remaining bastion connection parameters, set the following parameters to configure the bastion host connection.

TGT_BASTION_PORT - The port number defaults to 22 if not specified.

TGT_BASTION_USER - The bastion host target user is only required if the user specified for the target `zdmauth` plug-in is different from the user of the target bastion host. The bastion user defaults to the user specified for the target `zdmauth` plug-in if the parameter is not specified.

TGT_BASTION_IDENTITY_FILE - If not specified, the value defaults to the value specified for the `identity_file` argument of the target `zdmauth` plug-in.

E.44 TGT_HTTP_PROXY_PORT

TGT_HTTP_PROXY_PORT specifies the HTTPS proxy port if an SSH connection needs to use a proxy to connect to the target database server.

Property	Description
Syntax	TGT_HTTP_PROXY_PORT = <i>https_proxy_port_number</i>
Default value	There is no default value.

Usage Notes

Set both the TGT_HTTP_PROXY_URL and TGT_HTTP_PROXY_PORT parameters if the SSH connection needs to use an HTTPS proxy to connect to the target database server.

E.45 TGT_HTTP_PROXY_URL

TGT_HTTP_PROXY_URL specifies the HTTPS proxy URL if an SSH connection needs to use a proxy to connect to the target database server.

Property	Description
Syntax	TGT_HTTP_PROXY_URL = <i>https_proxy_url</i>
Default value	There is no default value.

Usage Notes

Set both the TGT_HTTP_PROXY_URL and TGT_HTTP_PROXY_PORT parameters if the SSH connection needs to use an HTTPS proxy to connect to the target database server.

E.46 TGT_OSS_PROXY_HOST

TGT_OSS_PROXY_HOST specifies the Object Storage Service proxy host on the target database server if a proxy is needed for connecting to the Object Store.

Property	Description
Syntax	TGT_OSS_PROXY_HOST = <i>oss_proxy_host</i>
Default value	There is no default value.

Usage Notes

Set both the TGT_OSS_PROXY_HOST and TGT_OSS_PROXY_PORT parameters if a proxy is needed for connecting to the Object Store.

E.47 TGT_OSS_PROXY_PORT

TGT_OSS_PROXY_PORT specifies the Object Storage Service proxy port number on the target database server if a proxy is needed for connecting to the Object Store.

Property	Description
Syntax	TGT_OSS_PROXY_PORT = <i>oss_proxy_port_number</i>
Default value	There is no default value.

Usage Notes

Set both the TGT_OSS_PROXY_HOST and TGT_OSS_PROXY_PORT parameters if a proxy is needed for connecting to the Object Store.

E.48 TGT_RECOACFS

TGT_RECOACFS specifies the location for the fast recovery area ACFS volume (*reco*) on the target database. Use only if required to override the values discovered automatically by Zero Downtime Migration.

Property	Description
Syntax	TGT_RECOACFS = <i>reco_location</i>
Default value	There is no default value.

Usage Notes

Zero Downtime Migration discovers the location for ASM and ACFS data, redo, and reco storage volumes from the specified target database, making these target database storage properties optional.

If you need to override the values automatically discovered by Zero Downtime Migration, then you can set the following parameters. For example, TGT_DATADG=+DATA3

For ASM use these parameters

TGT_DATADG

TGT_REDOG

TGT_RECODG

For ACFS use these parameters

TGT_DATAACFS

TGT_REDOACFS

TGT_RECOACFS

E.49 TGT_RECODG

TGT_RECODG specifies the location for the fast recovery area ASM disk group (reco) on the target database. Use only if required to override the values discovered automatically by Zero Downtime Migration.

Property	Description
Syntax	TGT_RECODG = <i>reco_location</i>
Default value	There is no default value.

Usage Notes

Zero Downtime Migration discovers the location for ASM and ACFS data, redo, and reco storage volumes from the specified target database, making these target database storage properties optional.

If you need to override the values automatically discovered by Zero Downtime Migration, then you can set the following parameters. For example, TGT_DATADG=+DATA3

For ASM use these parameters

TGT_DATADG

TGT_REDOG

TGT_RECODG

For ACFS use these parameters

TGT_DATAACFS

TGT_REDOACFS

TGT_RECOACFS

E.50 TGT_REDOACFS

TGT_REDOACFS specifies the location for redo log files ACFS volume (*redo*) on the target database. Use only if required to override the values discovered automatically by Zero Downtime Migration.

Property	Description
Syntax	TGT_REDOACFS = <i>redo_location</i>
Default value	There is no default value.

Usage Notes

Zero Downtime Migration discovers the location for ASM and ACFS data, redo, and reco storage volumes from the specified target database, making these target database storage properties optional.

If you need to override the values automatically discovered by Zero Downtime Migration, then you can set the following parameters. For example, TGT_DATADG=+DATAC3

For ASM use these parameters

TGT_DATADG

TGT_REDODG

TGT_RECODG

For ACFS use these parameters

TGT_DATAACFS

TGT_REDOACFS

TGT_RECOACFS

E.51 TGT_REDODG

TGT_REDODG specifies the location for redo log files ASM disk group (*redo*) on the target database. Use only if required to override the values discovered automatically by Zero Downtime Migration.

Property	Description
Syntax	TGT_REDODG = <i>redo_location</i>
Default value	There is no default value.

Usage Notes

Zero Downtime Migration discovers the location for ASM and ACFS data, redo, and reco storage volumes from the specified target database, making these target database storage properties optional.

If you need to override the values automatically discovered by Zero Downtime Migration, then you can set the following parameters. For example, TGT_DATADG=+DATAC3

For ASM use these parameters

TGT_DATADG

TGT_REDO DG

TGT_REC DG

For ACFS use these parameters

TGT_DATAACFS

TGT_REDOACFS

TGT_RECOACFS

E.52 TGT_RETAIN_DB_UNIQUE_NAME

TGT_RETAIN_DB_UNIQUE_NAME specifies whether to ship redo logs from Oracle Cloud to the on-premises standby, observe the environment for some time, and remove the fallback later.

Note

Oracle recommends to skip the TGT_RETAIN_DB_UNIQUE_NAME parameter.

When TGT_RETAIN_DB_UNIQUE_NAME=TRUE then the workflow phase ZDM_RETAIN_DBUNIQUE_NAME_TGT is present as the final phase. You must pause the migration job at a prior phase and resume the job when the fallback has to be removed.

Property	Description
Syntax	TGT_RETAIN_DB_UNIQUE_NAME = {TRUE FALSE}
Default value	FALSE
Range of values	TRUE - enables this feature FALSE - disables this feature

E.53 TGT_RMAN_CHANNELS

TGT_RMAN_CHANNELS specifies the number of RMAN channels to be allocated at the target database server for performing RMAN restore.

Property	Description
Syntax	TGT_RMAN_CHANNELS = <i>number_of_channels</i>
Default value	10

E.54 TGT_SKIP_DATAPATCH

TGT_SKIP_DATAPATCH specifies whether or not Zero Downtime Migration runs the datapatch utility on the target database as part of the post-migration tasks.

Property	Description
Syntax	TGT_SKIP_DATAPATCH = {TRUE FALSE}
Default value	FALSE
Range of values	TRUE - do not allow Zero Downtime Migration to run datapatch FALSE - allow Zero Downtime Migration to run datapatch

Usage Notes

If the target database environment is at a higher patch level than the source database (for example, if the source database is at Jan 2020 PSU/BP and the target database is at April 2020 PSU/BP), then set the TGT_SKIP_DATAPATCH parameter to FALSE to allow Zero Downtime Migration to run the datapatch utility on the target database as part of the post-migration tasks.

Otherwise, set the parameter to TRUE, and if the target database environment is at a higher patch level than the source database, you will need to run the datapatch utility manually after the migration.

E.55 TGT_SSH_RETRY_TIMEOUT

TGT_SSH_RETRY_TIMEOUT specifies the number of minutes during which retries are attempted after SSH connection failures. Retries stop when the timeout value has elapsed.

Property	Description
Syntax	TGT_SSH_RETRY_TIMEOUT = <i>number_of_minutes</i>
Default value	There is no default value.

E.56 TGT_SSH_TUNNEL_PORT

TGT_SSH_TUNNEL_PORT specifies the forwarding port on the source database server where the SSH tunnel to the target database server for SQL*Net connection is set up.

Property	Description
Syntax	TGT_SSH_TUNNEL_PORT = <i>ssh_tunnel_port_number</i>
Default value	There is no default value.

E.57 TGT_ZDLRA_WALLET_LOC

TGT_ZDLRA_WALLET_LOC specifies the path of the Zero Data Loss Recovery Appliance wallet on the target database server.

Property	Description
Syntax	TGT_ZDLRA_WALLET_LOC = <i>target_zdlra_wallet_location</i> The expected format for the location is /u02/app/ oracle/product/12.1.0/dbhome_3/dbs/ zdlra
Default value	There is no default value.

Usage Notes

When using Zero Data Loss Recovery Appliance as the migration backup medium, you must set the following parameters.

SRC_ZDLRA_WALLET_LOC

TGT_ZDLRA_WALLET_LOC

ZDLRA_CRED_ALIAS

E.58 TGT_STBY_NODE

TGT_STBY_NODE specifies the IP address of the target standby.

Note

This parameter is valid only for DR Physical Online migrations.

Property	Description
Syntax	TGT_STBY_NODE= <i>target standby ip address</i>
Default value	There is no default value.

E.59 TGT_STBY_DB_UNIQUE_NAME

TGT_STBY_DB_UNIQUE_NAME specifies the value of target standby database.

Note

This parameter is valid only for DR Physical Online migrations.

Property	Description
Syntax	TGT_STBY_DB_UNIQUE_NAME= <i>value of target standby database DB_UNIQUE_NAME</i>
Default value	There is no default value.

E.60 TGT_STBY_AUTH

TGT_STBY_AUTH specifies the authentication plugin name for connecting to the target standby database.

Note

This parameter is valid only for DR Physical Online migrations.

Property	Description
Syntax	TGT_STBY_AUTH= <i>plugin_name</i>
Default value	There is no default value.
Range of values	zdmauth

E.61 TGT_STBY_SUDO_USER

TGT_STBY_SUDO_USER specifies the user name to login on the target standby database server.

Note

This parameter is valid only for DR Physical Online migrations.

Property	Description
Syntax	TGT_STBY_SUDO_USER= <i>user:target_standby_database_server_login_user_name</i>
Default value	There is no default value.

E.62 TGT_STBY_IDENTITY_FILE

TGT_STBY_IDENTITY_FILE specifies the location of the identity file.

Note

This parameter is valid only for DR Physical Online migrations.

Property	Description
Syntax	TGT_STBY_IDENTITY_FILE= <i>identity_file:ZDM_installed_user_private_key_file_location</i>
Default value	There is no default value.

E.63 TGT_STBY_SUDO_PATH

TGT_STBY_SUDO_PATH specifies the sudo location on the target standby database.

Note

This parameter is valid only for DR Physical Online migrations.

Property	Description
Syntax	TGT_STBY_SUDO_PATH= <i>sudo_location:sudo_location</i>
Default value	There is no default value.

E.64 TGT_STBY_ZDLRA_WALLET_LOC

TGT_STBY_ZDLRA_WALLET_LOC specifies the location of the Zero Data Loss Recovery Appliance wallet on the target standby database.

Note

This parameter is valid only for DR Physical Online migrations.

Property	Description
Syntax	The expected format for the location is: TGT_STBY_ZDLRA_WALLET_LOC= <i>/u02/app/oracle/product/12.1.0/dbhome_3/dbs/zdlra</i>
Default value	There is no default value.

E.65 ZDM_TGT_STBY_CASCADING

Specifies how to keep the target standby database in sync during DR physical online migrations. Set ZDM_TGT_STBY_CASCADING to TRUE (default value) to allow redo log shipping from the target database or set to FALSE to allow the redo log shipping from the source database (primary).

Note

This parameter is valid only for DR Physical Online migrations.

Property	Description
Syntax	ZDM_TGT_STBY_CASCADING={TRUE FALSE}
Default value	TRUE

Property	Description
Required	No, only required for DR physical online migrations.

E.66 ZDM_UPGRADE_TARGET_HOME

Specify the location of `ZDM_UPGRADE_TARGET_HOME` when you want to upgrade your target database after migration to an upgraded version.

Note

Ensure that the `TGT_SKIP_DATAPATCH` should be `FALSE`.
Ensure that the version of `ORACLE_HOME` is an upgraded version.

Note

This parameter is valid only for DR Physical migrations.

Property	Description
Syntax	<code>ZDM_UPGRADE_TARGET_HOME=<home_path></code>
Default value	<code><></code>
Range of values	NA

E.67 ZDM_PRE_UPGRADE_TARGET_HOME

Specify the location of `ZDM_PRE_UPGRADE_TARGET_HOME` when you want to upgrade and plug your non-cdb source database to an upgraded version of the CDB target database. `ZDM_PRE_UPGRADE_TARGET_HOME` accepts `ORACLE_HOME` path in the target instance. The version of `ZDM_PRE_UPGRADE_TARGET_HOME` home should be same as the non-cdb source database.

Note

Value of the `NONCDBTOPDB_CONVERSION` should be `TRUE`. `TGT_SKIP_DATAPATCH` should be `FALSE`.

Property	Description
Syntax	<code>ZDM_PRE_UPGRADE_TARGET_HOME=<home_path></code>
Default value	<code><></code>
Range of values	NA

E.68 ZDLRA_CRED_ALIAS

ZDLRA_CRED_ALIAS specifies the Zero Data Loss Recovery Appliance wallet credential alias.

Property	Description
Syntax	ZDLRA_CRED_ALIAS = <i>zdlra_wallet_alias</i> The expected format for the alias is <i>zdlra scan:listener port/zdlra9:dedicated</i>
Default value	There is no default value.

Usage Notes

When using Zero Data Loss Recovery Appliance as the migration backup medium, you must set the following parameters.

SRC_ZDLRA_WALLET_LOC

TGT_ZDLRA_WALLET_LOC

ZDLRA_CRED_ALIAS

E.69

ZDM_BACKUP_DIFFERENTIAL_SRC_MONITORING_INTERVAL

ZDM_BACKUP_DIFFERENTIAL_SRC_MONITORING_INTERVAL specifies the time interval, in minutes, at which to monitor and report the progress of the ZDM_BACKUP_DIFFERENTIAL_SRC migration job phase.

Property	Description
Syntax	ZDM_BACKUP_DIFFERENTIAL_SRC_MONITORING_INTERVAL = <i>minutes</i>
Default value	10

Usage Notes

The migration job phase monitoring interval parameters, listed below, monitor and report the backup and restore operations progress at the set time interval, specified in minutes. Note that the migration job phase for which the monitoring interval applies is prefixed to `_MONITORING_INTERVAL` in each parameter listed above.

- ZDM_BACKUP_FULL_SRC_MONITORING_INTERVAL
- ZDM_BACKUP_INCREMENTAL_SRC_MONITORING_INTERVAL
- ZDM_BACKUP_DIFFERENTIAL_SRC_MONITORING_INTERVAL
- ZDM_CLONE_TGT_MONITORING_INTERVAL
- ZDM_OSS_RESTORE_TGT_MONITORING_INTERVAL
- ZDM_OSS_RECOVER_TGT_MONITORING_INTERVAL

To disable a monitoring interval parameter, set it to 0 (zero).

Note that for parameters that are interval based, if the results are not in the job logs, check the specific phase logs for the monitoring information.

E.70 ZDM_BACKUP_FULL_SRC_MONITORING_INTERVAL

`ZDM_BACKUP_FULL_SRC_MONITORING_INTERVAL` specifies the time interval, in minutes, at which to monitor and report the progress of the `ZDM_BACKUP_FULL_SRC` migration job phase.

Property	Description
Syntax	<code>ZDM_BACKUP_FULL_SRC_MONITORING_INTERVAL = minutes</code>
Default value	10

Usage Notes

The migration job phase monitoring interval parameters, listed below, monitor and report the backup and restore operations progress at the set time interval, specified in minutes. Note that the migration job phase for which the monitoring interval applies is prefixed to `_MONITORING_INTERVAL` in each parameter listed above.

- `ZDM_BACKUP_FULL_SRC_MONITORING_INTERVAL`
- `ZDM_BACKUP_INCREMENTAL_SRC_MONITORING_INTERVAL`
- `ZDM_BACKUP_DIFFERENTIAL_SRC_MONITORING_INTERVAL`
- `ZDM_CLONE_TGT_MONITORING_INTERVAL`
- `ZDM_OSS_RESTORE_TGT_MONITORING_INTERVAL`
- `ZDM_OSS_RECOVER_TGT_MONITORING_INTERVAL`

To disable a monitoring interval parameter, set it to 0 (zero).

Note that for parameters that are interval based, if the results are not in the job logs, check the specific phase logs for the monitoring information.

E.71 ZDM_BACKUP_INCREMENTAL_SRC_MONITORING_INTERVAL

`ZDM_BACKUP_INCREMENTAL_SRC_MONITORING_INTERVAL` specifies the time interval, in minutes, at which to monitor and report the progress of the `ZDM_BACKUP_INCREMENTAL_SRC` migration job phase.

Property	Description
Syntax	<code>ZDM_BACKUP_INCREMENTAL_SRC_MONITORING_INTERVAL = minutes</code>
Default value	10

Usage Notes

The migration job phase monitoring interval parameters, listed below, monitor and report the backup and restore operations progress at the set time interval, specified in minutes. Note that the migration job phase for which the monitoring interval applies is prefixed to `_MONITORING_INTERVAL` in each parameter listed above.

- `ZDM_BACKUP_FULL_SRC_MONITORING_INTERVAL`
- `ZDM_BACKUP_INCREMENTAL_SRC_MONITORING_INTERVAL`
- `ZDM_BACKUP_DIFFERENTIAL_SRC_MONITORING_INTERVAL`
- `ZDM_CLONE_TGT_MONITORING_INTERVAL`
- `ZDM_OSS_RESTORE_TGT_MONITORING_INTERVAL`
- `ZDM_OSS_RECOVER_TGT_MONITORING_INTERVAL`

To disable a monitoring interval parameter, set it to 0 (zero).

Note that for parameters that are interval based, if the results are not in the job logs, check the specific phase logs for the monitoring information.

E.72 ZDM_BACKUP_RETENTION_WINDOW

`ZDM_BACKUP_RETENTION_WINDOW` specifies the number of days after which backups created by Zero Downtime Migration become obsolete.

Property	Description
Syntax	<code>ZDM_BACKUP_RETENTION_WINDOW = days</code>
Default value	60

E.73 ZDM_BACKUP_TAG

`ZDM_BACKUP_TAG` specifies an RMAN backup tag that can be used to perform a database migration or create a backup.

Use cases:

Set `ZDM_USE_EXISTING_BACKUP=TRUE` to use the specified RMAN backup in `ZDM_BACKUP_TAG` as the full backup, to skip the full backup phase in a migration job. An error is thrown if the backup associated with the specified tag is not valid.

Set `ZDM_USE_EXISTING_BACKUP=FALSE` if you wish to create a backup with the specified tag in `ZDM_BACKUP_TAG`

Property	Description
Syntax	<code>ZDM_BACKUP_TAG=RMAN backup tag</code>
Default value	There is no default value
Range of values	Specify a valid RMAN backup tag to create or use an existing backup in the migration.

E.74 ZDM_CLONE_TGT_MONITORING_INTERVAL

`ZDM_CLONE_TGT_MONITORING_INTERVAL` specifies the time interval, in minutes, at which to monitor and report the progress of the `ZDM_CLONE_TGT` migration job phase.

Property	Description
Syntax	<code>ZDM_CLONE_TGT_MONITORING_INTERVAL = minutes</code>
Default value	10

Usage Notes

The migration job phase monitoring interval parameters, listed below, monitor and report the backup and restore operations progress at the set time interval, specified in minutes. Note that the migration job phase for which the monitoring interval applies is prefixed to `_MONITORING_INTERVAL` in each parameter listed above.

- `ZDM_BACKUP_FULL_SRC_MONITORING_INTERVAL`
- `ZDM_BACKUP_INCREMENTAL_SRC_MONITORING_INTERVAL`
- `ZDM_BACKUP_DIFFERENTIAL_SRC_MONITORING_INTERVAL`
- `ZDM_CLONE_TGT_MONITORING_INTERVAL`
- `ZDM_OSS_RESTORE_TGT_MONITORING_INTERVAL`
- `ZDM_OSS_RECOVER_TGT_MONITORING_INTERVAL`

To disable a monitoring interval parameter, set it to 0 (zero).

Note that for parameters that are interval based, if the results are not in the job logs, check the specific phase logs for the monitoring information.

E.75 ZDM_CURL_LOCATION

`ZDM_CURL_LOCATION` specifies a custom location for the CURL binary on the source.

Property	Description
Syntax	<code>ZDM_CURL_LOCATION = curl_location</code>
Default value	<code>/usr/bin/curl</code>

E.76 ZDM_LOG_OSS_PAR_URL

`ZDM_LOG_OSS_PAR_URL` specifies the pre-authenticated URL to use when uploading logs to Object Storage Service. The logs capture the current migration job phase and the execution status of the phase.

Property	Description
Syntax	<code>ZDM_LOG_OSS_PAR_URL = url</code>
Default value	There is no default value. By default this parameter is disabled.

E.77 ZDM_PDB_CLONE_METHOD

ZDM_PDB_CLONE_METHOD indicates the PDB clone method to be used.

The allowed values for this parameter depend on the MIGRATION_METHOD parameter value:

- Offline PDB clone methods create a point-in-time PDB copy of a source PDB (or non-CDB). Set MIGRATION_METHOD=OFFLINE_PHYSICAL to use any of the offline PDB clone methods. For MIGRATION_METHOD=OFFLINE_PHYSICAL:
 - COLD: Creates a point-in-time PDB copy of a source PDB (or non-CDB). The source database must be in read-only mode. Best for backups or when a precise point-in-time is needed and no source database activity is required.
 - HOT: Used to create an up-to-date copy of a PDB (or non-CDB) without stopping user activity. The source database can remain in read-write mode during the cloning.
- Online PDB clone method creates a PDB copy that can be continuously updated with redo data from the source PDB (or non-CDB). Set MIGRATION_METHOD=ONLINE_PHYSICAL to use the refreshable PDB clone method:

For MIGRATION_METHOD=ONLINE_PHYSICAL:

REFRESHABLE: Creates a PDB copy that can be continuously updates with redo data from the source PDB (or non-CDB).

Provides near-real-time replica of a source PDB that can be automatically updated.

Property	Description
Syntax	ZDM_PDB_CLONE_METHOD = COLD HOT REFRESHABLE
Default value	There is no default value.
Range of values	<ul style="list-style-type: none"> • COLD - point in time PDB copy • HOT - up-to-date PDB copy • REFRESHABLE - PDB copy that can be continuously updated
Required	No

E.78 ZDM_ODA_USERNAME

ZDM_ODA_USERNAME indicates the ODA account username for a Multi User Access (MUA) enabled system.

Note

You must grant the ODA-ADMINISTRATOR and ODA-DB roles to the ODA user account.

Property	Description
Syntax	ZDM_ODA_USERNAME = <ODA account username>
Default value	There is no default value.

Property	Description
Range of values	NA
Required	No, only for Multi User Access (MUA) enabled system.

E.79 ZDM_WALLET_ODA_PASSWORD

ZDM_WALLET_ODA_PASSWORD indicates the absolute path wallet location of the ODA account password for a Multi User Access (MUA) enabled system.

Note

You must grant the ODA-ADMINISTRATOR and ODA-DB roles to the ODA user account.

Property	Description
Syntax	ZDM_WALLET_ODA_PASSWORD = <i><absolute path ODA account password wallet location></i>
Default value	There is no default value.
Range of values	NA
Required	No, only for Multi User Access (MUA) enabled system.

E.80 ZDM_OPC_RETRY_COUNT

ZDM_OPC_RETRY_COUNT specifies the number of retry attempts tat will be made after an initial Object Store connection failure.

Property	Description
Syntax	ZDM_OPC_RETRY_COUNT = <i>number</i>
Default value	0 (zero) The default behavior is to attempt no retries.

E.81 ZDM_OPC_RETRY_WAIT_TIME

ZDM_OPC_RETRY_WAIT_TIME specifies the number of seconds to wait after an Object Store connection failure before attempting to retry the connection.

Property	Description
Syntax	ZDM_OPC_RETRY_WAIT_TIME = <i>seconds</i>
Default value	529 (seconds)

E.82 ZDM_OSS_RECOVER_TGT_MONITORING_INTERVAL

`ZDM_OSS_RECOVER_TGT_MONITORING_INTERVAL` specifies the time interval, in minutes, at which to monitor and report the progress of the `ZDM_OSS_RECOVER_TGT` migration job phase.

Property	Description
Syntax	<code>ZDM_OSS_RECOVER_TGT_MONITORING_INTERVAL</code> <code>= minutes</code>
Default value	10

Usage Notes

The migration job phase monitoring interval parameters, listed below, monitor and report the backup and restore operations progress at the set time interval, specified in minutes. Note that the migration job phase for which the monitoring interval applies is prefixed to `_MONITORING_INTERVAL` in each parameter listed above.

- `ZDM_BACKUP_FULL_SRC_MONITORING_INTERVAL`
- `ZDM_BACKUP_INCREMENTAL_SRC_MONITORING_INTERVAL`
- `ZDM_BACKUP_DIFFERENTIAL_SRC_MONITORING_INTERVAL`
- `ZDM_CLONE_TGT_MONITORING_INTERVAL`
- `ZDM_OSS_RESTORE_TGT_MONITORING_INTERVAL`
- `ZDM_OSS_RECOVER_TGT_MONITORING_INTERVAL`

To disable a monitoring interval parameter, set it to 0 (zero).

Note that for parameters that are interval based, if the results are not in the job logs, check the specific phase logs for the monitoring information.

E.83 ZDM_OSS_RESTORE_TGT_MONITORING_INTERVAL

`ZDM_OSS_RESTORE_TGT_MONITORING_INTERVAL` specifies the time interval, in minutes, at which to monitor and report the progress of the `ZDM_OSS_RESTORE_TGT` migration job phase.

Property	Description
Syntax	<code>ZDM_OSS_RESTORE_TGT_MONITORING_INTERVAL</code> <code>= minutes</code>
Default value	10

Usage Notes

The migration job phase monitoring interval parameters, listed below, monitor and report the backup and restore operations progress at the set time interval, specified in minutes. Note that the migration job phase for which the monitoring interval applies is prefixed to `_MONITORING_INTERVAL` in each parameter listed above.

- `ZDM_BACKUP_FULL_SRC_MONITORING_INTERVAL`
- `ZDM_BACKUP_INCREMENTAL_SRC_MONITORING_INTERVAL`
- `ZDM_BACKUP_DIFFERENTIAL_SRC_MONITORING_INTERVAL`

- ZDM_CLONE_TGT_MONITORING_INTERVAL
- ZDM_OSS_RESTORE_TGT_MONITORING_INTERVAL
- ZDM_OSS_RECOVER_TGT_MONITORING_INTERVAL

To disable a monitoring interval parameter, set it to 0 (zero).

Note that for parameters that are interval based, if the results are not in the job logs, check the specific phase logs for the monitoring information.

E.84 ZDM_RMAN_COMPRESSION_ALGORITHM

ZDM_RMAN_COMPRESSION_ALGORITHM specifies which RMAN compression algorithm to use for backups.

Property	Description
Syntax	ZDM_RMAN_COMPRESSION_ALGORITHM = {BASIC LOW MEDIUM HIGH NONE}
Default value	MEDIUM
Range of values	<p>BASIC - Basic Compression Algorithm.</p> <p>LOW - Least impact on backup throughput and suited for environments where CPU resources are the limiting factor.</p> <p>MEDIUM - Recommended for most environments. Good combination of compression ratios and speed</p> <p>HIGH - Best suited for backups over slower networks where the limiting factor is network speed</p> <p>NONE - Allows you to request uncompressed backups.</p>

E.85 ZDM_RMAN_DIRECT_METHOD

ZDM_RMAN_DIRECT_METHOD specifies the RMAN method (restore from service or active duplicate) to use when DATA_TRANSFER_MEDIUM=DIRECT data transfer method is specified.

You must also set the ZDM_SRC_DB_RESTORE_SERVICE_NAME parameter if you configure a physical migration using direct data transfer (DATA_TRANSFER_MEDIUM=DIRECT).

See [Direct Data Transfer Support](#) for more information about using direct data transfer in a physical migration

Property	Description
Syntax	ZDM_RMAN_DIRECT_METHOD = {RESTORE_FROM_SERVICE ACTIVE_DUPLICATE}
Default value	RESTORE_FROM_SERVICE

Property	Description
Range of values	<ul style="list-style-type: none"> RESTORE_FROM_SERVICE - Instantiates the standby target using RMAN restore from service. Restore from service is supported in Oracle Database 12.1 and later. ACTIVE_DUPLICATE - Instantiates the standby target using RMAN active duplicate. Active duplicate is supported in Oracle Database 11gR2 and later.

E.86 ZDM_RMAN_ENCRYPT_BACKUP

ZDM_RMAN_ENCRYPT_BACKUP specifies if you want to disable the backup encryption for NON_CLOUD.

Property	Description
Syntax	ZDM_RMAN_ENCRYPT_BACKUP = {TRUE FALSE}
Default value	TRUE
Range of values	TRUE - Enable the encryption. FALSE - Disable the encryption.

Note

This parameter is applicable only for NON_CLOUD targets as the encryption is mandatory in cloud. You can disable this parameter only for non-cloud migrations. Backup encryption is mandatory for cloud

E.87 ZDM_RMAN_SECTION_SIZE

ZDM_RMAN_SECTION_SIZE specifies the size for backups or for direct migration restore operation.

Property	Description
Syntax	ZDM_RMAN_SECTION_SIZE = {<integer>{K M G T}} Example, ZDM_RMAN_SECTION_SIZE=4G

Property	Description
Default value	64G
Modifiable on resume	Yes, the value will be used for any new backups.
Required	No

Note

Specify 0 to skip using the section size.

E.88 ZDM_SHARD_ID

ZDM_SHARD_ID is used to ensure that a migration job is running or is being resumed in the correct intended pod.

In a scenario where Zero Downtime Migration is scaled out to service multiple simultaneous migrations, each ZDM server has its own metadata store, which means that the same migration job ID values could be repeated across multiple ZDM servers.

To avoid job ID conflicts which could cause the incorrect job to be resumed on the incorrect ZDM server, the ZDM_SHARD_ID for each job will be configured contain the ZDM host name to which the migration job is being sent. This value will be seeded by E2E during RSP creation.

The value of ZDM_SHARD_ID and the other RSP tokens will be used by ZDM to confirm that the job metadata matches the RSP file values for the source and target database properties to ensure the correct job ID and ZDM server are resumed.

If the value from ZDM_SHARD_ID in the response file is set, and it does not match the current host name, the following exception is thrown:

```
PRGZ-#### : Specified shard ID zdm_host_name_a does not match with current ZDM
host zdm_host_name_b.
```

in which *den01gl* is the value read from the response file, and *den01gl* is the current pod's host name

Property	Description
Syntax	<code>ZDM_SHARD_ID = <i>zdm_host_name</i></code>
Default value	No default value By default, ZDM will not consider the host name before starting or resuming a job.
Range of values	ZDM_SHARD_ID accepts the host name of the pod in which the current job will be run or resumed. It accepts host name or fully qualified domain name. The ZDM_SHARD_ID verification is case insensitive

E.89 ZDM_SKIP_DG_CONFIG_CLEANUP

ZDM_SKIP_DG_CONFIG_CLEANUP indicates whether Zero Downtime Migration should clean up the Oracle Data Guard configuration from the source and target databases at the end of the migration when using online physical migration.

Property	Description
Syntax	ZDM_SKIP_DG_CONFIG_CLEANUP = {TRUE FALSE}
Default value	FALSE By default, ZDM will deconfigure Data Guard parameters configured for migration.
Range of values	TRUE - Do not clean up the Oracle Data Guard configuration. FALSE - Clean up the Oracle Data Guard configuration.

E.90 ZDM_SKIP_TDE_WALLET_MIGRATION

ZDM_SKIP_TDE_WALLET_MIGRATION indicates whether Zero Downtime Migration should skip export and import of TDE wallet from the source and target database.

Property	Description
Syntax	ZDM_SKIP_TDE_WALLET_MIGRATIONP = {TRUE FALSE}
Default value	FALSE By default, ZDM will export TDE wallet from the source and copy and stage the wallet on the target database.
Range of values	TRUE - Do not export the TDE wallet from the source and copy and stage the wallet on the target database. FALSE - Export TDE wallet from the source and copy and stage the wallet on the target database.

E.91 ZDM_SRC_DB_RESTORE_SERVICE_NAME

ZDM_SRC_DB_RESTORE_SERVICE_NAME specifies the fully qualified name of the service on the source database to be used for an online physical migration (MIGRATION_METHOD=ONLINE_PHYSICAL) using direct data transfer (DATA_TRANSFER_MEDIUM=DIRECT).

You must also set the ZDM_RMAN_DIRECT_METHOD parameter if you configure a physical migration using direct data transfer (DATA_TRANSFER_MEDIUM=DIRECT).

See [Direct Data Transfer Support](#) for more information about using direct data transfer in a physical migration

Property	Description
Syntax	<code>ZDM_SRC_DB_RESTORE_SERVICE_NAME = source_database_service</code>
Default value	There is no default value. If not specified, the default database service is used.

E.92 ZDM_SRC_TNS_ADMIN

`ZDM_SRC_TNS_ADMIN` specifies the custom location for `TNS_ADMIN` on the source database server when there is no Oracle Grid Infrastructure. If a Grid Infrastructure exists, then the `TNS_ADMIN` property must be set in the CRS resource attribute environment of the database resource.

Property	Description
Syntax	<code>ZDM_SRC_TNS_ADMIN = tns_admin_location</code>
Default value	There is no default value.

E.93 ZDM_SRC_DB_OKV_HOME

`ZDM_SRC_DB_OKV_HOME` indicates the `OKV_HOME` location in the source database when migrating an OKV wallet.

By default, the source `OKV_HOME` is set to the source `WALLET_ROOT` + `'/okv'`. If you have configured your OKV wallet in a different folder, use this parameter to specify your `OKV_HOME` location.

Property	Description
Syntax	<code>ZDM_SRC_DB_OKV_HOME = your_OKV_HOME_path</code>
Default value	There is no default value.
Range of values	Full path to the your source <code>OKV_HOME</code> location.
Required	No

E.94 ZDM_SRC_PDB_NAME

`ZDM_SRC_PDB_NAME` indicates the name of the source PDB to be cloned from the source CDB.

When the source database is a non-CDB, leave the parameter empty.

Property	Description
Syntax	<code>ZDM_SRC_PDB_NAME = your_SRC_PDB_NAME</code>
Default value	There is no default value.
Range of values	NA
Required	No

E.95 ZDM_TGT_PDB_NAME

ZDM_TGT_PDB_NAME indicates the name of the target PDB to be cloned from the source CDB.

Property	Description
Syntax	<code>ZDM_TGT_PDB_NAME = your_TGT_PDB_NAME</code>
Default value	There is no default value.
Range of values	NA
Required	Yes, when ZDM_PDB_CLONE_METHOD is set.

E.96 ZDM_TGT_DB_OKV_HOME

ZDM_TGT_DB_OKV_HOME indicates the OKV_HOME location in the target database when migrating an OKV wallet.

By default, the target OKV_HOME is set to the target `WALLET_ROOT + '/okv'`. If you have configured your OKV wallet in a different folder, use this parameter to specify your OKV_HOME location.

Property	Description
Syntax	<code>ZDM_TGT_DB_OKV_HOME = your_OKV_HOME_path</code>
Default value	There is no default value.
Range of values	Full path to the your target OKV_HOME location.
Required	No

E.97 ZDM_TGT_DBLINK_NAME

ZDM_TGT_DBLINK_NAME indicates the name of the database link from the target database pointing to the source PDB (or non-CDB).

Zero Downtime Migration automatically creates the database link when it does not exist.

For refreshable PDB using switchover:

- If the source database is a CDB, the database link should point to the root container.
- A second database link at the source database pointing to the target CDB is required. Matching database link name and credentials for both database links is required.
- When an existing database link for the target database is supplied and there is no matching database link for the source database then the credentials are required for ZDM to create the second database link. Database link credentials are provided using the ZDM_TGT_DBLINK_USERNAME and ZDM_TGT_DBLINK_PASSWORD_WALLET parameters.

Property	Description
Syntax	<code>ZDM_TGT_DBLINK_NAME = your_TGT_DBLINK_NAME</code>

Property	Description
Default value	ZDM_DBLINK_<job_id>
Range of values	N/A
Required	No

E.98 ZDM_TGT_DBLINK_USERNAME

ZDM_TGT_DBLINK_USERNAME indicates the name of the database username of the database link from the target database pointing to the source PDB (or non-CDB).

Zero Downtime Migration automatically creates the database username when it does not exist.

For refreshable PDB using switchover, an additional database username for the second database link at the source database pointing to the target CDB is required. Matching credentials and database link name for both database links are required.

Property	Description
Syntax	ZDM_TGT_DBLINK_USERNAME = <i>your_TGT_DBLINK_USERNAME</i>
Default value	ZDM_DBLINK_<job_id>
Range of values	N/A
Required	No

E.99 ZDM_TGT_DBLINK_PASSWORD_WALLET

ZDM_TGT_DBLINK_PASSWORD_WALLET indicates the wallet containing the password of the database username for the database link from the target database pointing to the source database (or non-CDB).

Zero Downtime Migration automatically generates a random password if the wallet is not provided.

For refreshable PDB using switchover, an additional database username for the second database link at the source database pointing to the target CDB is required. Matching credentials and database link name for both database links are required.

Property	Description
Syntax	ZDM_TGT_DBLINK_PASSWORD_WALLET = <i>your_TGT_DBLINK_PASSWORD_WALLET</i>
Default value	<random password generated by ZDM>
Range of values	N/A
Required	No

E.100 ZDM_SRC_DB_OKV_VIRTUAL_WALLET_NAME

ZDM_SRC_DB_OKV_VIRTUAL_WALLET_NAME indicates the OKV virtual wallet name from which the okvutil utility downloads the entire wallet.

If the OKV endpoint is configured to use a default wallet, this parameter is optional and ZDM will download the default OKV wallet to migrate the database.

Property	Description
Syntax	ZDM_SRC_DB_OKV_VIRTUAL_WALLET_NAME = <i>okv_virtual_wallet_name</i>
Default value	There is no default value.
Range of values	A virtual wallet name available for the OKV endpoint. If empty, ZDM uses the default wallet name associated with the OKV endpoint.
Required	No, only required if OKV endpoint is not configured to use a default wallet.

E.101 ZDM_TGT_DB_OKV_VIRTUAL_WALLET_NAME

ZDM_TGT_DB_OKV_VIRTUAL_WALLET_NAME indicates the OKV virtual wallet name where the okvutil utility will upload the wallet obtained from the source database.

If the OKV endpoint is configured to use a default wallet, this parameter is optional and ZDM will upload the default OKV wallet to migrate the database.

Property	Description
Syntax	ZDM_TGT_DB_OKV_VIRTUAL_WALLET_NAME = <i>okv_virtual_wallet_name</i>
Default value	There is no default value.
Range of values	A virtual wallet name available for the OKV endpoint. If empty, ZDM uses the default wallet name associated with the OKV endpoint.
Required	No, only required if OKV endpoint is not configured to use a default wallet.

E.102 ZDM_PDB_REFRESH_INTERVAL

ZDM_PDB_REFRESH_INTERVAL specifies how frequently the target PDB clone updates to reflect data changes from the source PDB (or non-CDB). This parameter is defined in minutes.

Note

The ZDM_PDB_REFRESH_INTERVAL parameter is only applicable for the refreshable PDB clone method.

Property	Description
Syntax	<code>ZDM_PDB_REFRESH_INTERVAL = your_PDB_REFRESH_INTERVAL</code>
Default value	60 (minutes)
Range of values	1 - 2999
Required	No

E.103 ZDM_SWITCHOVER

`ZDM_SWITCHOVER` specifies if the switchover operations will be executed by ZDM during the database migration.

For the refreshable PDB clone method, when `ZDM_SWITCHOVER` is set to `TRUE`, the database roles of both the source PDB and the target PDB are reversed.

Property	Description
Syntax	<code>ZDM_SWITCHOVER = TRUE FALSE</code>
Default value	<code>TRUE</code>
Range of values	<ul style="list-style-type: none"> <code>TRUE</code> - Switchover <code>FALSE</code> - Failover
Required	No

E.104 ZDM_STANDBY_DB_CONNECT_STRING

Specifies the connect string of the standby database when `ZDM_USE_EXISTING_STANDBY` is enabled.

Optional parameter to set when `ZDM_USE_EXISTING_STANDBY` is enabled:

`ZDM_STANDBY_DB_CONNECT_STRING`

See [Using an Existing Standby to Instantiate the Target Database](#).

Specify the connect string either in `EZconnect` format or in long form connect descriptor format as shown:

`EZConnect Format: ZDM_STANDBY_DB_CONNECT_STRING=standby-host.example.com:1521/
standbydb`

Syntax (Long service name):

```
ZDM_STANDBY_DB_CONNECT_STRING=(DESCRIPTION=(ADDRESS_LIST=(ADDRESS=(PROTOCOL=TCP)
(HOST=standby-host.example.com)(PORT=1521)))
(CONNECT_DATA=(SERVICE_NAME=standbydb)))
```

Note

You must configure the `ZDM_STANDBY_DB_CONNECT_STRING` parameter if the Data Guard Broker configuration does not use the `EZconnect` connection string.

Property	Description
Syntax	<code>ZDM_STANDBY_DB_CONNECT_STRING = connect_string</code>
Default value	None
Range of values	Enter the connect string for an existing standby for the source primary database

E.105 ZDM_UPGRADE_OPTIONS

Use ZDM_UPGRADE_OPTIONS in the response file when performing physical migration with upgrade to pass additional, tool-specific upgrade options to the upgrade step. The ZDM_UPGRADE_OPTIONS is an optional parameter.

- ZDM supports migration and upgrade of CDB for Oracle Exadata Database Service on Dedicated Infrastructure and Oracle Exadata Database Service on Cloud@Customer target environment using the dbaascli utility.
- ZDM supports migration and upgrade of CDB for VMDB targets and uses dbcli utility.
- For non-cloud target environments, ZDM uses autoupgrade to perform upgrade of CDB.
- ZDM uses autoupgrade to perform upgrade with non-CDB to PDB conversion.

For example:

ZDM_UPGRADE_OPTIONS for autoupgrade:

```
ZDM_UPGRADE_OPTIONS=run_utlpr=yes;timezone_upg=yes;catctl_options=-n 24 -N
4;remove_underscore_parameters=yes
```

Note

For dbcli and dbaascli this parameter accepts only DBUA upgrade_options parameters.

Here is an example of ZDM_UPGRADE_OPTIONS for dbcli and dbaascli:

```
ZDM_UPGRADE_OPTIONS=-upgrade_parallelism 4;-upgradeTimezone true
```

Property	Description
Syntax	<code>ZDM_UPGRADE_OPTIONS</code> = <code>{<key1=value1>;<key2=value2>; }</code> for autoupgrade <code>ZDM_UPGRADE_OPTIONS = {<key1 value1>;<key2 value2>}</code> for DBUA
Default value	

E.106 ZDM_USE_DG_BROKER

Indicates whether Zero Downtime Migration can use an Oracle Data Guard broker configuration to manage database role switchover.

See [Using Oracle Data Guard Broker Role Switchover](#).

Note that broker configuration is not supported for Oracle Database 11.2.0.4.

Property	Description
Syntax	ZDM_USE_DG_BROKER = {TRUE FALSE}
Default value	FALSE
Range of values	TRUE - Use broker for the migration FALSE - Do not use broker for the migration

E.107 ZDM_USE_EXISTING_BACKUP

ZDM_USE_EXISTING_BACKUP indicates whether Zero Downtime Migration can use an existing RMAN backup to perform a database migration.

If this parameter is set to TRUE, you must also set parameter ZDM_BACKUP_TAG. If no value is provided for ZDM_BACKUP_TAG, and ZDM_USE_EXISTING_BACKUP=TRUE an error is thrown.

Property	Description
Syntax	ZDM_USE_EXISTING_BACKUP = {TRUE FALSE}
Default value	FALSE
Range of values	TRUE - Use an existing RMAN backup for the migration FALSE - Do not use an existing RMAN backup for the migration

E.108 ZDM_USE_EXISTING_STANDBY

Indicates whether Zero Downtime Migration can use an existing standby database to instantiate the standby in the target environment in a physical migration.

Optional parameter to set when ZDM_USE_EXISTING_STANDBY is enabled:

ZDM_STANDBY_DB_CONNECT_STRING

See [Using an Existing Standby to Instantiate the Target Database](#).

Note

This migration option is only available when you are using direct data transfer with RMAN restore from service. Because Oracle Database 11.2 doesn't support RMAN restore from service, it is therefore not supported for migration from an existing standby.

Property	Description
Syntax	ZDM_USE_EXISTING_STANDBY = {TRUE FALSE}
Default value	FALSE
Range of values	TRUE - Use an existing standby for the migration FALSE - Do not use a standby for the migration

E.109 ZDM_USE_EXISTING_UNDO_SIZE

ZDM_USE_EXISTING_UNDO_SIZE specifies whether Zero Downtime Migration should use the existing undo tablespace size when creating a new undo tablespace, if required.

Property	Description
Syntax	ZDM_USE_EXISTING_UNDO_SIZE = {TRUE FALSE}
Default value	TRUE By default, Zero Downtime Migration uses the largest size of the existing undo tablespaces.
Range of values	TRUE - Use the existing undo tablespace size. FALSE - Do not use the existing undo tablespace size.

E.110 ZDM_TGT_UPGRADE_TIMEZONE

ZDM_TGT_UPGRADE_TIMEZONE specifies whether Zero Downtime Migration performs timezone upgrade operation on the target database as part of the post-migration tasks.

Property	Description
Syntax	ZDM_TGT_UPGRADE_TIMEZONE = {TRUE FALSE}
Default value	FALSE
Range of values	TRUE - Specify TRUE if you want to upgrade target database time zone file version to the latest available time zone file version present in target database. FALSE - Specify FALSE if you do not want to upgrade target database time zone file version to the latest available time zone file version present in target database.

Usage Notes

This property is applicable for physical migration where source database time zone version is less than target time zone version. After completion of physical migration, target database timezone version is downgraded to source time zone version.

Enable this property to upgrade time zone version of target database to pre-migration time zone version as part of post- migration job performed in this phase. Also upgrade the values of

TIMESTAMP WITH TIME ZONE data type to the upgraded time zone version, based on the DBMS_DST package.

The following phases are applicable if value of the ZDM_TGT_UPGRADE_TIMEZONE parameter is TRUE:

- TIMEZONE_UPGRADE_PREPARE_TGT
- TIMEZONE_UPGRADE_TGT

Related Topics

- [Upgrading the Time Zone File and Timestamp with Time Zone Data](#)

E.111 ZDM_APPLY_LAG_MONITORING_INTERVAL

ZDM_APPLY_LAG_MONITORING_INTERVAL specifies the lag monitoring interval.

Property	Description
Syntax	ZDM_APPLY_LAG_MONITORING_INTERVAL = {NONE DAILY WEEKLY}
Default value	NONE
Range of values	NONE - No interval is specified. DAILY - Determines next MIDNIGHT and would be +24hrs for next schedule. WEEKLY - Determines next MIDNIGHT and would be +7days for next schedule.

E.112 ZDM_NONCDBTOPDB_PDB_NAME

ZDM_NONCDBTOPDB_PDB_NAME is used to specify the database name if you want to convert a source database from nonCDB to PDB.

Property	Description
Syntax	ZDM_NONCDBTOPDB_PDB_NAME = <DB_NAME>
Default value	ZDM_AUX_<DB_NAME>
Range of values	When migrating non-CDB source to CDB target as a PDB, the PDB name to be used. If empty, ZDM uses ZDM_AUX_<SOURCE_DBNAME> by default.

E.113 SRC_DB_PASSWORDFILE_LOC

SRC_DB_PASSWORDFILE_LOC specifies the location of the password file on the source database server.

If the database user is specified for source database host access and if the database password file is in ASM, then copy it to the sourcenode filesystem path for the specified dbuser to access the Syntax Local File System path. For example, /u02/app/oracle/network/admin/orapw<sid>

Property	Description
Syntax	<code>SRC_DB_PASSWORDFILE_LOC = source_db_passwordfile_location</code>
Default value	There is no default value.
Range of values	Not applicable
Required	No
Modifiable on Resume	Yes

E.114 SRC_DB_TDE_WALLET_LOC

`SRC_DB_TDE_WALLET_LOC` specifies the path of the TDE wallet on the source database server.

This parameter allows multiple TDE wallet locations (separated by ||). You can specify multiple TDE wallet locations when using PDBs in isolated mode. For example,

```
SRC_DB_TDE_WALLET_LOC=/u02/app/oracle/network/admin/tde||/u02/app/oracle/network/
admin/pdb1/tde||/u02/app/oracle/network/admin/pdb2/tde
```

The allowed characters include: a-z, A-Z, 0-9, /, +, ., _ and -.

If `NoSudo DBUSER` auth is specified for source database host access and if the database TDE wallet is in ASM, then copy it to the `sourcenode` filesystem path for the specified `dbuser` to allow access. For example, `/u02/app/oracle/network/admin/tde`.

Note

The TDE wallet paths must be similar to the output of this query: `SQL> SELECT * FROM v$encryption_wallet.`

Property	Description
Syntax	<code>SRC_DB_TDE_WALLET_LOC = source_db_tde_wallet_location</code>
Default value	There is no default value.
Range of values	Not applicable
Required	No
Modifiable on Resume	Yes

E.115 WALLET_SOURCEADMIN

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, which is used to get the source database administrative admin password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_SOURCEADMIN = wallet_path</code>
Default value	There is no default value
Range of value	Full path to the wallet.
Required	No
Modifiable on Resume	No

E.116 WALLET_OSS

Specifies the absolute path location for wallet to be used for OSS.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_OSS = wallet_path</code>
Default value	There is no default value
Range of value	Full path to the wallet.
Required	No
Modifiable on Resume	No

E.117 WALLET_DV

Specifies the absolute path location for wallet to be used for Oracle Database Vault.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_DV = wallet_path</code>
Default value	There is no default value
Range of value	Full path to the wallet.
Required	No
Modifiable on Resume	No

E.118 WALLET_TDEKEYSTORE

Specifies the absolute path location for wallet to be used for TDE keystore.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The WALLET_* parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	WALLET_TDEKEYSTORE = <i>wallet_path</i>
Default value	There is no default value
Range of value	Full path to the wallet.
Required	No
Modifiable on Resume	No

E.119 WALLET_TGTTDEKEYSTORE

Specifies the absolute path location for wallet to be used for the target TDE keystore.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The WALLET_* parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	WALLET_TGTTDEKEYSTORE = <i>wallet_path</i>
Default value	There is no default value
Range of value	Full path to the wallet.
Required	No
Modifiable on Resume	No

E.120 WALLET_BACKUP

Specifies the absolute path location for wallet to be used for backup.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The WALLET_* parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	WALLET_BACKUP = <i>wallet_path</i>

Property	Description
Default value	There is no default value
Range of value	Full path to the wallet.
Required	No
Modifiable on Resume	No

F

Zero Downtime Migration Logical Migration Response File Parameters Reference

Zero Downtime Migration response file parameters supported for logical migrations.

F.1 DATA_TRANSFER_MEDIUM

Specifies how data will be transferred from the source database system to the target database system.

See also [Configuring the Transfer Medium and Specifying Transfer Nodes](#)

Property	Description
Syntax	DATA_TRANSFER_MEDIUM = {OSS NFS DBLINK COPY AMAZON3}
Default value	OSS
Range of values	<p>OSS - Object Storage Service</p> <p>NFS - Network File System</p> <p>DBLINK - Direct transfer of data over a database link.</p> <p>COPY - secure copy (for co-managed and user managed targets)</p> <p>MANUAL_COPY -</p> <p>This option is valid only for no-ssh case which means that you have not specified the -targetnode or the -sourcenode info in the zdmcli migrate command.</p> <p>Specifying this option skips copying the dump files by ZDM. Copy the dumps to the import directory in the target node. Use the -pauseafter method with value ZDM_DATAPUMP_EXPORT_SRC in the zdmcli migrate command so that the migrations pauses post Export and then you can copy the dump files to the target node's import directory. After this, you can resume the migration.</p> <p>ZDM uses the dumps in the import directory and continues with the migration. If you do not use pauseafter, ZDM fails in the IMPORT phase and displays the error that the required dump files are not present in the target import directory.</p> <p>You can then copy the dumps and resume the migration.</p> <p>AMAZON3 - Amazon Simple Storage Service (Amazon S3) bucket (only supported when SOURCEDATABASE_ENVIRONMENT_NAME=AMAZON</p>
Required	Yes
Modifiable on Resume	No

F.2 DATAPUMPSETTINGS_CREATEAUTHTOKEN

Indicates whether to create a new OCI Auth Token.

Note

This parameter is applicable only when the source database is Oracle Autonomous Database on Shared Exadata Infrastructure or Oracle Autonomous Database on Dedicated Exadata Infrastructure.

If you are not using a network database link for Data Pump Import, an OCI Auth Token is created for the specified OCI user to import Data Pump dump files from the Object Storage into an Autonomous Database.

To reuse an existing Auth Token, set this property to `FALSE`.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_CREATEAUTHTOKEN = { TRUE FALSE }</code>
Default value	<code>FALSE</code>
Range of values	<code>TRUE</code> - Creates an OCI Auth Token for the specified OCI user <code>FALSE</code> - Does not create an OCI Auth Token.
Required	No
Modifiable on Resume	Until <code>ZDM_PREPARE_DATAPUMP_TGT</code> phase is COMPLETED.

F.3 DATAPUMPSETTINGS_DATABASELINKDETAILS_NAME

Specifies the name of the database link from the OCI database to the on-premise database.

Zero Downtime Migration creates the database link if the link does not already exist.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

The `DATAPUMPSETTINGS_DATABASELINKDETAILS_*` parameters are optional details for creating a network database link from OCI database to the on-premise database.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATABASELINKDETAILS_NAME = db_link_name</code>

Property	Description
Default value	There is no default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT phase is COMPLETED.

F.4

DATAPUMPSETTINGS_DATABASELINKDETAILS_WALLETBUCKET_BUCKETNAME

Specifies the OCI Object Storage bucket.

The DATAPUMPSETTINGS_DATABASELINKDETAILS_WALLETBUCKET_* parameters are used with Autonomous Database migration targets. These parameters settings specify the OCI Object Storage details used to store the wallet containing the certificate for on-premise database to create a database link from the Autonomous Database to the on-premise database using TLS.

Not required for a TCP connection from Autonomous Database to the on-premise database.

Parameter Relationships

The optional DATAPUMPSETTINGS_* parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_DATABASELINKDETAILS_WALLETBUCKET_BUCKETNAME = <i>Object Storage bucket name</i>
Default value	There is no default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_TGT phase is COMPLETED.

F.5

DATAPUMPSETTINGS_DATABASELINKDETAILS_WALLETBUCKET_NAMESPACENAME

Specifies the Object Storage namespace.

The DATAPUMPSETTINGS_DATABASELINKDETAILS_WALLETBUCKET_* parameters are used with Autonomous Database migration targets. These parameters settings specify the OCI Object Storage details used to store the wallet containing the certificate for on-premise database to create a database link from the Autonomous Database to the on-premise database using TLS.

Not required for a TCP connection from Autonomous Database to the on-premise database.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATABASELINKDETAILS_WALLET_BUCKET_NAMESPACE = Object Storage bucket namespace</code>
Default value	There is no default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_PREPARE_DATAPUMP_TGT</code> phase is COMPLETED.

F.6 DATAPUMPSETTINGS_DATABUCKET_BUCKETNAME

In lieu of a network database link, the OCI Object Storage bucket specified in `DATAPUMPSETTINGS_DATABUCKET_BUCKETNAME` is used to store Data Pump dump files for migrating to an Autonomous Database.

`DATAPUMPSETTINGS_DATABUCKET_BUCKETNAME` is one of the optional settings for logical migrations using Data Pump.

Use with `DATAPUMPSETTINGS_DATABUCKET_NAMESPACENAME`

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATABUCKET_BUCKETNAME = Name of the Object Storage bucket</code>
Default value	There is no default value
Range of values	Enter the storage bucket name
Required	No
Modifiable on Resume	Until <code>ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC</code> phase is COMPLETED.

F.7 DATAPUMPSETTINGS_DATABUCKET_NAMESPACENAME

In lieu of a network database link, the OCI Object Storage bucket specified with `DATAPUMPSETTINGS_DATABUCKET_NAMESPACENAME` is used to store Data Pump dump files for migrating to an Autonomous Database.

`DATAPUMPSETTINGS_DATABUCKET_NAMESPACENAME` is one of the optional settings for logical migrations using Data Pump.

Use with DATAPUMPSETTINGS_DATABUCKET_BUCKETNAME

Parameter Relationships

The optional DATAPUMPSETTINGS_* parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_DATABUCKET_NAMESPACENAME = <i>Object Storage namespace</i>
Default value	There is no default value
Range of values	Enter the storage bucket namespace
Required	No
Modifiable on Resume	Until ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC phase is COMPLETED.

F.8

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_ESTIMATEBYSTATISTICS

Specifies the STATISTICS method for Data Pump dump size estimation.

Zero Downtime Migration estimates the Data Pump dump size using the BLOCKS or STATISTICS methods. You are expected to apply discretion in arriving at the FILESYSTEM space required for the dump path, considering other factors that affect the actual dump size expected. The estimated dump size and actual size varies based on the data compression applied on the data in the database.

- If data is compressed, then it would be the same as that of the reported ESTIMATE
- If data is uncompressed, then Zero Downtime Migration exports with COMPRESSION set as MEDIUM and the resulting dump would be ~50% of estimate
- There is deviation in dump size expected between data having HCC vs. Advanced compression modes

Note that by default, Zero Downtime Migration performs estimation using the BLOCKS method as part of the precheck and as part of the actual migration part of phase ZDM_DATAPUMP_ESTIMATE_SRC.

Parameter Relationships

The optional DATAPUMPSETTINGS_* parameters let you customize Oracle Data Pump Export and Import jobs.

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_* are optional parameters for Data Pump Export and Import. See SET_PARAMETER Procedures for more information.

Property	Description
Syntax	DATAPUMPSETTINGS_DATAPUMPPARAMETERS_ESTIMATEBYSTATISTICS = [TRUE FALSE]
Default value	FALSE

Property	Description
Valid values	TRUE enables this parameter FALSE disables this parameter
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_ESTIMATE_SRC phase is COMPLETED.

F.9

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_TABLEEXISTS ACTION

Specifies the action to be performed when data is loaded into a preexisting table.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

`DATAPUMPSETTINGS_DATAPUMPPARAMETERS_*` are optional parameters for Data Pump Export and Import. See `SET_PARAMETER` Procedures for more information.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_TABLEEXISTS ACTION = [SKIP TRUNCATE REPLACE APPEND]</code>
Default value	SKIP
Range of values	<p>SKIP - the preexisting table is left unchanged.</p> <p>TRUNCATE - rows are removed from a preexisting table before inserting rows from the Import. Note that if TRUNCATE is specified on tables referenced by foreign key constraints, the TRUNCATE will be modified into a REPLACE.</p> <p>REPLACE - preexisting tables are replaced with new definitions. Before creating the new table, the old table is dropped.</p> <p>APPEND - new rows are added to the existing rows in the table</p> <p>See <code>TABLE_EXISTS_ACTION</code> entry in Table 48-25 "Valid Options for the name Parameter in the <code>SET_PARAMETER</code> Procedure" in <code>SET_PARAMETER</code> Procedures</p>
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_IMPORT_TGT phase is COMPLETED.

F.10

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_USERMETADATA

For EXPORT and Network IMPORT, if set to a nonzero value for schema-mode operations, specifies that the metadata to re-create the user's schemas should also be part of the operation.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

`DATAPUMPSETTINGS_DATAPUMPPARAMETER_*` are optional parameters for Data Pump Export and Import. See `SET_PARAMETER` Procedures for more information.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_USERMETADATA = integer</code>
Default value	There is no default value
Valid values	An integer value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_DATAPUMP_EXPORT_SRC</code> is COMPLETED, or until <code>ZDM_DATAPUMP_IMPORT_TGT</code> phase when using <code>DATA_TRANSFER_MEDIUM=DBLINK</code> .

F.11

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_IMPORTPARALLELISMDEGREE

Specifies the maximum number of worker processes that can be used for a Data Pump Import job.

For migration to an Autonomous Database target, Zero Downtime Migration automatically queries its CPU core count and sets this parameter.

Note

While the value is calculated automatically, if you have already set this parameter, then the value is not calculated and ZDM will consider the value that you set.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_* are optional parameters for Data Pump Export and Import. See SET_PARAMETER Procedures for more information.

Property	Description
Syntax	DATAPUMPSETTINGS_DATAPUMPPARAMETERS_IMPORTPARALLELISMDEGREE = <i>integer</i>
Default value	There is no default value
Valid values	An integer value is expected
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_IMPORT_TGT phase is COMPLETED.

F.12

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXPORTPARALLELISMDEGREE

Specifies the maximum number of worker processes that can be used for a Data Pump Import job.

For migration to an Autonomous Database target, Zero Downtime Migration automatically queries its CPU core count and sets this parameter.

Parameter Relationships

The optional DATAPUMPSETTINGS_* parameters let you customize Oracle Data Pump Export and Import jobs.

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_* are optional parameters for Data Pump Export and Import. See SET_PARAMETER Procedures for more information.

Property	Description
Syntax	DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXPORTPARALLELISMDEGREE = <i>integer</i>
Default value	There is no default value
Valid values	An integer value is expected
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_EXPORT_SRC phase is COMPLETED.

F.13

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_DISABLESTATSGATHERING

Enable this parameter to minimize the resource impact of statistics gathering during the Data Pump job execution.

Set the DATAPUMPSETTINGS_DATAPUMPPARAMETERS_DISABLESTATSGATHERING parameter to `TRUE` in the Data Pump job procedure. This helps to minimize the resource impact of statistics gathering during the Data Pump job execution.

Note

This parameter disables the statistics gathering only during the Data Pump import, not during export.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

`DATAPUMPSETTINGS_DATAPUMPPARAMETERS_*` are optional parameters for Data Pump Export and Import. See `SET_PARAMETER` Procedures for more information.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_DISABLESTATSGATHERING = {TRUE FALSE}</code>
Default value	<code>FALSE</code>
Valid values	Following are the supported values: <ul style="list-style-type: none">• <code>TRUE</code>: Disable the Data Pump job statistics gathering• <code>FALSE</code>: Enable the Data Pump job statistics gathering
Required	No
Modifiable on Resume	No

F.14

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_ENCRYPTION

Specifies what should be encrypted in the dump file set.

Note

Oracle Database Standard Edition 2 does not have dump encryption support and set `DATAPUMPSETTINGS_DATAPUMPPARAMETERS_ENCRYPTION=NONE` for migration to proceed with data being exported using Data Pump without encryption.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

`DATAPUMPSETTINGS_DATAPUMPPARAMETERS_*` are optional parameters for Data Pump Export and Import. See `SET_PARAMETER` Procedures for more information.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_ENCRYPTION = <encryptionValue></code>
Default value	ALL
Valid values	Following are the supported values: <ul style="list-style-type: none"> • DATA_ONLY • METADATA_ONLY • ENCRYPTED_COLUMNS_ONLY • ALL • NONE
Required	No
Modifiable on Resume	No

F.15

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXCLUDETYPELIST

Specifies a comma separated list of object types to exclude.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

`DATAPUMPSETTINGS_DATAPUMPPARAMETERS_*` are optional parameters for Data Pump Export and Import. See `SET_PARAMETER` Procedures for more information.

Property	Description
Syntax	DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXCLUDETYPELIST = <i>object_type_list</i>
Default value	There is no default
Valid values	A comma separated list of object types
Required	No
Modifiable on Resume	No

Example

```
DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXCLUDETYPELIST=cluster,dblink,comment
```

F.16

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_FLASHBACKTIME

During export, specify the timestamp to determine a consistent point for reading your data. This parameter sets the FLASHBACK_TIME parameter for Data Pump Export.

Note

The value for DATAPUMPSETTINGS_DATAPUMPPARAMETERS_FLASHBACKTIME can be either SYSTIMESTAMP or a value that can start with TO_TIMESTAMP. Online migration does not support TO_TIMESTAMP; use SYSTIMESTAMP instead.

This parameter is applicable for both offline and online logical migration.

Note

Do not specify this parameter when using Oracle GoldenGate for online migration.

Parameter Relationships

The optional DATAPUMPSETTINGS_* parameters let you customize Oracle Data Pump Export and Import jobs.

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_* are optional parameters for Data Pump Export and Import. See SET_PARAMETER Procedures for more information.

Property	Description
Syntax	DATAPUMPSETTINGS_DATAPUMPPARAMETERS_FLASHBACKTIME = <i>FLASHBACKTIME_string</i> For example: DATAPUMPSETTINGS_DATAPUMPPARAMETERS_FLASHBACKTIME= TO_TIMESTAMP('2025-07-30 17:45:00', 'YYYY-MM-DD HH24:MI:SS')
Default value	There is no default value
Range of values	A string value is expected
Valid values	A comma separated list of object types
Required	No
Modifiable on Resume	No

F.17

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_SKIPCURRENT

Specifies whether actions that were "in progress" on a previous execution of the job are skipped when the job restarts.

This mechanism allows you to skip actions that trigger fatal bugs and cause the premature termination of a job. Multiple actions can be skipped on a restart. The log file identifies which actions are skipped.

The skip is only honored for Import jobs.

If a domain index was being processed, all pieces of the domain index are skipped, even if the error only occurred in a sub-component of the domain index.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

`DATAPUMPSETTINGS_DATAPUMPPARAMETERS_*` are optional parameters for Data Pump Export and Import. See `SET_PARAMETER` Procedures for more information.

Property	Description
Syntax	DATAPUMPSETTINGS_DATAPUMPPARAMETERS_SKIPCURRENT = [TRUE FALSE]
Default value	FALSE
Valid values	TRUE enables this parameter FALSE disables this parameter
Required	No
Modifiable in Resume	Until <code>ZDM_DATAPUMP_IMPORT_TGT</code> phase is COMPLETED.

F.18

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_NOCLUSTER

Specifies whether all Data Pump workers are started on the current instance or on instances usable by the job.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

`DATAPUMPSETTINGS_DATAPUMPPARAMETERS_*` are optional parameters for Data Pump Export and Import. See `SET_PARAMETER` Procedures for more information.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_NOCLUSTER = [TRUE FALSE]</code>
Default value	FALSE
Valid values	TRUE all Data Pump workers are started on the current instance FALSE Data Pump workers are started on instances usable by the job
Required	No
Modifiable on Resume	No

F.19

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_RETAININDEX

Specifies whether to retain the index.

While migrating to the Oracle Autonomous Database on Shared Exadata Infrastructure target database, the `INDEXTYPE` objects are excluded by default. Set the `DATAPUMPSETTINGS_DATAPUMPPARAMETERS_RETAININDEX` parameter to retain the `INDEXTYPE` objects from source to target Oracle Autonomous Database on Shared Exadata Infrastructure database.

Note

This is not applicable for the other supported target databases as `INDEXTYPE` objects are always migrated.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

`DATAPUMPSETTINGS_DATAPUMPPARAMETERS_*` are optional parameters for Data Pump Export and Import. See `SET_PARAMETER` Procedures for more information.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_RETAININDEX = [TRUE FALSE]</code>
Default value	FALSE
Valid values	TRUE retains the index FALSE does not retain the index
Required	No
Modifiable on Resume	Until <code>ZDM_DATAPUMP_EXPORT_SRC</code> phase is COMPLETED, or until <code>ZDM_DATAPUMP_IMPORT_TGT</code> phase when using <code>DATA_TRANSFER_MEDIUM=DBLINK</code> .

F.20

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_PARTITIONOPTION

`DATAPUMPSETTINGS_DATAPUMPPARAMETERS_PARTITIONOPTION` specifies how partitioned tables should be handled during an import operation when the target database type is Oracle Autonomous Data Warehouse.

`DATAPUMPSETTINGS_DATAPUMPPARAMETERS` are optional parameters for Data Pump Export and Import. See `SET_PARAMETER` Procedures for more information.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_PARTITIONOPTION = [DEPARTITION MERGE NONE]</code>
Default value	NONE
Valid values	DEPARTITION, MERGE, NONE

F.21 DATAPUMPSETTINGS_DELETEDUMPSIN OSS

Indicates whether to retain dump files which are uploaded to Object Storage as part of the migration.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_DELETEDUMPSINOS = {TRUE FALSE}
Default value	TRUE
Range of values	TRUE = delete dumps FALSE = retain dumps
Required	No
Modifiable on Resume	Until ZDM_POST_DATAPUMP_TGT phase is COMPLETED.

F.22 DATAPUMPSETTINGS_ENABLETRACE

Allows users to disable the traces for Data Pump.

Set this property to `FALSE` to disable any traces and by default, the property is `TRUE`.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_ENABLETRACE = [TRUE FALSE]
Default value	TRUE
Valid values	<ul style="list-style-type: none"> TRUE FALSE
Required	No
Modifiable on Resume	No

F.23 DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_NAME

Specifies the object name of a directory on server file system of an on-premises database.

In lieu of a network database link, a directory on the server file system of an on-premises database, specified with the `DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_*` properties is used to store Data Pump Export dump files.

Zero Downtime Migration creates this object if it does not already exist

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_NAME = <i>Name</i>
Default value	There is no default value
Range of values	Name of directory object in the database.
Required	No
Modifiable on Resume	Until ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC phase is COMPLETED.

F.24

DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_PATH

Specifies the object path of a directory on server file system of an on-premises database.

In lieu of a network database link, a directory on the server file system of an on-premises database, specified with the `DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_*` properties is used to store Data Pump Export dump files.

Zero Downtime Migration creates this object if it does not already exist

Note

For Oracle Database 19c and later releases, the `UTL_FILE_DIR` initialization parameter is desupported, which means symbolic links for Data Pump directories are not supported.

If you attempt to use an affected feature configured with symbolic links, then you encounter ORA-29283: invalid file operation: path traverses a symlink. Oracle recommends that you instead use directory objects in place of symbolic links.

See *How Does Oracle Data Pump Move Data?* for more information.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_PATH = <i>Path</i>
Default value	There is no default value
Range of values	Absolute path of directory on database server
Required	No
Modifiable on Resume	Until ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC phase is COMPLETED.

F.25 DATAPUMPSETTINGS_EXPORTVERSION

Specifies the Data Pump job export version.

See Oracle Data Pump documentation for Data Pump Export Version.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_EXPORTVERSION = ["COMPATIBLE" , "12" , "LATEST"]</code>
Default value	<code>COMPATIBLE</code> , if the target database is of same or higher version than that of source database, and specific version, if the target database is a lower version than that of source database.
Required	No

F.26 DATAPUMPSETTINGS_FIXINVALIDOBJECTS

Specifies whether invalid objects are recompiled in the database as part of the migration job.

Note

Starting with Oracle Zero Downtime Migration 26 (26.1) release, the `DATAPUMPSETTINGS_FIXINVALIDOBJECTS` parameter is deprecated and will be desupported in a future release. It is replaced by the following parameters:

- `FIXINVALIDS_ENABLED`
- `FIXINVALIDS_BYSCHEMA`
- `FIXINVALIDS_PARALLELCOUNT`
- `FIXINVALIDS_RETRYCOUNT`

Migration can result in invalid schema objects. Typically, invalid objects fix themselves as they are accessed or run. However, Oracle recommends that invalid objects are recompiled in the database as part of the Zero Downtime Migration migration job so that issues with invalid objects, and any required dependencies, are resolved before users encounter these invalid objects.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_FIXINVALIDOBJECTS = {TRUE FALSE}
Default value	FALSE
Range of values	TRUE = fix invalid objects FALSE = do not fix invalid objects
Required	No
Modifiable on Resume	Until ZDM_POST_DATAPUMP_TGT phase is COMPLETED.

F.27 DATAPUMPSETTINGS_IGNOREERROR

Enables you to define and ignore specific sequences of ORA errors (Data Pump error blocks). You can configure multiple error blocks, such as IGNOREERROR-1, IGNOREERROR-2, and so on, to customize error handling during execution.

The DATAPUMPSETTINGS_IGNOREERROR parameter works by matching error strings using regular expressions. Each parameter is configured to match a specific sequence of ORA errors (error block) based on the error, messages generated during execution. Here's how the matching works:

Group multiple error patterns into a single parameter, separated by commas and wildcard character * (preceded by period . for example, you can use ORA-39083.*INDEX.*) for matching.

Example: DATAPUMPSETTINGS_IGNOREERROR-1="ORA-39083.*INDEX.*,ORA-02158,ORA-39082: Object type PACKAGE BODY.*"

The above example matches:

- Error for ORA-39083 containing "INDEX" as error string.
- The exact error ORA-02158 (only ORA-02158 string is matched).
- The error containing string ORA-39082: Object type PACKAGE BODY.

Example 1:

```
ORA-39083: Object type INDEX:"FUSION_SOCIAL"."XCO$TI_01" failed to create
with error:ORA-02158: invalid CREATE INDEX option
ORA-39082: Object type PACKAGE BODY:"FUSION_SOCIAL"."WAGGLE_CODE" created
with compilation warnings
```

Example 2:

```
ORA-29855: error occurred in the execution of ODCIINDEXCREATE routine
ORA-20000: some user-defined error message
ORA-06512: at "CTXSYS.DRUE", line 123ORA-06512: at "CTXSYS.TEXTINDEXMETHODS",
line 456
```

Define each error block in the response file using an IGNOREERROR parameter as follows:

```
DATAPUMPSETTINGS_IGNOREERROR-1="ORA-39083.*INDEX.*,ORA-02158,ORA-39082:
Object type PACKAGE BODY.*"
```

```
DATAPUMPSETTINGS_IGNOREERROR-2="ORA-29855.*ODCIINDEXCREATE.*,ORA-20000,ORA-06512.*CTXSYS.DRUE.*,ORA-06512.*CTXSYS.TEXTINDEXMETHODS.*"
```

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_IGNOREERROR =</code>
Default value	There is no default value
Range of values	Absolute path of directory on database server
Required	No
Modifiable on Resume	Until <code>ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT</code> phase is <code>COMPLETED</code> .

F.28

DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_PATH

Specifies the absolute path of an import directory object.

In lieu of a network database link, a directory on the server file system of OCI database is used to store Data Pump dump files.

Zero Downtime Migration creates this object if it does not already exist.

For Autonomous Database migration targets, the `DATA_PUMP_DIR` object will already exist.

Note

For Oracle Database 19c and later releases, the `UTL_FILE_DIR` initialization parameter is desupported, which means symbolic links for Data Pump directories are not supported.

If you attempt to use an affected feature configured with symbolic links, then you encounter `ORA-29283: invalid file operation: path traverses a symlink`. Oracle recommends that you instead use directory objects in place of symbolic links.

See *How Does Oracle Data Pump Move Data?* for more information.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_PATH =</code> <i>Path of the directory object</i>
Default value	There is no default value
Range of values	Absolute path of directory on database server

Property	Description
Required	No
Modifiable on Resume	Until ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT phase is COMPLETED.

F.29

DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_NAME

Specifies the name of an import directory object.

In lieu of a network database link, a directory on the server file system of OCI database is used to store Data Pump dump files.

Zero Downtime Migration creates this object if it does not already exist.

For Autonomous Database migration targets, the DATA_PUMP_DIR object will already exist.

Parameter Relationships

The optional DATAPUMPSETTINGS_* parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_NAME = <i>Name of the directory object</i>
Default value	There is no default value
Range of values	Name of directory object in database
Required	No
Modifiable on Resume	Until ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT phase is COMPLETED.

F.30 DATAPUMPSETTINGS_JOBMODE

Specifies the Data Pump export mode.

Parameter Relationships

The optional DATAPUMPSETTINGS_* parameters let you customize Oracle Data Pump Export and Import jobs.

Usage

Property	Description
Syntax	DATAPUMPSETTINGS_JOBMODE = <i>jobModeValue</i>
Default value	SCHEMA

Property	Description
Range of values	<p>FULL performs a full database export.</p> <p>SCHEMA (default) lets you specify a set of schemas to export.</p>
	<div> <p>Note</p> <p>Ensure to not use SCHEMA with GOLDENGATESETTINGS_USEMIGRATIONMODE=TRUE. However, you can set the value to FULL for migration mode.</p> </div> <p>TABLE lets you specify a set of tables to export. In this mode, Zero Downtime Migration precreates the target schema before Data Pump import.</p> <p>TABLESPACE lets you specify a set of tablespaces to export. In this mode, Zero Downtime Migration precreates the target schema before Data Pump import.</p> <p>TRANSPORTABLE is not supported by Zero Downtime Migration.</p> <p>See Oracle Data Pump Export Modes for more information.</p>
Required	No
Modifiable on Resume	No

F.31 DATAPUMPSETTINGS_METADATAFILTERS-LIST_ELEMENT_NUMBER

Defines the name, the object type, and the value of the filter for the Data Pump `METADATA_FILTER` property.

To add multiple filters, increment the integer appended to the parameter name, as shown in the examples below.

```
DATAPUMPSETTINGS_METADATAFILTERS-1=name:nameValue1st,
objectType:objectTypeValue1st, value:valueValue1st
DATAPUMPSETTINGS_METADATAFILTERS-2=name:nameValue2nd,
objectType:objectTypeValue2nd, value:valueValue2nd
```

To exclude select `SCHEMA` Objects for `FULL` mode:

```
DATAPUMPSETTINGS_METADATAFILTERS-1=name:NAME_EXPR,value:'NOT IN(' 'SYSMAN'
')',objectType:SCHEMA
```

```
DATAPUMPSETTINGS_METADATAFILTERS-2=name:NAME_EXPR,value:'NOT IN(' 'SH'
')',objectType:SCHEMA
```

Note that the `SCHEMA` name `SYSMAN` is surrounded by two single quotes and not a double quote.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_METADATAFILTERS-LIST_ELEMENT_NUMBER = name:nameValue, objectType:objectTypeValue, value:valueValue</code>
Default value	There is no default value
Range of values	An entry specifying the name, type, and value is expected, as shown in the examples above.
Required	No
Modifiable on Resume	No

F.32 DATAPUMPSETTINGS_METADATAREMAPS-LIST_ELEMENT_NUMBER

Defines remapping to be applied to objects as they are processed.

To add multiple remappings, increment the integer appended to the parameter name, as shown in the examples below.

```
DATAPUMPSETTINGS_METADATAREMAPS-1=type:typeValue1st,
oldValue:oldValueValue1st, newValue:newValueValue1st
DATAPUMPSETTINGS_METADATAREMAPS-2=type:typeValue2nd,
oldValue:oldValueValue2nd, newValue:newValueValue2nd
```

See `METADATA_REMAP` Procedure for more information.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_METADATAREMAPS-LIST_ELEMENT_NUMBER = type:typeValue, oldValue:oldValueValue, newValue:newValueValue</code> See Remaps Provided by the METADATA_REMAP Procedure for more information about the values that can be specified for type.
Default value	There is no default value

Property	Description
Range of values	An entry specifying the new value, old value and type is expected, as shown in the examples above.
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_EXPORT_SRC phase is COMPLETED, or until ZDM_DATAPUMP_IMPORT_TGT phase when using DATA_TRANSFER_MEDIUM=DBLINK

F.33 DATAPUMPSETTINGS_METADATAATTRANSFORMS-LIST_ELEMENT_NUMBER

Defines the name, the object type, and the value for the Data Pump METADATA_TRANSFORM property.

To add multiple filters, increment the integer appended to the parameter name, as shown in the examples below.

```
DATAPUMPSETTINGS_METADATAATTRANSFORMS-1=name:nameValue1st,
objectType:objectTypeValue1st, value:valueValue1st
DATAPUMPSETTINGS_METADATAATTRANSFORMS-2=name:nameValue2nd,
objectType:objectTypeValue2nd, value:valueValue2nd
```

See [METADATA_TRANSFORM](#) for more information.

Parameter Relationships

The optional DATAPUMPSETTINGS_* parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_METADATAATTRANSFORMS-LIST_ELEMENT_NUMBER = name:nameValue, objectType:objectTypeValue, value:valueValue

Note

See [METADATA_TRANSFORM](#) for more information about the values that can be specified for name.

Default value

There is no default value

Range of values

An entry specifying the name, type, and value is expected, as shown in the examples above.

Required

No

Property	Description
Modifiable on Resume	No

Usage Notes

You can set `XMLTYPE_STORAGE_CLAUSE` to 'BINARY XML'.

`DATAPUMPSETTINGS_METADATATRANSFORMS-1=name:XMLTYPE_STORAGE_CLAUSE, value:'BINARY XML'`. With this enhancement all XML types can be converted as part of the migration.

In another example, you can set

`DATAPUMPSETTINGS_METADATATRANSFORMS-2=name:TABLE_COMPRESSION_CLAUSE, value:'NONE'`.

F.34 DATAPUMPSETTINGS_METADATAFIRST

Specifies that Zero Downtime Migration will import METADATA and DATA as separate phases in the migration job work flow. Setting `DATAPUMPSETTINGS_METADATAFIRST` to `TRUE` will import the METADATA before DATA.

Migrating METADATA and DATA as separate phase in the migration job workflow provides these benefits:

- Allows you to quickly identify the migration issues that arise due to lockdown profiles in ADB.
- Allows quick completion of export/import operations of large databases and identify and rectify DDL import errors
- Allows you to intervene in the migration workflow with target custom actions that require the database objects to exist, namely USER Schema or TABLE or other associated OBJECT definitions
- Helps you identify potential import failure points in DDL processing

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Usage

Property	Description
Syntax	<code>DATAPUMPSETTINGS_METADATAFIRST = {TRUE FALSE}</code>
Default value	FALSE
Range of values	TRUE = import METADATA before DATA as a separate migration job workflow phase FALSE = do not import METADATA and DATA in separate phases
Required	No
Modifiable on Resume	Until <code>ZDM_VALIDATE_SRC</code>

F.35 DATAPUMPSETTINGS_MONITORINTERVALMINUTES

Specifies the Data Pump monitor interval in minutes. This setting is optional.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_MONITORINTERVALMINUTES = number</code>
Default value	10
Range of values	An integer value is expected
Required	No
Modifiable on Resume	No

F.36 DATAPUMPSETTINGS_OMITENCRYPTIONCLAUSE

Sets `TRANSFORM=OMIT_ENCRYPTION_CLAUSE`, which directs Data Pump to suppress any encryption clauses associated with objects using encrypted columns.

This parameter is valid for targets on Oracle Database 19c and later releases.

`OMIT_ENCRYPTION_CLAUSE` applies to materialized view, table, and tablespace objects, and enables objects which were using encrypted columns in the source to get created in a target database environment where encryption attributes are not supported.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_OMITENCRYPTIONCLAUSE = [TRUE FALSE]</code>
Default value	TRUE
Valid values	TRUE enables this parameter FALSE disables this parameter
Required	No
Modifiable on Resume	No

F.37 DATAPUMPPARAMETER_<PARAMETER_NAME>

Specifies the Data Pump parameter in the following format:

`DATAPUMPPARAMETER_<PARAMETER_NAME>=<PARAMETER_VALUE>, stage:<STAGE_NAME>`

`<PARAMETER_NAME>` : Oracle Data Pump parameter name to apply.

<PARAMETER_VALUE> : The value for the specified Data Pump parameter. If the value is a string, enclose it in single quotes.

<STAGE_NAME> : Stage in which Data Pump parameter will be applied. Enter one of the allowed values.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPPARAMETER_<PARAMETER_NAME>=<PARAMETER_VALUE>,stage:<STAGE_NAME></code>
Default value	There is no default value
Valid values for <STAGE_NAME>	<code>INIT_EXPORT</code> , <code>INIT_IMPORT</code> , <code>ALL_EXPORT</code> , <code>ALL_IMPORT</code> , <code>RELOAD_EXPORT</code> , <code>RELOAD_IMPORT</code> , <code>ALL</code>
Required	No
Modifiable on Resume	Until <code>ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT</code> phase is <code>COMPLETED</code> .

F.38 DATAPUMPSETTINGS_RETAINDUMPS

Specifies if you want to clean the dumps in OSS or FSS.

If this parameter is set to `TRUE`, then export dumps are not cleaned as part of the post actions in the selected data transfer medium; OSS, NFS, or FSS.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_RETAINDUMPS = [TRUE FALSE]</code>
Default value	<code>FALSE</code> For regular export/import job, the dumps are cleaned up in OSS or FSS.
Valid values	<code>TRUE</code> enables this parameter <code>FALSE</code> disables this parameter
Required	No
Modifiable on Resume	Until <code>ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT</code> phase is <code>COMPLETED</code> .

F.39 DATAPUMPSETTINGS_REUSE_DUMPMPREFIX

(Optional) Specifies the dump prefix of the existing dump files from a previous job.

ZDM can reuse the existing DataPump dump files from the previous ZDM jobs. This is optional and can be done by specifying in this parameter the dump file prefix as `ZDM_<jobID>_DP_EXPORT_<#>_dmp`. ZDM auto detects the dump files in the indicated import directory object path and includes them for import. In this case, ZDM does not include the estimate, export, and transfer phase. If the specified dumps are not present, an error is thrown.

Note

To retain the dumps in the ZDM job, set `DATAPUMPSETTINGS_RETAINDUMPS` to `TRUE`.

Specify the dump's prefix pattern for preexisting dumps that you want to re-import. Provide the prefix as `ZDM_<jobID>_DP_EXPORT_<#>_dmp`.

Note

Setting `REUSE` and `DATAPUMPSETTINGS_METADATAFIRST` to `TRUE` is not currently supported in the Oracle Zero Downtime Migration 21c (21.5) release.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_REUSE_DUMPMPREFIX = ZDM_<jobID>_DP_EXPORT_<#>_dmp</code>
Default value	None
Valid values	NA
Required	No
Modifiable on Resume	No

F.40 DATAPUMPSETTINGS_SECUREFILELOB

Sets `TRANSFORM=LOB_STORAGE:SECUREFILE`, which directs Data Pump to transform basic LOBs into securefile LOBs during the Data Pump import.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_SECUREFILELOB = [TRUE FALSE]
Default value	TRUE
Valid values	TRUE enables this parameter FALSE disables this parameter
Required	No
Modifiable on Resume	No

F.41 DATAPUMPSETTINGS_SCHEMABATCHCOUNT

Specifies the number of schemas to be processed in parallel as batches.

When DATAPUMPSETTINGS_JOBMODE=SCHEMA you can specify the number of schemas to be migrated in parallel. If this count is specified, then Zero Downtime Migration determines the set of schemas included in each batch from the list of user schemas identified from the database.

DATAPUMPSETTINGS_SCHEMABATCHCOUNT is mutually exclusive with the DATAPUMPSETTINGS_SCHEMABATCH parameter. DATAPUMPSETTINGS_METADATAFIRST is not supported along with the DATAPUMPSETTINGS_SCHEMABATCHCOUNT or DATAPUMPSETTINGS_SCHEMABATCH parameters.

Note

Database initialization parameter MAX_DATAPUMP_JOBS_PER_PDB determines the maximum number of concurrent Oracle Data Pump jobs for each PDB.

Property	Description
Syntax	DATAPUMPSETTINGS_SCHEMABATCHCOUNT = <i>integer</i>
Default value	There is no default value
Range of values	An integer equal to or less than database initialization parameter MAX_DATAPUMP_JOBS_PER_PDB
Required	No
Modifiable on Resume	Until ZDM_VALIDATE_SRC phase is COMPLETED

F.42 DATAPUMPSETTINGS_SCHEMABATCH-LIST_ELEMENT_NUMBER

Specifies which schemas are batched together to be migrated in parallel.

When DATAPUMPSETTINGS_JOBMODE=SCHEMA you can specify which schemas are migrated together in parallel as a batch. Increment the -LIST_ELEMENT_NUMBER value to differentiate the batches.

In this example there are two batches, each containing two schemas that are migrated in parallel.

```
DATAPUMPSETTINGS_SCHEMABATCH-1=n1,n2
```

```
DATAPUMPSETTINGS_SCHEMABATCH-2=n3,n4
```

DATAPUMPSETTINGS_SCHEMABATCH is mutually exclusive with the DATAPUMPSETTINGS_SCHEMABATCHCOUNT parameter.

Note

Database initialization parameter MAX_DATAPUMP_JOBS_PER_PDB determines the maximum number of concurrent Oracle Data Pump jobs for each PDB.

Property	Description
Syntax	DATAPUMPSETTINGS_SCHEMABATCH- <i>LIST_ELEMENT_NUMBER</i> = list of schemas
Default value	There is no default value.
Range of values	<i>LIST_ELEMENT_NUMBER</i> must be a unique integer value for each batch specified list of schemas must be a comma-separated list of schemas
Required	No
Modifiable on Resume	Until ZDM_VALIDATE_SRC phase is COMPLETED

F.43 DATAPUMPSETTINGS_SKIPDEFAULTTRANSFORM

Skips default transform parameters.

Set this property to `TRUE` to avoid all internal Zero Downtime Migration transform defaults.

Parameter Relationships

The optional DATAPUMPSETTINGS_* parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_SKIPDEFAULTTRANSFORM = [TRUE FALSE]
Default value	FALSE
Valid values	TRUE enables this parameter FALSE disables this parameter
Required	No
Modifiable on Resume	No

F.44 DATAPUMPSETTINGS_TEXTINDEX_METHOD

Controls the population of TEXT INDEXes during the import process and improves the performance of the import operation.

Set this property to `NOPOPULATE` to not populate the `TEXT_INDEXES` during the Data Pump import.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_TEXTINDEX_METHOD = [NOPOPULATE]</code>
Default value	There is no default value
Valid values	<code>NOPOPULATE</code>
Required	No
Modifiable on Resume	No

F.45 DATAPUMPSETTINGS_TRACELEVEL

Set any trace level for the Data Pump logging using this property.

By default, ZDM adds the tracing level of `1FF0300` (To trace all components). You can enable or disable any tracing by choosing the right tracing level. Refer to [Export/Import Data Pump Parameter TRACE - How to Diagnose Oracle Data Pump](#) doc for the lists all the valid trace levels.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_TRACELEVEL = [1FF0300]</code>
Default value	<code>1FF0300</code>
Valid values	A trace level string which contains only hexadecimal characters
Required	No
Modifiable on Resume	Until <code>ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC</code> phase is <code>COMPLETED</code> .

F.46 DUMPTRANSFERDETAILS_PUBLICREAD

Specifies if the dump files on NFS are readable for others.

Parameter Relationships

This option allows target database user to read the dumps on the shared path when the dump files are allowed to be read by public.

This helps when the user accessing source database server is not allowed to change the group ownership on dumps on the shared path.

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_PUBLICREAD = {TRUE FALSE}</code>
Default value	FALSE
Range of values	TRUE: Dump files on NFS are readable by public. FALSE: Dump files on NFS are not readable by public.
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.47 DUMPTRANSFERDETAILS_PARALLELCOUNT

Specifies the maximum number of Export dump files to transfer to Object Storage or remote node in parallel.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_PARALLELCOUNT = <i>integer</i></code>
Default value	3
Range of values	This parameter accepts integer values
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.48 DUMPTRANSFERDETAILS_RETRYCOUNT

Specifies the number of times to retry upload or transfer of dump failure.

Intermittent network failures observed during the transfer of Data Pump dumps can be mitigated by setting the `DUMPTRANSFERDETAILS_RETRYCOUNT` parameter.

Parameter Relationships

The `DUMPTRANSFERDETAILS` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_RETRYCOUNT = integer</code>
Default value	3
Range of values	This parameter accepts integer values
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.49 DUMPTRANSFERDETAILS_RSYNCAVAILABLE

Specifies that the transfer dump files are using the Linux rsync utility.

Ensure rsync is installed in both source and target servers. Oracle Exadata does not ship with rsync, refer to MOS Doc ID 1556257.1 for details. ZDM defaults to scp command for transfer.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_RSYNCAVAILABLE = {TRUE FALSE}</code>
Default value	FALSE
Range of values	TRUE - transfer dump files are using the Linux rsync utility FALSE - not using rsync
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.50 DUMPTRANSFERDETAILS_S3BUCKET_ACCESSKEY

Specifies the access key of the Amazon Simple Storage Service (Amazon S3) bucket.

When you set `DATA_TRANSFER_MEDIUM=AMAZON3` to migrate an Amazon Web Services RDS Oracle database to Oracle Autonomous AI Database using an S3 bucket, you must also set the `DUMPTRANSFERDETAILS_S3BUCKET_*` parameters.

See [Migrating from Amazon Web Services RDS to Oracle Autonomous AI Database](#) for details.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_S3BUCKET_ACCESSKEY = s3_bucket_access_key</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.51 DUMPTRANSFERDETAILS_S3BUCKET_NAME

Specifies the name of the Amazon Simple Storage Service (Amazon S3) bucket.

When you set `DATA_TRANSFER_MEDIUM=AMAZON3` to migrate an Amazon Web Services RDS Oracle database to Oracle Autonomous AI Database using an S3 bucket, you must also set the `DUMPTRANSFERDETAILS_S3BUCKET_*` parameters.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_S3BUCKET_NAME = s3_bucket_name</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.52 DUMPTRANSFERDETAILS_S3BUCKET_REGION

Specifies the region of the Amazon Simple Storage Service (Amazon S3) bucket.

When you set `DATA_TRANSFER_MEDIUM=AMAZON3` to migrate an Amazon Web Services RDS Oracle database to Oracle Autonomous AI Database using an S3 bucket, you must also set the `DUMPTRANSFERDETAILS_S3BUCKET_*` parameters.

See [Migrating from Amazon Web Services RDS to Oracle Autonomous AI Database](#) for details.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_S3BUCKET_REGION = s3_bucket_region</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.53 DUMPTRANSFERDETAILS_SHAREDSTORAGE_NAME

Specifies the name of the exported filesystem to be specified for mount in Autonomous Database.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_SHAREDSTORAGE_NAME = name</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.54 DUMPTRANSFERDETAILS_SHAREDSTORAGE_HOST

Specifies the hostname to access shared path in the Autonomous Database.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Property	Description
Syntax	DUMPTRANSFERDETAILS_SHAREDSTORAGE_HOST = <i>name</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.55 DUMPTRANSFERDETAILS_SHAREDSTORAGE_PATH

Specifies the exported path to be mounted in the Autonomous Database.

Parameter Relationships

The DUMPTRANSFERDETAILS_* parameters specify details to transfer dumps from the source node to the target node.

Property	Description
Syntax	DUMPTRANSFERDETAILS_SHAREDSTORAGE_PATH = <i>name</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.56

DUMPTRANSFERDETAILS_SHAREDSTORAGE_DETACHFSS POST

Enable this parameter if you want to retain FSS which is attached by the workflow.

If File Storage Service (FSS) is used as DATA_TRANSFER_MEDIUM for migrating to ADB, then ZDM auto-mounts the FSS if it is not already mounted.

However, now ZDM unmounts the attached FSS mounted by ZDM and you have an option to retain the FSS attached in both target and source databases post migration.

Parameter Relationships

The DUMPTRANSFERDETAILS_* parameters specify details to transfer dumps from the source node to the target node.

Property	Description
Syntax	DUMPTRANSFERDETAILS_SHAREDSTORAGE_DETACHFSSPOST {TRUE FALSE}
Default value	TRUE

Property	Description
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.57 DUMPTRANSFERDETAILS_SOURCE_OCIHOME

Specifies the Oracle Cloud OCI-CLI Binary path.

Parameter Relationships

The DUMPTRANSFERDETAILS_SOURCE_* parameters specify details to upload the Dump files from source node Data Pump dump location to Oracle Cloud Object Storage.

The DUMPTRANSFERDETAILS_* parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	DUMPTRANSFERDETAILS_SOURCE_OCIHOME = <i>path</i>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.58 DUMPTRANSFERDETAILS_SOURCE_PARTSIZEMB

Specifies the part size in MB for chunked transfer.

Parameter Relationships

The DUMPTRANSFERDETAILS_SOURCE_* parameters specify details to upload the Dump files from source node Data Pump dump location to Oracle Cloud Object Storage.

The DUMPTRANSFERDETAILS_* parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	DUMPTRANSFERDETAILS_SOURCE_PARTSIZEMB = <i>integer</i>
Default value	128
Range of values	An integer value is expected

Property	Description
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.59

DUMPTRANSFERDETAILS_SOURCE_NOSSHUPLODMETHOD

Specifies the method to use no-ssh upload.

Parameter Relationships

When value of this parameter is HTTPS, then `ociWalletLoc` is required to be a valid path.

For the default method, value of this parameter is NONE. Data is uploaded to OSS securely by using Curl or OCI CLI.

Property	Description
Syntax	DUMPTRANSFERDETAILS_SOURCE_NOSSHUPLODMETHOD = <Specify the method to use no-ssh upload details.>
Default value	NONE
Required	No

F.60 DUMPTRANSFERDETAILS_SOURCE_OCIWALLETLOC

Specifies the directory path of the OCI SSL wallet location on the source database server node.

Parameter Relationships

The DUMPTRANSFERDETAILS_SOURCE_OCIWALLETLOC parameter specifies the OCI wallet location in the respective database servers.

Property	Description
Syntax	DUMPTRANSFERDETAILS_SOURCE_OCIWALLETLOC = < Directory path for OCI SSL wallet location on the source database server node.>
Default value	None
Required	No

F.61

DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_DUMPDIRPATH

Specifies the absolute path of the directory to copy or upload dump files.

The `DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_*` parameters are configured when you use a standalone server as transfer server.

Transfer dump files using Oracle Cloud OCI-CLI or curl, or copy to or from a node other than the database server.

This option can be leveraged for cases where OCI CLI is installed and configured in a specific node per data center and the node has the Data Pump export or import directory path shared with it. This avoids the requirement of installing OCI CLI on the database node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node. Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The `DUMPTRANSFERDETAILS_SOURCE_*` parameters specify details to upload the Dump files from source node Data Pump dump location to Oracle Cloud Object Storage.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_DUMPDIRPATH = path</code>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.62

DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_HOST

Specifies the dump transfer node host name.

The `DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_*` parameters are configured when you use a standalone server as transfer server.

Transfer dump files using Oracle Cloud OCI-CLI or curl, or copy to or from a node other than the database server.

This option can be leveraged for cases where OCI CLI is installed and configured in a specific node per data center and the node has the Data Pump export or import directory path shared with it. This avoids the requirement of installing OCI CLI on the database node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node. Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The `DUMPTRANSFERDETAILS_SOURCE_*` parameters specify details to upload the Dump files from source node Data Pump dump location to Oracle Cloud Object Storage.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_HOST = host_name</code>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.63

DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_SUDOPATH

Specifies the Sudo path on the dump transfer node.

The `DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_*` parameters are configured when you use a standalone server as transfer server.

Transfer dump files using Oracle Cloud OCI-CLI or curl, or copy to or from a node other than the database server.

This option can be leveraged for cases where OCI CLI is installed and configured in a specific node per data center and the node has the Data Pump export or import directory path shared with it. This avoids the requirement of installing OCI CLI on the database node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node. Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The `DUMPTRANSFERDETAILS_SOURCE_*` parameters specify details to upload the Dump files from source node Data Pump dump location to Oracle Cloud Object Storage.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_SUDOPATH = path</code>
Default value	No default value
Range of values	A string value is expected
Required	No

Property	Description
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.64

DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_USER

Specifies the user allowed to execute OCI CLI in the dump transfer node.

The DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_* parameters are configured when you use a standalone server as transfer server.

Transfer dump files using Oracle Cloud OCI-CLI or curl, or copy to or from a node other than the database server.

This option can be leveraged for cases where OCI CLI is installed and configured in a specific node per data center and the node has the Data Pump export or import directory path shared with it. This avoids the requirement of installing OCI CLI on the database node.

Parameter Relationships

The DUMPTRANSFERDETAILS_* parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The DUMPTRANSFERDETAILS_SOURCE_* parameters specify details to upload the Dump files from source node Data Pump dump location to Oracle Cloud Object Storage.

Property	Description
Syntax	DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_USER = <i>user</i>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.65

DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_USERKEY

Specifies the user's authentication key.

The DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_* parameters are configured when you use a standalone server as transfer server.

Transfer dump files using Oracle Cloud OCI-CLI or curl, or copy to or from a node other than the database server.

This option can be leveraged for cases where OCI CLI is installed and configured in a specific node per data center and the node has the Data Pump export or import directory path shared with it. This avoids the requirement of installing OCI CLI on the database node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node. Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The `DUMPTRANSFERDETAILS_SOURCE_*` parameters specify details to upload the Dump files from source node Data Pump dump location to Oracle Cloud Object Storage.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_SOURCE_TRANSFERNODE_USERKEY = user_auth_key</code>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.66 DUMPTRANSFERDETAILS_SOURCE_USEOCICLI

Indicates that transfer dump files use Oracle Cloud Infrastructure command line interface (CLI).

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The `DUMPTRANSFERDETAILS_SOURCE_*` parameters specify details to upload the Dump files from source node Data Pump dump location to Oracle Cloud Object Storage.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_SOURCE_USEOCICLI = {TRUE FALSE}</code>
Default value	FALSE
Range of values	TRUE or FALSE
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.67 DUMPTRANSFERDETAILS_SRCPROXY_HOSTNAME

Specifies the proxy host name to be used on the source database server node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node. Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	DUMPTRANSFERDETAILS_SRCPROXY_HOSTNAME <i>= hostname</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.68 DUMPTRANSFERDETAILS_SRCPROXY_PORT

Specifies the proxy port to be used on the source database server node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node. Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	DUMPTRANSFERDETAILS_SRCPROXY_PORT <i>= port number</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.69 DUMPTRANSFERDETAILS_SRCPROXY_PROTOCOL

Specifies whether HTTP or HTTPS proxy protocol is to be used on the source database server node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node. Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	DUMPTRANSFERDETAILS_SRCPROXY_PROTOCOL = HTTP or HTTPS
Default value	HTTP
Required	No
Modifiable on Resume	Yes

F.70 DUMPTRANSFERDETAILS_TARGET_OCIHOME

Specifies the Oracle Cloud Infrastructure command line interface (CLI) Binary path.

Parameter Relationships

The DUMPTRANSFERDETAILS_* parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The DUMPTRANSFERDETAILS_TARGET_* parameters specify details to download the Dump files to the target node Data Pump dump location from Oracle Cloud Object Storage.

Property	Description
Syntax	DUMPTRANSFERDETAILS_TARGET_OCIHOME = <i>path</i>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.71

DUMPTRANSFERDETAILS_TARGET_NOSSHUPLOADMETHOD

Specifies the method to use no-ssh upload. When HTTPS is used, ociWalletLoc is required to be a valid path.

Parameter Relationships

When value of the parameter is HTTPS, then ociWalletLoc is required to be a valid path. For default method, when value of the parameter is NONE, data is uploaded to OSS securely using Curl or OCI CLI.

Property	Description
Syntax	DUMPTRANSFERDETAILS_TARGET_NOSSHUPLOADETHOD = <Specify the method to use no-ssh upload details.>
Default value	NONE
Required	No

F.72 DUMPTRANSFERDETAILS_TARGET_OCIWALLETLOC

Specifies the directory path of the OCI SSL wallet location on the target database server node.

Parameter Relationships

Specifies the OCI wallet location in the respective database server.

Property	Description
Syntax	DUMPTRANSFERDETAILS_TARGET_OCIWALLETLOC = < Directory path for OCI SSL wallet location on the target database server node.>
Default value	None
Required	No

F.73 DUMPTRANSFERDETAILS_TARGET_PARTSIZEMB

Specifies the part size in MB for chunked transfer.

Parameter Relationships

The DUMPTRANSFERDETAILS_* parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The DUMPTRANSFERDETAILS_TARGET_* parameters specify details to download the Dump files to the target node Data Pump dump location from Oracle Cloud Object Storage.

Property	Description
Syntax	DUMPTRANSFERDETAILS_TARGET_PARTSIZEMB = <i>integer</i>
Default value	128
Range of values	An integer value is expected
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.74

DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_DUMPDIRPATH

Specifies the absolute path of the directory to copy or upload dump files.

The `DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_*` parameters are configured when you use a standalone server as transfer server.

Transfer dump files using the OCI CLI or curl, or copy to or from a node other than the database server.

This option can be leveraged for cases where OCI CLI is installed and configured in a specific node per data center and the node has the Data Pump export or import directory path shared with it. This avoids the requirement of installing OCI CLI on the database node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through Oracle Cloud Infrastructure command line interface (CLI) or Curl.

The `DUMPTRANSFERDETAILS_TARGET_*` parameters specify details to download the Dump files to the target node Data Pump dump location from Oracle Cloud Object Storage.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_DUMPDIRPATH = path</code>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.75

DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_HOST

Specifies the dump transfer node host name.

The `DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_*` parameters are configured when you use a standalone server as transfer server.

Transfer dump files using OCI CLI or curl, or copy to or from a node other than the database server.

This option can be leveraged for cases where OCI CLI is installed and configured in a specific node per data center and the node has the Data Pump export or import directory path shared with it. This avoids the requirement of installing OCI CLI on the database node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through Oracle Cloud Infrastructure command line interface (CLI) or Curl.

The `DUMPTRANSFERDETAILS_TARGET_*` parameters specify details to download the Dump files to the target node Data Pump dump location from Oracle Cloud Object Storage.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_HOST = host_name</code>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.76

DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_SUDOPATH

Specifies the Sudo path on the dump transfer node.

The `DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_*` parameters are configured when you use a standalone server as transfer server.

Transfer dump files using OCI CLI or curl, or copy to or from a node other than the database server.

This option can be leveraged for cases where OCI CLI is installed and configured in a specific node per data center and the node has the Data Pump export or import directory path shared with it. This avoids the requirement of installing OCI CLI on the database node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through Oracle Cloud Infrastructure command line interface (CLI) or Curl.

The `DUMPTRANSFERDETAILS_TARGET_*` parameters specify details to download the Dump files to the target node Data Pump dump location from Oracle Cloud Object Storage.

Property	Description
Syntax	DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_SUDOPATH = <i>path</i>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.77

DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_USER

Specifies the user allowed to execute OCI CLI in the dump transfer node.

The DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_* parameters are configured when you use a standalone server as transfer server.

Transfer dump files using OCI CLI or curl, or copy to or from a node other than the database server.

This option can be leveraged for cases where OCI CLI is installed and configured in a specific node per data center and the node has the Data Pump export or import directory path shared with it. This avoids the requirement of installing OCI CLI on the database node.

Parameter Relationships

The DUMPTRANSFERDETAILS_* parameters specify details to transfer dumps from the source node to the target node. Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through Oracle Cloud Infrastructure command line interface (CLI) or Curl.

The DUMPTRANSFERDETAILS_TARGET_* parameters specify details to download the Dump files to the target node Data Pump dump location from Oracle Cloud Object Storage.

Property	Description
Syntax	DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_USER = <i>user</i>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.78

DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_USERKEY

Specifies the user's authentication key.

The `DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_*` parameters are configured when you use a standalone server as transfer server.

Transfer dump files using OCI CLI or curl, or copy to or from a node other than the database server.

This option can be leveraged for cases where OCI CLI is installed and configured in a specific node per data center and the node has the Data Pump export or import directory path shared with it. This avoids the requirement of installing OCI CLI on the database node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through Oracle Cloud Infrastructure command line interface (CLI) or Curl.

The `DUMPTRANSFERDETAILS_TARGET_*` parameters specify details to download the Dump files to the target node Data Pump dump location from Oracle Cloud Object Storage.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_TARGET_TRANSFERNODE_USERKEY = user_auth_key</code>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.79 DUMPTRANSFERDETAILS_TARGET_USEOCICLI

Indicates that transfer dump files use Oracle Cloud Infrastructure command line interface (CLI).

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The `DUMPTRANSFERDETAILS_TARGET_*` parameters specify details to download the Dump files to the target node Data Pump dump location from Oracle Cloud Object Storage.

Property	Description
Syntax	DUMPTRANSFERDETAILS_TARGET_USEOCICLI = {TRUE FALSE}
Default value	FALSE
Range of values	TRUE or FALSE
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.80

DUMPTRANSFERDETAILS_TRANSFERTARGET_DUMPDIRPATH

Specifies the absolute path of the directory to copy or upload dump files.

Parameter Relationships

The DUMPTRANSFERDETAILS_* parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The DUMPTRANSFERDETAILS_TRANSFERTARGET_* parameters specify details for the target node to copy the Dump files from source node Data Pump dump location or transfer node directory path specified. Default target database host.

Property	Description
Syntax	DUMPTRANSFERDETAILS_TRANSFERTARGET_DUMPDIRPATH = <i>path</i>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until ZDM_TRANSFER_DUMPS_SRC phase is COMPLETED

F.81 DUMPTRANSFERDETAILS_TRANSFERTARGET_HOST

DUMPTRANSFERDETAILS_TRANSFERTARGET_HOST specifies the dump transfer node host name.

Parameter Relationships

The DUMPTRANSFERDETAILS_* parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The `DUMPTRANSFERDETAILS_TRANSFERTARGET_*` parameters specify details for the target node to copy the Dump files from source node Data Pump dump location or transfer node directory path specified. Default target database host.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_TRANSFERTARGET_HOST = <i>host_name</i></code>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.82

DUMPTRANSFERDETAILS_TRANSFERTARGET_SUDOPATH

Specifies the Sudo path on the dump transfer node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The `DUMPTRANSFERDETAILS_TRANSFERTARGET_*` parameters specify details for the target node to copy the Dump files from source node Data Pump dump location or transfer node directory path specified. Default target database host.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_TRANSFERTARGET_SUDO PATH = <i>path</i></code>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.83 DUMPTRANSFERDETAILS_TRANSFERTARGET_USER

Specifies the host user name that has write permission to the indicated dump storage path.

The user specified in `DUMPTRANSFERDETAILS_TRANSFERTARGET_USER` should be allowed to

- Execute OCI CLI in the specified host to download the dumps from the Object Storage bucket if `DATA_TRANSFER_MEDIUM=OSS`
- Copy the dump files from the source node to the target host specified if `DATA_TRANSFER_MEDIUM=COPY`.

See [Configuring the Transfer Medium and Specifying Transfer Nodes](#) for more information about configuring the dump transfer details parameters.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The `DUMPTRANSFERDETAILS_TRANSFERTARGET_*` parameters specify details for the target node to copy the Dump files from source node Data Pump dump location or transfer node directory path specified. Default target database host.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_TRANSFERTARGET_USER = host_username</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.84

DUMPTRANSFERDETAILS_TRANSFERTARGET_USERKEY

Specifies the user's authentication key.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

The `DUMPTRANSFERDETAILS_TRANSFERTARGET_*` parameters specify details for the target node to copy the Dump files from source node Data Pump dump location or transfer node directory path specified. Default target database host.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_TRANSFERTARGET_USER KEY = user_auth_key</code>
Default value	No default value
Range of values	A string value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.85 DUMPTRANSFERDETAILS_TGTPROXY_HOSTNAME

Specifies the proxy host name to be used on the target database server node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node. Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_TGTPROXY_HOSTNAME</code> <code>= hostname</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.86 DUMPTRANSFERDETAILS_TGTPROXY_PORT

Specifies proxy port number to be used on the target database server node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node. Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_TGTPROXY_PORT</code> <code>=port number</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is COMPLETED

F.87 DUMPTRANSFERDETAILS_TGTPROXY_PROTOCOL

Specifies whether HTTP or HTTPS proxy protocol is to be used on the target database server node.

Parameter Relationships

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node. Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	DUMPTRANSFERDETAILS_TGTPROXY_PROTOCOL = HTTP or HTTPS
Default value	HTTP
Required	No
Modifiable on Resume	Yes

F.88 EXCLUDEOBJECTS-LIST_ELEMENT_NUMBER

Specifies database objects to exclude from migration.

To exclude multiple objects, increment the integer appended to the parameter name, as shown in the examples below.

```
EXCLUDEOBJECTS-1=owner:ownerValue1, objectName:objectNameValue1,
objectType:objectTypeValue1
```

```
EXCLUDEOBJECTS-2=owner:ownerValue2, objectName:objectNameValue2,
objectType:objectTypeValue2
```

See [Selecting Objects for Migration](#) for more information about using EXCLUDEOBJECTS.

Property	Description
Syntax	EXCLUDEOBJECTS-LIST_ELEMENT_NUMBER = owner:ownerValue, objectName:objectNameValue, objectType:objectTypeValue
Default value	There is no default value.
Range of values	An entry specifying the owner, object name, and object type is expected, as shown in the examples above.
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_EXPORT_SRC phase is COMPLETED, or until ZDM_DATAPUMP_IMPORT_TGT phase when using DATA_TRANSFER_MEDIUM=DBLINK.

F.89 FIXINVALIDS_ENABLED

Specifies if fixing invalid objects is enabled.

Enabling this feature allows ZDM to attempt to fix the invalids post a successful import. ZDM attempts to fix invalids twice and any invalids found after that are reported as warning for you to review and handle.

Note

Ensure the database user specified to connect to the target database has execute permission on SYS.UTL_RECOMP.

Migration can result in invalid schema objects. Typically, invalid objects fix themselves as they are accessed or run. However, Oracle recommends that invalid objects are recompiled in the database as part of the Zero Downtime Migration migration job so that issues with invalid objects, and any required dependencies, are resolved before users encounter these invalid objects.

Parameter Relationships

The optional `FIXINVALIDS_*` parameters let you customize fixing invalids.

Property	Description
Syntax	<code>FIXINVALIDS_ENABLED = {TRUE FALSE}</code>
Default value	TRUE
Range of values	TRUE = fix invalid objects FALSE = do not fix invalid objects
Required	No
Modifiable on Resume	Until <code>ZDM_POST_DATAPUMP_TGT</code> phase is COMPLETED.

F.90 FIXINVALIDS_BYSCHEMA

Indicates fixing invalids to be performed at schema parallelism.

Parameter Relationships

The optional `FIXINVALIDS_*` parameters let you customize fixing invalids.

Property	Description
Syntax	<code>FIXINVALIDS_BYSCHEMA = {TRUE FALSE}</code>
Default value	TRUE
Range of values	TRUE = fix invalid objects FALSE = do not fix invalid objects
Required	No
Modifiable on Resume	Until <code>ZDM_POST_DATAPUMP_TGT</code> phase is COMPLETED.

F.91 FIXINVALIDS_PARALLELCOUNT

Indicates the minimum number of parallel counts for fixing invalids.

Defines number of recompile threads to run in parallel. Parallel recompilation can use multiple CPUs to reduce the time taken to recompile invalid objects. This uses the `RECOMP_PARALLEL` procedure.

Note

The process of recompiling an invalid object writes a significant amount of data to system tables and is quite I/O intensive. A slow disk system may be a significant bottleneck and limit speedups available from a higher degree of parallelism.

Parameter Relationships

The optional `FIXINVALIDS_*` parameters let you customize fixing invalids.

Property	Description
Syntax	<code>FIXINVALIDS_PARALLELCOUNT = integer</code>
Default value	Null
Range of values	
Required	No
Modifiable on Resume	Until <code>ZDM_POST_DATAPUMP_TGT</code> phase is COMPLETED.

F.92 FIXINVALIDS_RETRYCOUNT

Indicates the minimum number of retry attempts for fixing invalids.

Parameter Relationships

The optional `FIXINVALIDS_*` parameters let you customize fixing invalids.

Property	Description
Syntax	<code>FIXINVALIDS_RETRYCOUNT = integer</code>
Default value	2
Range of values	
Required	No
Modifiable on Resume	Until <code>ZDM_POST_DATAPUMP_TGT</code> phase is COMPLETED.

F.93 GOLDENGATEHUB_ALLOWSELSIGNEDCERTIFICATE

Indicates whether Oracle GoldenGate server's self-signed HTTPS certificate should be accepted to avoid the `sun.security.provider.certpath.SunCertPathBuilderException: unable to find valid certification path to requested target` error, similar to the `curl --insecure` command.

Parameter Relationships

For online logical migration, you must set the `GOLDENGATEHUB_*` parameters to provide Zero Downtime Migration with details about Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATEHUB_ALLOWSELFsignedCERTIFICAT E = {TRUE FALSE}
Default value	FALSE
Range of values	<ul style="list-style-type: none"> TRUE FALSE
Required	No
Modifiable on Resume	Yes

F.94 GOLDENGATEHUB_ADMINUSERNAME

Specifies the Oracle GoldenGate deployment's administrator username.

For an Oracle GoldenGate deployment provisioned using Oracle Cloud Marketplace image, retrieve the `oggadmin` username and password credentials in the `/home/opc/ogg-credentials.json` file on the Oracle Cloud compute instance where Oracle GoldenGate is running. For Oracle GoldenGate deployment running in a docker container, obtain the `oggadmin` username and password credentials as indicated at [Administrative Account Password](#).

Parameter Relationships

For online logical migration, you must set the `GOLDENGATEHUB_*` parameters to provide Zero Downtime Migration with details about Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATEHUB_ADMINUSERNAME = <i>user_name</i>
Default value	There is no default value
Range of values	Oracle GoldenGate hub's administrator user name
Required	No*
	*Required for online logical migration
Modifiable on Resume	Until ZDM_PREPARE_GG_HUB phase is COMPLETED.

F.95 GOLDENGATEHUB_COMPUTEID

Specifies the Oracle Cloud identifier of the VM.

Parameter Relationships

For online logical migration, you must set the `GOLDENGATEHUB_*` parameters to provide Zero Downtime Migration with details about Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATEHUB_COMPUTEID = <i>vm_identifier</i>
Default value	There is no default value
Range of values	Oracle Cloud identifier of the VM

Property	Description
Required	No* *Required for online logical migration
Modifiable on Resume	Until ZDM_PREPARE_GG_HUB phase is COMPLETED.

F.96 GOLDENGATEHUB_SOURCEDEPLOYMENTNAME

Specifies the name of the GoldenGate Microservices deployment to operate on the source database.

Parameter Relationships

For online logical migrations, you must set the GOLDENGATEHUB parameters to provide Zero Downtime Migration with details about Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATEHUB_SOURCEDEPLOYMENTNAME = <i>GG_microservices_deployment_name</i>
Default value	There is no default value
Range of values	Name of the GoldenGate Microservices deployment to operate on the source database
Required	No* *Required for online logical migration
Modifiable on Resume	Until ZDM_PREPARE_GG_HUB phase is COMPLETED.

F.97 GOLDENGATEHUB_TARGETDEPLOYMENTNAME

Specifies the name of the GoldenGate Microservices deployment to operate on the target database.

Parameter Relationships

For online logical migrations, you must set the GOLDENGATEHUB parameters to provide Zero Downtime Migration with details about Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATEHUB_TARGETDEPLOYMENTNAME = <i>GG_microservices_deployment_name</i>
Default value	There is no default value
Range of values	Name of the GoldenGate Microservices deployment to operate on the target database
Required	No* *Required for online logical migration
Modifiable on Resume	Until ZDM_PREPARE_GG_HUB phase is COMPLETED.

F.98 GOLDENGATEHUB_URL

Specifies the Oracle GoldenGate hub's REST endpoint.

For example, `GOLDENGATEHUB_URL=https://<FQDN or IP address of server hosting GoldenGate deployment>`. For more information, see, [Network](#).

Parameter Relationships

For online logical migrations, you must set the `GOLDENGATEHUB` parameters to provide Zero Downtime Migration with details about Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	<code>GOLDENGATEHUB_URL = GG_hub_rest_endpoint</code>
Default value	There is no default value
Range of values	Oracle GoldenGate hub's REST endpoint
Required	No* *Required for online logical migration
Modifiable on Resume	Until <code>ZDM_PREPARE_GG_HUB</code> phase is COMPLETED.

F.99 GOLDENGATESETTINGS_ACCEPTABLELAG

Specifies GoldenGate end-to-end latency lag time

Zero Downtime Migration monitors GoldenGate end-to-end latency until the lag time is lower than the value (in seconds) specified in `GOLDENGATESETTINGS_ACCEPTABLELAG`.

Parameter Relationships

For online logical migrations, you can set the optional `GOLDENGATESETTINGS_*` parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	<code>GOLDENGATESETTINGS_ACCEPTABLELAG = seconds</code>
Default value	30 seconds
Required	No
Required	No
Modifiable on Resume	Until <code>ZDM_MONITOR_GG_LAG</code> phase is COMPLETED.

F.100

GOLDENGATESETTINGS_EXTRACT_PERFORMANCEPROFILE

Tunes Oracle GoldenGate Integrated Capture.

Use this setting to automatically configure relevant parameters to achieve the desired throughput and latency.

Parameter Relationships

The GOLDENGATESETTINGS_EXTRACT_* parameters define settings for the Integrated Extract process.

Only one Extract can be configured.

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATESETTINGS_EXTRACT_PERFORMANCEPROFILE = [HIGH MEDIUM LOW_RES]
Default value	HIGH
Valid values	HIGH, MEDIUM, LOW_RES
Required	No
Modifiable on Resume	Until ZDM_CREATE_GG_EXTRACT_SRC phase is COMPLETED.

F.101

GOLDENGATESETTINGS_EXTRACT_WARNLONGTRANS_CHECKINTERVAL

Specifies the frequency in seconds with which Oracle GoldenGate checks for long-running transactions.

Parameter Relationships

GOLDENGATESETTINGS_EXTRACT_WARNLONGTRANS_* parameters specify a length of time in seconds that a transaction can be open before Extract generates a warning message that the transaction is long-running.

The GOLDENGATESETTINGS_EXTRACT_* parameters define settings for the Integrated Extract process.

Only one Extract can be configured.

For online logical migrations, you can set the optional `GOLDENGATESETTINGS_*` parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	<code>GOLDENGATESETTINGS_EXTRACT_WARNLONGTRANS_CHECKINTERVAL = integer</code>
Default value	There is no default value
Valid values	An integer value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_CREATE_GG_EXTRACT_SRC</code> phase is COMPLETED.

F.102

GOLDENGATESETTINGS_EXTRACT_WARNLONGTRANS_DURATION

Specifies a length of time in seconds that a transaction can be open before the GoldenGate Extract process generates a warning message that the transaction is long-running.

Parameter Relationships

`GOLDENGATESETTINGS_EXTRACT_WARNLONGTRANS_*` parameters specify a length of time in seconds that a transaction can be open before Extract generates a warning message that the transaction is long-running.

The `GOLDENGATESETTINGS_EXTRACT_*` parameters define settings for the Integrated Extract process.

Only one Extract can be configured.

For online logical migrations, you can set the optional `GOLDENGATESETTINGS_*` parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	<code>GOLDENGATESETTINGS_EXTRACT_WARNLONGTRANS_DURATION = integer</code>
Default value	There is no default value
Valid values	An integer value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_CREATE_GG_EXTRACT_SRC</code> phase is COMPLETED.

F.103

GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS

Specifies the objects that will be migrated during target database instantiation (initial load). However, the specified objects will not be captured by Oracle GoldenGate Extract. Instead, the specified objects will be reloaded during switchover when there is no active workload on the source database.

Following are the allowed values and their format:

```
GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS-1=<object details>
```

```
GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS-n=[owner:<ownerValue>,  
objectName:<objectNameValue>, objectType:<objectTypeValue>]
```

Example: Two entries

```
GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS-1=owner:<ownerValue1st>,  
objectName:<objectNameValue1st>, objectType:<objectTypeValue1st>  
GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS-2=owner:<ownerValue2nd>,  
objectName:<objectNameValue2nd>, objectType:<objectTypeValue2nd>
```

Note

You can specify the parameter only when starting a job.

You cannot modify when resuming or modifying a job.

Do not specify the tables already being excluded by Oracle GoldenGate `reload_query_advisor` using this parameter; otherwise an input validation error will occur.

The specified tables are instantiated in the target database during initial load using Data Pump. Subsequently, during switchover, ZDM reloads the tables only if they have been modified in source database after initial load.

You can skip Oracle GoldenGate `reload_query_advisor` by setting the parameter `GOLDENGATESETTINGS_SKIPRELOADQUERYADVISOR` to `TRUE`.

Parameter Relationships

The `GOLDENGATESETTINGS_EXTRACT_*` parameters define settings for the Integrated Extract process. Only one Extract can be configured.

For online logical migrations, you can set the optional `GOLDENGATESETTINGS_*` parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS =
Default value	There is no default value
Required	No
Modifiable on Resume	No

F.104

GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS

Specifies the objects that will be migrated during target database instantiation (initial load). However, the specified objects will not be replicated by Oracle GoldenGate Replicat. Instead, the specified objects will be reloaded during switchover when there is no active workload on source database.

Following are the allowed values and their format:

```
GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS-1=<object details>
```

```
GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS-n=[owner:<ownerValue>,
objectName:<objectNameValue>, objectType:<objectTypeValue>]
```

Example: Two entries

```
GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS-1=owner:<ownerValue1st>,
objectName:<objectNameValue1st>, objectType:<objectTypeValue1st>
```

```
GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS-2=owner:<ownerValue2nd>,
objectName:<objectNameValue2nd>, objectType:<objectTypeValue2nd>
```

Note

You cannot specify the parameter when you start a job.
You can modify the parameter when you resume or modify a job.

You can modify the parameter only to add tables to the exclusion list.

Do not specify the tables already being excluded by Oracle GoldenGate `reload_query_advisor` using this parameter; otherwise an input validation error will occur.

If Replicat is online: ZDM will stop Replicat, update parameters, and restart Replicat.

The `modify job` accepts updated response file containing parameters

`GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS` and/or `GOLDENGATESETTINGS_EXCLUDERELOAD`.

Parameter Relationships

The `GOLDENGATESETTINGS_EXTRACT_*` parameters define settings for the Integrated Extract process. Only one Extract can be configured.

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS =
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_PREPARE_SWITCHOVER_APP phase is COMPLETED.

F.105 GOLDENGATESETTINGS_EXCLUDERELOAD

Specifies the database objects to be excluded from reload during switchover.

By default, tables excluded from Extract or Replicat will be reloaded during switchover only if the tables have been modified in source database since initial load. To override this default behavior, database objects specified in this parameter are excluded from reloading during the switchover regardless of modifications.

Following are the allowed values and their format:

```
GOLDENGATESETTINGS_EXCLUDERELOAD-1=<object
details>GOLDENGATESETTINGS_EXCLUDERELOAD-n=[owner:<ownerValue>,
objectName:<objectNameValue>, objectType:<objectTypeValue>]
```

Example: Two entries

```
GOLDENGATESETTINGS_EXCLUDERELOAD-1=owner:<ownerValue1st>,
objectName:<objectNameValue1st>,
objectType:<objectTypeValue1st>GOLDENGATESETTINGS_EXCLUDERELOAD-2=owner:<ownerValue2nd>,
objectName:<objectNameValue2nd>, objectType:<objectTypeValue2nd>
```

You can specify tables identified by Oracle GoldenGate reload_query_advisor or tables included in lists GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS, GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS.

The modify job accepts updated response file containing parameters

GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS and/or GOLDENGATESETTINGS_EXCLUDERELOAD.

Modify a ZDM job specifying parameter GOLDENGATESETTINGS_EXCLUDERELOAD to indicate tables which should not be reloaded during switchover.

Parameter Relationships

The GOLDENGATESETTINGS_EXTRACT_* parameters define settings for the Integrated Extract process. Only one Extract can be configured.

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATESETTINGS_EXCLUDERELOAD =
Default value	There is no default value

Property	Description
Required	No
Modifiable on Resume	Until ZDM_PREPARE_SWITCHOVER_APP phase is COMPLETED.

F.106

GOLDENGATESETTINGS_SKIPRELOADQUERYADVISOR

Specifies if Oracle GoldenGate reload advisor to identify unsupported tables is skipped.

By default, GOLDENGATESETTINGS_SKIPRELOADQUERYADVISOR is FALSE, so Oracle GoldenGate `reload_query_advisor` is executed for source database to identify highly active tables lacking row uniqueness. The results reported by the `reload_query_advisor` are used to exclude source tables from Oracle GoldenGate Extract. Instead, the reported tables will be reloaded during application switchover downtime.

You can override the default behavior to skip Oracle GoldenGate `reload_query_advisor` and instead specify GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS when starting a job or GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS when resuming or modifying a job.

Parameter Relationships

The GOLDENGATESETTINGS_EXTRACT_* parameters define settings for the Integrated Extract process. Only one Extract can be configured.

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATESETTINGS_EXCLUDERELOAD = TRUE FALSE
Default value	FALSE
Valid values	TRUE FALSE
Required	No
Modifiable on Resume	

F.107 GOLDENGATESETTINGS_EXTRACT_PARALLELISM

Specifies the number of processes supporting the database logmining server.

Parameter Relationships

The GOLDENGATESETTINGS_EXTRACT_* parameters define settings for the Integrated Extract process. Only one Extract can be configured.

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATESETTINGS_EXTRACT_PARALLELISM = <i>integer</i>
Default value	2
Valid values	A positive integer value is expected
Required	No
Modifiable on Resume	Until ZDM_CREATE_GG_EXTRACT_TGT phase is COMPLETED.

Note

Parallelism greater than 1 is not supported for Oracle Database Standard Edition 2.

F.108

GOLDENGATESETTINGS_RELOADUNREPLICATEDOBJECTS

Specifies whether to reload objects that are not supported by Oracle GoldenGate for replication.

Parameter Relationships

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Set this parameter to `TRUE` to reload objects that are not supported by Oracle GoldenGate for replication.

For Online logical migration, ZDM evaluation phase `ZDM_VALIDATE_SRC` queries view `DBA_GOLDENGATE_SUPPORT_MODE` and reports the list of tables with Oracle GoldenGate `support_mode = NONE` or `support_mode = PLSQL` as objects to be excluded for online logical migration.

Set the ZDM parameter `GOLDENGATESETTINGS_RELOADUNREPLICATEDOBJECTS` to:

- automatically exclude tables with Oracle GoldenGate `support_mode = NONE` or `support_mode = PLSQL` for Oracle GoldenGate replication.
- automatically reload tables with Oracle GoldenGate `support_mode = NONE` or `support_mode = PLSQL` in target database using Oracle Data Pump during ZDM phase `ZDM_RELOAD_PARALLEL_EXPORT_IMPORT` during switchover window.

As part of online logical migrations, when value of the `GOLDENGATESETTINGS_RELOADUNREPLICATEDOBJECTS = TRUE`, then the audit trails are also imported during the reload phase `ZDM_RELOAD_PARALLEL_EXPORT_IMPORT`.

When value of the `GOLDENGATESETTINGS_RELOADUNREPLICATEDOBJECTS = TRUE`, then `SOURCEDATABASE_ALLOWTEMPTABLE` is set to `TRUE` by default. If this is unexpected, then you need

to set the value of `SOURCEDATABASE_ALLOWTEMPTABLE` to `FALSE`. However, setting it to `FALSE` can lead to Datapump import performance issue.

For more details, see [Handling Application Switchover in a Logical Migration](#).

Property	Description
Syntax	<code>GOLDENGATESETTINGS_RELOADUNREPLICATEDOBJECTS = TRUE FALSE</code>
Default value	<code>FALSE</code>
Required	No
Modifiable on Resume	Until <code>ZDM_VALIDATE_SRC</code> phase is completed.

F.109

GOLDENGATESETTINGS_REPLICAT_MAPPARALLELISM

Specifies the number of threads used to read GoldenGate trail files.

Starting with Oracle Zero Downtime Migration 21c (21.4) release, this property is deprecated and will be desupported in a future release. For more information, see [GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE](#).

Valid for Parallel Replicat.

Parameter Relationships

The `GOLDENGATESETTINGS_REPLICAT_*` parameters define settings for the Parallel Replicat process.

For online logical migrations, you can set the optional `GOLDENGATESETTINGS_*` parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	<code>GOLDENGATESETTINGS_REPLICAT_MAPPARALLELISM = integer</code>
Default value	4
Valid values	An integer value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_CREATE_GG_REPLICAT_TGT</code> phase is COMPLETED.

F.110

GOLDENGATESETTINGS_REPLICAT_MAXAPPLYPARALLELISM

Defines the range in which the GoldenGate Replicat automatically adjusts its apply parallelism.

Starting with Oracle Zero Downtime Migration 21c (21.4) release, this property is deprecated and will be desupported in a future release. For more information, see GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE.

Valid for Parallel Replicat.

Parameter Relationships

The GOLDENGATESETTINGS_REPLICAT_* parameters define settings for the Parallel Replicat process.

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATESETTINGS_REPLICAT_MAXAPPLYPARALLELISM = <i>integer</i>
Default value	50
Valid values	An integer value is expected
Required	No
Modifiable on Resume	Until ZDM_CREATE_GG_REPLICAT_TGT phase is COMPLETED.

F.111

GOLDENGATESETTINGS_REPLICAT_MINAPPLYPARALLELISM

Defines the range in which the GoldenGate Replicat automatically adjusts its apply parallelism.

Starting with Oracle Zero Downtime Migration 21c (21.4) release, this property is deprecated and will be desupported in a future release. For more information, see GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE.

Valid for Parallel Replicat.

Parameter Relationships

The GOLDENGATESETTINGS_REPLICAT_* parameters define settings for the Parallel Replicat process.

For online logical migrations, you can set the optional `GOLDENGATESETTINGS_*` parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	<code>GOLDENGATESETTINGS_REPLICAT_MINAPPLYPARALLELISM = integer</code>
Default value	4
Valid values	An integer value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_CREATE_GG_REPLICAT_TGT</code> phase is COMPLETED.

F.112

GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE

Tunes GoldenGate Replicat.

Starting with Oracle Zero Downtime Migration 21c (21.4) release, the following properties are deprecated and will be desupported in a future release:

- `GOLDENGATESETTINGS_REPLICAT_MAPPARALLELISM`
- `GOLDENGATESETTINGS_REPLICAT_APPLYPARALLELISM`
- `GOLDENGATESETTINGS_REPLICAT_MAXAPPLYPARALLELISM`
- `GOLDENGATESETTINGS_REPLICAT_MINAPPLYPARALLELISM`

These parameters are replaced by the `GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE` parameter. If you configure the `GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE` parameter, then you do not have to configure these deprecated parameters. However, if you do configure these deprecated parameters, then the `GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE` parameter will not be valid.

Set the performance profile to automatically configure relevant parameters to achieve the desired throughput and latency.

Parameter Relationships

The `GOLDENGATESETTINGS_REPLICAT_*` parameters define settings for simplifying the tuning of GoldenGate Replicat.

For online logical migrations, you can set the optional `GOLDENGATESETTINGS_*` parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	<code>GOLDENGATESETTINGS_REPLICAT_PERFORMANCEPROFILE = HIGH LOW</code>
Default value	HIGH

Property	Description
Valid values	Use HIGH when there is no concurrent workload on target database. Use LOW when there is concurrent workload on target database.
Required	No
Modifiable on Resume	Until ZDM_CREATE_GG_REPLICAT_TGT phase is COMPLETED.

Note

- When **HIGH** is set, Replicat Mappers = 5 and Appliers = 2 * CPU_COUNT
- When **LOW** is set, Replicat Mappers = 4 and Appliers = CPU_COUNT / 2

F.113 GOLDENGATESETTINGS_REPLICATEDDL

Specifies whether to set Oracle GoldenGate Replicat parameter GOLDENGATESETTINGS_REPLICATEDDL.

During the migration period it is recommended to avoid DDL operations. When DDL is replicated, Oracle GoldenGate Replicat serializes data to ensure that there are no locking issues between DML and DDL on the same objects. This can slow down the replication progress.

Parameter Relationships

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATESETTINGS_REPLICATEDDL = TRUE FALSE
Default value	FALSE
Required	No
Modifiable on Resume	Until ZDM_MONITOR_GG_LAG phase is COMPLETED.

F.114 GOLDENGATESETTINGS_RELOADAQOBJECTS

Allows users to specify if AQ objects need to be reloaded post import.

Note

If you intend to reload AQ, then apply the following there is RDBMS patches for source and target databases:

- Apply the patch for bug 34174611 on source database.
- Apply the patch for Bug 34314402 that addresses table_exists_action for AQ tables on target database.

Ensure that you have applied the respective patches as mentioned above for the source and target databases before setting
GOLDENGATESETTINGS_RELOADAQOBJECTS=TRUE.

When GOLDENGATESETTINGS_RELOADAQOBJECTS = TRUE, ZDM attempts to reload the AQ objects as part of the ZDM_RELOAD_PARALLEL_EXPORT_IMPORT phase post the initial import and replication. When GOLDENGATESETTINGS_RELOADAQOBJECTS = FALSE, ZDM assumes that the source database does not contain any AQ objects which should be reloaded.

Parameter Relationships

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATESETTINGS_RELOADAQOBJECTS = TRUE FALSE
Default value	FALSE
Required	No
Modifiable on Resume	Until ZDM_CREATE_GG_REPLICAT_TGT phase is COMPLETED.

F.115 GOLDENGATESETTINGS_REPLICATIONMODE

Allows the users to select INTEGRATED or NONINTEGRATED replication.

Parameter Relationships

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

For more information on INTEGRATED and NONINTEGRATED replication, see [Configuring Oracle GoldenGate Replicat](#).

Property	Description
Syntax	GOLDENGATESETTINGS_REPLICATIONMODE = PARALLEL_INTEGRATED PARALLEL_NON_INTEGRATED
Default value	NON_INTEGRATED
Required	No
Modifiable on Resume	Until ZDM_CREATE_GG_REPLICAT_TGT phase is COMPLETED.

F.116

GOLDENGATESETTINGS_REPLICAT_SPLITTRANSRECS

Specifies that large transactions should be divided into pieces of specified size (records) and applied in parallel.

Valid for Parallel Replicat.

Parameter Relationships

The GOLDENGATESETTINGS_REPLICAT_* parameters define settings for simplifying the tuning of GoldenGate Replicat.

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATESETTINGS_REPLICAT_SPLITTRANSRECS = <i>integer</i>
Default value	100000
Valid values	An integer value is expected.
Required	No
Modifiable on Resume	Until ZDM_CREATE_GG_REPLICAT_TGT phase is COMPLETED.

F.117 GOLDENGATESETTINGS_FEATUREGROUP

Allows the users to select specific feature groups for procedural replication. The feature group name includes ALL_SUPPORTED, AQ, FGA, DBFS, and so on.

See [Oracle Fusion Middleware Reference for Oracle GoldenGate, 18c \(18.1.0\)](#) for more information.

Parameter Relationships

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATESETTINGS_FEATUREGROUP = <feature_group_name>
Default value	ALL_SUPPORTED
Required	No
Modifiable on Resume	Until ZDM_MONITOR_GG_LAG phase is COMPLETED.

F.118

GOLDENGATESETTINGS_ENABLEPROCEDURALREPLICATION

Allows the users to enable procedural replication.

Parameter Relationships

For online logical migrations, you can set the optional GOLDENGATESETTINGS_* parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	GOLDENGATESETTINGS_ENABLEPROCEDURALREPLICATION = TRUE FALSE
Default value	FALSE
Required	No
Modifiable on Resume	Until ZDM_CREATE_GG_REPLICAT_TGT phase is COMPLETED.

F.119

GOLDENGATESETTINGS_ENABLEEVENTBASEDSWITCHOVER

Allows the users to automatically enable event based switchover.

To enable event based switchover, set the value of the parameter as `TRUE`. ZDM creates an event table in source and target databases, and creates event trigger in source database. When you resume or modify a job with `-performswitchover` argument, ZDM inserts a record in the source event table. Once the event is triggered, the REPLICAT stops after processing the transaction indicating switchover readiness. After REPLICAT stops, ZDM proceeds with switchover readiness validation and allows database to be switched over.

If you set the value of the parameter as `TRUE` then ZDM performs the following actions:

1. Creates event table and triggers in the source database under `ggadmin` user.
2. Creates event table in target database under `ggadmin` user.

3. Resumes and modifies new argument `-performswitchover` so that you can indicate when the source database is ready for switchover.
4. Inserts a record in the source event table.
5. Performs readiness validation and allows database to be switched over.
6. Deletes the event table on both the source and target databases in `ZDM_CLEAN_UP`.

Parameter Relationships

For online logical migrations, you can set the optional `GOLDENGATESETTINGS_*` parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	<code>GOLDENGATESETTINGS_ENABLEEVENTBASEDSWITCHOVER = TRUE FALSE</code>
Default value	FALSE
Required	No
Modifiable on Resume	Until <code>ZDM_VALIDATE_SRC</code> phase is COMPLETED.

F.120 GENFIXUP

Displays the path to remedial scripts for failing checks when a migration is run with Cloud Premigration Advisor Tool (CPAT) enabled. Generate the ZDM fixup scripts.

The following values are possible:

- YES: Generate the SQL fixup scripts for checks such as `gg_enabled_replication`, `gg_force_logging`, `gg_supplemental_log_data_min`, `has_libraries`, `has_low_streams_pool_size`, `has_columns_of_rowid_type`, `has_java_objects` and `has_java_source`.
- NO: Does not generate SQL fixup scripts.

Parameter Relationships

Property	Description
Syntax	<code>GENFIXUP = NO YES</code>
Default value	NO
Required	No
Modifiable on Resume	Until <code>ZDM_SETUP_SRC</code> phase is COMPLETED.

F.121 GOLDENGATESETTINGS_USEFLASHBACKQUERY

Specifies whether to set Oracle GoldenGate Extract parameters that allow ID KEY support mode objects to be replicated.

If you set parameter `GOLDENGATESETTINGS_USEFLASHBACKQUERY = TRUE`, Zero Downtime Migration sets the following Oracle GoldenGate Extract parameters that allow ID KEY support mode objects to be replicated.

Parameter Relationships

For online logical migrations, you can set the optional `GOLDENGATESETTINGS_*` parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	<code>GOLDENGATESETTINGS_USEFLASHBACKQUERY = TRUE FALSE</code>
Default value	FALSE
Required	No
Modifiable on Resume	

F.122 GOLDENGATESETTINGS_USEMIGRATIONMODE

Specifies whether to configure Oracle GoldenGate Extract with the `MIGRATION_MODE` option.

If you set parameter `GOLDENGATESETTINGS_USEMIGRATIONMODE = TRUE`, then Extract configured with this option automatically includes all supported tables, includes DDL on supported tables, and excludes unsupported objects such as advanced queuing, text indexes, materialized views, and so on.

Extract is automatically configured with `MIGRATION_MODE` when at least one of the following is true:

- If `GOLDENGATESETTINGS_USEMIGRATIONMODE = TRUE`.
- Oracle source database version is higher than or equal to Oracle Database 19c (19.25) and GoldenGate build is higher than or equal to Release Update 23.6.

Restrictions:

- `MIGRATION_MODE` option is only supported for Data Pump job mode FULL, so `TABLE` and `SCHEMA` options are not allowed.
- `MIGRATION_MODE` only works with per PDB configuration, Extract configured with CDB or multi-PDBs will cause errors.
- The properties `GOLDENGATESETTINGS_USEFLASHBACKQUERY`, `GOLDENGATESETTINGS_ENABLEPROCEDURALREPLICATION` and `GOLDENGATESETTINGS_REPLICATEDDL` cannot be used together with `MIGRATION_MODE`.

Parameter Relationships

For online logical migrations, you can set the optional `GOLDENGATESETTINGS_*` parameters to provide Zero Downtime Migration with details about the Oracle GoldenGate Microservices configuration.

Property	Description
Syntax	<code>GOLDENGATESETTINGS_USEMIGRATIONMODE = TRUE FALSE</code>
Default value	FALSE

Property	Description
Required	No
Modifiable on Resume	Until ZDM_VALIDATE_SRC phase is completed.

F.123 IGNOREEXPORTERRORS

Specifies comma separated list of ORA errors to be ignored for Oracle Data Pump export. For any new error to be ignored, suffix the new error to the list of default errors to be ignored.

Note

Starting with Oracle Zero Downtime Migration 26 (26.1) release, the following parameters are deprecated and will be desupported in a future release:

- IGNOREIMPORTERRORS
- IGNOREEXPORTERRORS

These are replaced by the IGNOREERROR parameter.

Property	Description
Syntax	IGNOREEXPORTERRORS = ORA_error_list
Default value	ORA-31684,ORA-39111,ORA-39082
Range of values	ORA-31684,ORA-39111,ORA-39082
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_EXPORT_SRC phase is COMPLETED.

F.124 IGNOREIMPORTERRORS

Specifies comma separated list of ORA errors to be ignored for Oracle Data Pump import. For any new error to be ignored, suffix the new error to the list of default errors to be ignored.

Note

Starting with Oracle Zero Downtime Migration 26 (26.1) release, the following parameters are deprecated and will be desupported in a future release:

- IGNOREIMPORTERRORS
- IGNOREEXPORTERRORS

These are replaced by the IGNOREERROR parameter.

Property	Description
Syntax	IGNOREIMPORTERRORS = ORA_error_list
Default value	ORA-31684,ORA-39111,ORA-39082

Property	Description
Range of values	ORA-31684,ORA-39111,ORA-39082
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_IMPORT_TGT phase is COMPLETED.

F.125 IGNOREPHASEERRORS-n

Indicates whether non-critical errors for specified phase will be ignored.

ZDM provides the new `IGNOREPHASEERRORS-n` parameter to suppress noncritical failures and for the selected phases without affecting overall job success. Each entry uses the format:

`IGNOREPHASEERRORS-n= name:<PHASE>,value:<TRUE|FALSE>`, where `n` starts at 1 and increments for each phase. Only the allowed phases are supported.

For example,

`IGNOREPHASEERRORS-1= name:ZDM_ADVANCE_SEQUENCES,value:TRUE` indicates that errors in `ZDM_ADVANCE_SEQUENCES` phase are non-critical and can be ignored. ZDM checks the errors in failing phase and if critical reported them as fatal, otherwise only logs them.

Property	Description
Syntax	<code>IGNOREPHASEERRORS-n = name:"<phase name>",value:<></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_IMPORT_TGT phase is COMPLETED.

F.126 IGNOREERROR

Allows you to ignore specific Data Pump errors by specifying error-matching strings as parameter values.

The legacy parameters `IGNOREIMPORTERRORS` and `IGNOREEXPORTERRORS` accept a comma-separated list of specific ORA error codes for example., `ORA-XXXX` and suppress those exact errors during the Data Pump export and import phase. However, these legacy parameters do not support error string matching. `IGNOREERROR` is therefore an enhancement, providing more flexible error matching capabilities. To maintain mutual exclusivity between `IGNOREIMPORTERRORS` or `IGNOREEXPORTERRORS`, and `IGNOREERROR`, a check has been added in the GHCTL layer to give an error if they are used together.

To ignore all export and import errors, you can specify the keyword `ALL` in the `IGNOREERROR` value for example, `DATAPUMPSETTINGS_IGNOREERROR-1=ALL`.

Note

Starting with Oracle Zero Downtime Migration 26 (26.1) release, the following parameters are deprecated and will be desupported in a future release:

- IGNOREIMPORTERRORS
- IGNOREEXPORTERRORS

These are replaced by the IGNOREERROR parameter.

Property	Description
Syntax	IGNOREERROR = name:"<phase name>",value:<>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_IMPORT_TGT phase is COMPLETED.

F.127 INCLUDEOBJECTS-LIST_ELEMENT_NUMBER

Specifies database objects to include for migration.

To include multiple objects, increment the integer appended to the parameter name, as shown in the examples below.

```
INCLUDEOBJECTS-1=owner:ownerValue1, objectName:objectNameValue1,
objectType:objectTypeValue1
```

```
INCLUDEOBJECTS-2=owner:ownerValue2, objectName:objectNameValue2,
objectType:objectTypeValue2
```

See [Selecting Objects for Migration](#) for more information about using INCLUDEOBJECTS.

Property	Description
Syntax	INCLUDEOBJECTS-LIST_ELEMENT_NUMBER = owner:ownerValue, objectName:objectNameValue, objectType:objectTypeValue
Default value	There is no default value
Range of values	An entry specifying the owner, object name, and object type is expected, as shown in the examples above.
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_EXPORT_SRC phase is COMPLETED, or until ZDM_DATAPUMP_IMPORT_TGT phase when using DATA_TRANSFER_MEDIUM=DBLINK.

F.128 MIGRATION_METHOD

In a logical migration, specifies whether the migration is online logical or offline logical

The required `MIGRATION_METHOD` parameter specifies whether the migration is online (Data Pump with Oracle GoldenGate replication) or offline (Data Pump only).

Property	Description
Syntax	<code>MIGRATION_METHOD = { ONLINE_LOGICAL OFFLINE_LOGICAL }</code>
Default value	<code>OFFLINE_LOGICAL</code>
Range of values	<code>ONLINE_LOGICAL</code> migrate the database with Data Pump, with replication using Oracle GoldenGate for minimal downtime <code>OFFLINE_LOGICAL</code> migrate the database with Data Pump, with no replication
Required	Yes
Modifiable on Resume	No

F.129 MIGRATE_APEX

Specify if you want to enable the migration of APEX workspace metadata from the source to the target database.

ZDM migrates APEX workspace metadata if you set this parameter to `TRUE` and if the source and target versions are compatible. The APEX workspace metadata is staged to a staging table in user specified for export and imported in the target database as a post Data Pump import action.

Property	Description
Syntax	<code>MIGRATE_APEX = { TRUE FALSE }</code>
Default value	<code>FALSE</code>
Required	No
Modifiable on Resume	Until <code>ZDM_VALIDATE_SRC</code> phase is <code>COMPLETED</code>

F.130 MIGRATE_AWR

Allows you to migrate the AWR report from the source to the target database.

If you set value of the `MIGRATE_AWR` parameter to `TRUE`, then:

- Three additional phases `ZDM_EXPORT_AWR_SRC`, `ZDM_TRANSFER_AWR_DUMPS_SRC` and `ZDM_IMPORT_AWR_TGT` are included in the workflow to handle the migration of AWR data.
- If you set value of the `MIGRATE_AWR` parameter to `TRUE`, then ZDM will migrate the AWR report from source database to target database.

Property	Description
Syntax	<code>MIGRATE_AWR = { TRUE FALSE }</code>

Property	Description
Default value	FALSE
Required	No
Modifiable on Resume	No

F.131 MIGRATE_STS

Allows you to migrate the STS data from the source to the target database.

If you set value of the `MIGRATE_STS` parameter to `TRUE`, then ZDM migrates the STS data from source database to target database.

Property	Description
Syntax	<code>MIGRATE_STS = {TRUE FALSE}</code>
Default value	FALSE
Required	Yes
Modifiable on Resume	No

F.132 OCIAUTHENTICATIONDETAILS_REGIONID

Specifies the OCI region identifier.

See the Region Identifier column in the table at [Regions and Availability Domains](#).

Parameter Relationships

To call REST APIs, you must configure the `OCIAUTHENTICATIONDETAILS_*` parameters.

Property	Description
Syntax	<code>OCIAUTHENTICATIONDETAILS_REGIONID = <i>region_id</i></code>
Default value	There is no default value
Required	Yes
Modifiable on Resume	Yes

F.133

OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_FINGERPRINT

Specifies the fingerprint of the public API key.

See [Required Keys and OCIDs](#) for more information.

Parameter Relationships

To call REST APIs, you must configure the `OCIAUTHENTICATIONDETAILS_*` parameters.

Property	Description
Syntax	OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_FINGERPRINT = <i>fingerprint</i>
Default value	There is no default value
Required	Yes
Modifiable on Resume	Yes

F.134

OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_PRIVATEKEYFILE

Specifies the absolute path of API private key file.

See [Required Keys and OCIDs](#) for more information.

Parameter Relationships

To call REST APIs, you must configure the OCIAUTHENTICATIONDETAILS_* parameters.

Property	Description
Syntax	OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_PRIVATEKEYFILE = <i>path</i>
Default value	There is no default value
Required	Yes
Modifiable on Resume	Yes

F.135

OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_TENANTID

Specifies the OCID of the OCI tenancy.

You can find the tenant OCID on OCI at Governance and Administration, Administration, Tenancy Details. The tenancy OCID is shown under Tenancy Information.

Example:

ocid1.tenancy.oc1..aaaaaaaaba3pv6wkcr4jqae5f44n2b2m2yt2j6rx32uzr4h25vqstifsfdsq

See [Managing the Tenancy](#) and [Required Keys and OCIDs](#) for more information.

Parameter Relationships

To call OCI REST APIs, you must configure the OCIAUTHENTICATIONDETAILS_* parameters.

Property	Description
Syntax	OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_TENANTID = <i>ocid_string</i>

Property	Description
Default value	There is no default value
Valid values	A string value is expected
Required	Yes
Modifiable on Resume	Yes

F.136

OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_USERID

Specifies the OCID of the IAM user.

You can find the IAM OCID on OCI at Console, Profile, User Settings.

See [Managing Users](#) and [Required Keys and OCIDs](#) for more information.

Parameter Relationships

To call OCI REST APIs, you must configure the `OCIAUTHENTICATIONDETAILS_*` parameters.

Property	Description
Syntax	<code>OCIAUTHENTICATIONDETAILS_USERPRINCIPAL_USERID = <i>userid</i></code>
Default value	There is no default value
Required	Yes
Modifiable on Resume	Yes

F.137 OCIPROXY_HOSTNAME

Specifies the HTTP proxy hostname required for OCI REST endpoint access from ZDM host.

Parameter Relationships

The `OCIPROXY_*` parameters specify details about the proxy for connecting to OCI REST endpoints.

Property	Description
Syntax	<code>OCIPROXY_HOSTNAME = <i>hostname</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.138 OCIPROXY_PORT

Specifies the HTTP proxy port required for OCI REST endpoint access from ZDM host.

Parameter Relationships

The `OCIPROXY_*` parameters specify details about the proxy for connecting to OCI REST endpoints.

Property	Description
Syntax	<code>OCIPROXY_PORT = port number</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.139 OCIPROXY_PROTOCOL

Specifies the HTTP proxy protocol required for OCI REST endpoint access from ZDM host.

Parameter Relationships

The `OCIPROXY_*` parameters specify details about the proxy for connecting to OCI REST endpoints.

Property	Description
Syntax	<code>OCIPROXY_PROTOCOL = HTTP or HTTPS</code>
Default value	None
Required	Yes
Modifiable on Resume	Yes

F.140 OCISDKCONFIG_REGISTERREGIONDETAILS_REALM_KEY

Specify the `REALM_KEY` properties if you will register a new OCI realm required by `REGION` properties.

Refer to Realm Key in the table available at [About Regions and Availability Domains](#).

Note

ZDM is bundled with a list of the known OCI regions and any region that gets added after the release of ZDM may not get recognized and the ZDM job may report an error on an unidentified OCI region. If the given OCI region is not recognized by ZDM, specify the OCI region details in `OCISDKCONFIG_REGISTERREGIONDETAILS*` for a database in the given region.

Parameter Relationships

The OCISDKCONFIG_* parameters specify OCI SDK configurations.

Property	Description
Syntax	OCISDKCONFIG_REGISTERREGIONDETAILS_REALM_KEY =
Default value	There is no default value
Required	No
Modifiable on Resume	Can be modified in any phase, no restrictions.

F.141

OCISDKCONFIG_REGISTERREGIONDETAILS_REALM_DOMAINCOMPONENT

Specify the second level domain of the realm. Specify the REALM_DOMAINCOMPONENT properties if you will register a new OCI realm required by REGION properties.

Note

ZDM is bundled with a list of the known OCI regions and any region that gets added after the release of ZDM may not get recognized and the ZDM job may report an error on an unidentified OCI region. If the given OCI region is not recognized by ZDM, specify the OCI region details in OCISDKCONFIG_REGISTERREGIONDETAILS* for a database in the given region.

Parameter Relationships

The OCISDKCONFIG_* parameters specify OCI SDK configurations.

Property	Description
Syntax	OCISDKCONFIG_REGISTERREGIONDETAILS_REALM_DOMAINCOMPONENT =
Default value	There is no default value
Required	No
Modifiable on Resume	Can be modified in any phase, no restrictions.

F.142

OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_ID

Specify the REGISTERREGIONDETAILS_* properties when working with a new OCI region.

Refer to Region Identifier in the table available at [About Regions and Availability Domains](#).

Note

ZDM is bundled with a list of the known OCI regions and any region that gets added after the release of ZDM may not get recognized and the ZDM job may report an error on an unidentified OCI region. If the given OCI region is not recognized by ZDM, specify the OCI region details in `OCISDKCONFIG_REGISTERREGIONDETAILS*` for a database in the given region.

Parameter Relationships

The `OCISDKCONFIG_*` parameters specify OCI SDK configurations.

Property	Description
Syntax	<code>OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_ID =</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Can be modified in any phase, no restrictions.

F.143

OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_KEY

Specify the `REGISTERREGIONDETAILS_*` properties when working with a new OCI region.

Refer to Region Key in the table available at [About Regions and Availability Domains](#).

Note

ZDM is bundled with a list of the known OCI regions and any region that gets added after the release of ZDM may not get recognized and the ZDM job may report an error on an unidentified OCI region. If the given OCI region is not recognized by ZDM, specify the OCI region details in `OCISDKCONFIG_REGISTERREGIONDETAILS*` for a database in the given region.

Parameter Relationships

The `OCISDKCONFIG_*` parameters specify OCI SDK configurations.

Property	Description
Syntax	<code>OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_KEY =</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Can be modified in any phase, no restrictions.

F.144

OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_REALMKEY

Specify the `REGISTERREGIONDETAILS_*` properties when working with a new OCI region.

Refer to Realm Key in the table available at [About Regions and Availability Domains](#).

Note

ZDM is bundled with a list of the known OCI regions and any region that gets added after the release of ZDM may not get recognized and the ZDM job may report an error on an unidentified OCI region. If the given OCI region is not recognized by ZDM, specify the OCI region details in `OCISDKCONFIG_REGISTERREGIONDETAILS*` for a database in the given region.

Parameter Relationships

The `OCISDKCONFIG_*` parameters specify OCI SDK configurations.

Property	Description
Syntax	<code>OCISDKCONFIG_REGISTERREGIONDETAILS_REGION_REALMKEY =</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Can be modified in any phase, no restrictions.

F.145 PROFILE

Specifies the full path to the source database profile file. ZDM maintains a key-value template for each of the supported database PROFILE. ZDM defines custom defaults with every PROFILE supported parameter.

Property	Description
Syntax	<code>PROFILE = {EBS.profile, FA.profile}</code>
Default value	NONE
Range of values	
Required	No
Modifiable on Resume	Yes

F.146 RUNCPATREMOTELY

Specifies whether Cloud Premigration Advisor Tool (CPAT) should run on the Zero Downtime Migration service host with a remote connection to the source database.

See [Running CPAT with a Remote Connection](#) for details.

Property	Description
Syntax	<code>RUNCPATREMOTELY = {TRUE FALSE}</code>
Default value	FALSE
Range of values	TRUE = run CPAT remotely FALSE = do not run CPAT remotely
Required	No
Modifiable on Resume	No

F.147 RUNFIXUPS

Specifies if you want to run automated fixups on the target database host.

Property	Description
Syntax	<code>RUNFIXUPS = {TRUE FALSE}</code>
Default value	FALSE
Range of values	TRUE = Automated fixup scripts are processed for the target database. FALSE = Automated Fixup scripts are not processed for the target database.
Required	No
Modifiable on Resume	No

F.148 REFRESHMVIEWS

Specifies whether you want to add the `ZDM_REFRESH_MVIEW` phase, for refreshing the materialized views post migration.

If `REFRESHMVIEW = FALSE`, then the `ZDM_REFRESH_MVIEW` phase is not added and materialized views are not refreshed post migration.

Note

If you do not set this property, by default the `ZDM_REFRESH_MVIEW` phase will be part of the migration for CLI based migration. However, for the Database Migration Service, the `ZDM_REFRESH_MVIEW` phase will not be a part of the migration.

See [Logical Migration Phase Descriptions](#) for details.

Property	Description
Syntax	REFRESHMVIEWS = {TRUE FALSE}
Default value	NULL
Range of values	TRUE = enables refresh of materialized views FALSE = does not enable refresh of materialized views NULL
Required	No
Modifiable on Resume	No

F.149 RELOADOBJECTS-LIST_ELEMENT_NUMBER

Specifies if the database objects have to be migrated in offline mode in an online job during target database instantiation.

Note

Starting with Oracle Zero Downtime Migration 26 (26.1) release, the `RELOADOBJECTS` parameter is deprecated and will be desupported in a future release. It is replaced by the following parameters:

- `GOLDENGATESETTINGS_EXTRACT_EXCLUDEOBJECTS`
- `GOLDENGATESETTINGS_REPLICAT_EXCLUDEOBJECTS`
- `GOLDENGATESETTINGS_EXCLUDERELOAD`
- `GOLDENGATESETTINGS_SKIPRELOADQUERYADVISOR`

Objects are migrated to the target database part of Data Pump for the target database instantiation. However, the objects are not considered for online syncing from source to target using Oracle GoldenGate. This can cater to any objects that are not to be replicated or not supported for replication. If objects are to be excluded from migration, then use the `EXCLUDEOBJECTS` parameter.

For objects specified in `RELOADOBJECTS-*`, objects with prefix `AQ$_` will be ignored. Basically, AQ objects are ignored if specified in the `RELOADOBJECTS-` property. To include AQ objects for reload, you must use `GOLDENGATESETTINGS_RELOADAQOBJECTS=TRUE`. ZDM reloads all the AQ objects in such case.

The specified objects are not replicated using Oracle GoldenGate. Instead, the specified objects are reloaded to the target database using Oracle Data Pump during phase `ZDM_RELOAD_PARALLEL_EXPORT_IMPORT` when there is no active workload on the source database.

Note

- This parameter is only supported for online logical migration.
- Use of wildcard expressions are allowed.

To reload multiple objects, increment the integer appended to the parameter name, as shown in the examples below.

```
RELOADOBJECTS-1=owner:ownerValue1, objectName:objectNameValue1,
objectType:objectTypeValue1
```

```
RELOADOBJECTS-2=owner:ownerValue2, objectName:objectNameValue2,
objectType:objectTypeValue2
```

See [Selecting Objects for Migration](#) for more information about using RELOADOBJECTS.

Note

You must note the following restrictions:

- Ensure to not reload AQ\$ objects or any ORACLE_MAINTAINED objects.
- Using DBLINK method is not supported for the reload feature.
- The base AQ tables can be reloaded, which will reload all the dependent objects.
- To reload the base AQ tables, the Oracle Database 19c source database must include the latest Datapump Bundle patch that includes patch for bug 34174611.
- Reload of base AQ should not be performed for database versions earlier than Oracle Database 19c.
- Reloading the base AQ tables with support mode as internal or PLSQL without the patch for bug 34174611 results in missing AQ\$ table.

Property	Description
Syntax	RELOADOBJECTS-LIST_ELEMENT_NUMBER = owner:ownerValue, objectName:objectNameValue, objectType:objectTypeValue
Default value	False
Range of values	True False
Required	No
Modifiable on Resume	Until ZDM_VALIDATE_SRC phase is COMPLETED.

F.150 COPYCPATREPORTTOZDMHOST

Specifies whether to copy the CPAT report log from the source database server to the ZDM server host job log directory for easier access to logs and more efficient troubleshooting.

Use this parameter when value of RUNCPATREMOTELY=FALSE and CPAT reports are required to be located in ZDM host. The COPYCPATREPORTTOZDMHOST parameter is skipped and the value is always FALSE when RUNCPATREMOTELY=TRUE.

Property	Description
Syntax	COPYCPATREPORTTOZDMHOST = {TRUE FALSE}

Property	Description
Default value	FALSE
Range of values	TRUE = copy the CPAT report log FALSE = do not copy the CPAT report log
Required	No
Modifiable on Resume	No

F.151 FORCECPATENUSLOCALE

Forces CPAT to use the en_US.UTF-8 Locale.

Property	Description
Syntax	FORCECPATENUSLOCALE = {TRUE FALSE}
Default value	FALSE
Range of values	TRUE = Enable CPAT to use the en_US.UTF-8 Locale. FALSE = Allows CPAT to use the default locale.
Required	No
Modifiable on Resume	Yes

F.152 SOURCECONTAINERDATABASE_ADMINUSERNAME

Specifies the source CDB administrator user name.

Parameter Relationships

For online logical migrations, the SOURCECONTAINERDATABASE_* parameters specify connection details for the source database CDB root.

Note

SOURCECONTAINERDATABASE_* is required for online migration when the source is a PDB. The Oracle GoldenGate Capture runs at CDB\$ROOT level.

Property	Description
Syntax	SOURCECONTAINERDATABASE_ADMINUSERNAME = <i>username</i>
Default value	There is no default value
Required	No
Modifiable on Resume	No

F.153

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE

Specifies the identity file to access the bastion, as part of the database connection details for bastion-based access to the database.

Parameter Relationships

For online logical migrations, the SOURCECONTAINERDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the source CDB.

The SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_* parameters specify details for bastion based access to the database.

Property	Description
Syntax	SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE = <i>bastion_id_file</i>
Default value	There is no default value
Required	Not mandatory for migration jobs
Modifiable on Resume	Yes

F.154

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP

Specifies the IP address of the source CDB bastion host, as part of the database connection details for bastion-based access to the database.

Parameter Relationships

For online logical migrations, the SOURCECONTAINERDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the source CDB root.

The SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_* parameters specify details for bastion based access to the database.

Property	Description
Syntax	SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP = <i>bastion_ip_address</i>
Default value	There is no default value
Required	Not mandatory for migration jobs
Modifiable on Resume	Yes

F.155

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT

Specifies the bastion host port, as part of the database connection details for bastion-based access to the container database (CDB).

Parameter Relationships

For online logical migrations, the `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source CDB root.

The `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_*` parameters specify details for bastion based access to the database.

Property	Description
Syntax	<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT =</code> <i>bastion_port_number</i>
Default value	There is no default value
Required	Not mandatory for migration jobs
Modifiable on Resume	Yes

F.156

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP

Specifies the remote host IP address to access from the bastion, as part of the database connection details for bastion-based access to the container database (CDB).

Parameter Relationships

For online logical migrations, the `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source CDB root.

The `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_*` parameters specify details for bastion based access to the database.

Property	Description
Syntax	<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP =</code> <i>ip_address</i>
Default value	There is no default value
Required	Not mandatory for migration jobs
Modifiable on Resume	Yes

F.157

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME

Specifies the user name to access the bastion, as part of the database connection details for bastion-based access to the container database (CDB).

Parameter Relationships

For online logical migrations, the `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source CDB root.

The `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_*` parameters specify details for bastion based access to the database.

Property	Description
Syntax	<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME = username</code>
Default value	There is no default value
Required	Not mandatory for migration jobs
Modifiable on Resume	Yes

F.158

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_HOST

Specifies the listener host name or IP address for the source container database (CDB).

Parameter Relationships

For online logical migrations, the `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source CDB root.

Property	Description
Syntax	<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_HOST = listener_host</code>
Default value	There is no default value
Required	Not mandatory for migration jobs Not required for migrations to Autonomous Database.
Modifiable on Resume	Yes

F.159

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PORT

Specifies the listener port number for the source container database (CDB).

Parameter Relationships

For online logical migrations, the `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source CDB root.

Property	Description
Syntax	<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PORT = listener_port</code>
Default value	There is no default value
Required	Not mandatory for migration jobs Not required for migrations to Autonomous Database.
Modifiable on Resume	Yes

F.160

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL

Specifies the proxy protocol for the CDB.

Parameter Relationships

For online logical migrations, the `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source CDB root.

The `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_*` parameters specify connection details for the source CDB root through an HTTP proxy.

Property	Description
Syntax	<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL = <protocolValue></code>
Default value	There is no default value. Following values are supported: <ul style="list-style-type: none">• HTTP• HTTPS
Required	No
Modifiable on Resume	Yes

F.161

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME

Specifies the HTTPS proxy host name for the CDB.

Parameter Relationships

For online logical migrations, the `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source CDB root.

The `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_*` parameters specify connection details for the source CDB root through an HTTP proxy.

Property	Description
Syntax	<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME = <i>proxy_hostname</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.162

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT

Specifies the HTTPS proxy host port number for the CDB.

Parameter Relationships

For online logical migrations, the `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source CDB root.

The `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_*` parameters specify connection details for the source CDB root through an HTTP proxy.

Property	Description
Syntax	<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT = <i>proxy_port</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.163

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_SERVICENAME

Specifies the fully qualified source CDB service name.

Parameter Relationships

For online logical migrations, the `SOURCECONTAINERDATABASE_*` parameters specify connection details for the source database CDB root.

Property	Description
Syntax	<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_SERVICENAME = service_name</code>
Default value	There is no default value
Required	Not mandatory for migration jobs Not required for Autonomous Database
Modifiable on Resume	No

F.164

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_TLSDetails_CREDENTIALSLOCATION

Specifies the directory containing client credentials (wallet, keystore, trustfile, etc.) for the CDB.

Note

This parameter is not required for Autonomous Database.

Parameter Relationships

For online logical migrations, the `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source CDB root.

The `SOURCECONTAINERDATABASE_CONNECTIONDETAILS_TLSDetails_*` parameters specify details for TLS connection to the database CDB. These settings are not required if you are using TCP.

Property	Description
Syntax	<code>SOURCECONTAINERDATABASE_CONNECTIONDETAILS_TLSDetails_CREDENTIALSLOCATION = directory</code>
Default value	There is no default value

Property	Description
Required	Not mandatory for migration jobs Not required for Autonomous Database Not required if you are using TCP
Modifiable on Resume	Yes

F.165

SOURCECONTAINERDATABASE_CONNECTIONDETAILS_TLSDetails_DISTINGUISHEDNAME

Specifies the distinguished name (DN) of the database server (SSL_SERVER_CERT_DN).

Note

This parameter is not required for Autonomous Database.

Parameter Relationships

For online logical migrations, the SOURCECONTAINERDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the source CDB root.

The SOURCECONTAINERDATABASE_CONNECTIONDETAILS_TLSDetails_* parameters specify details for TLS connection to the CDB. These settings are not required if you are using TCP.

Property	Description
Syntax	SOURCECONTAINERDATABASE_CONNECTIONDETAILS_TLSDetails_DISTINGUISHEDNAME = <i>distinguished_name</i>
Default value	There is no default value
Required	Not mandatory for migration jobs Not required for Autonomous Database Not required if you are using TCP
Modifiable on Resume	Yes

F.166

SOURCECONTAINERDATABASE_GGADMINUSERNAME

Specifies the source CDB GoldenGate administrator user name.

Parameter Relationships

For online logical migrations, the SOURCECONTAINERDATABASE_* parameters specify connection details for the source database CDB root.

Property	Description
Syntax	SOURCECONTAINERDATABASE_GGADMINUSERNAME = <i>GoldenGate administrator username</i>
Default value	There is no default value
Required	Not mandatory for migration jobs
Modifiable on Resume	No

F.167 SOURCEDATABASE_ADMINUSERNAME

Specifies the source database administrator user name.

Parameter Relationships

The SOURCEDATABASE_* parameters specify connection details for the source database.

Property	Description
Syntax	SOURCEDATABASE_ADMINUSERNAME = <i>source administrator username</i>
Default value	There is no default value
Required	Yes
Modifiable on Resume	No

F.168 SOURCEDATABASE_ALLOWTEMPTABLE

Indicates whether a new table should be created to store the unsupported table names of Oracle GoldenGate.

Parameter Relationships

The SOURCEDATABASE_* parameters specify connection details for the source database.

ZDM fetches the list of unsupported table names of Oracle GoldenGate from the metadata tables and stores them separately in a temporary table. Setting this parameter to `TRUE` allows ZDM to create a new `TEMP_ZDM_<jobid>` table in the source database. ZDM stores all the Oracle GoldenGate unsupported table names in this table. Once reload is completed, this table is dropped as part of the `ZDM_CLEANUP_SRC` phase.

Property	Description
Syntax	SOURCEDATABASE_ALLOWTEMPTABLE= { <code>TRUE</code> <code>FALSE</code> }
Default value	<code>FALSE</code>
Required	No
Modifiable on Resume	No

F.169

SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE

Specifies the identity file to access the bastion for bastion-based access to the database.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE = <i>identity file</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.170

SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP

Specifies the IP address of the bastion host for bastion-based access to the database.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP = <i>ip address</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.171

SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT

Specifies the port number of the bastion host for bastion-based access to the database.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT = <i>port_number</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.172

SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP

Specifies the remote host IP address to access from the bastion for bastion-based access to the database.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP = <i>ip_address</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.173

SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME

Specifies the user name to access the bastion for bastion-based access to the database.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME = username</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.174 SOURCEDATABASE_CONNECTIONDETAILS_HOST

Specifies the source database listener host name or IP address.

Parameter Relationships

The `SOURCEDATABASE_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_HOST = hostname_or_ip</code>
Default value	There is no default value
Required	Yes* *Not required for Autonomous Database.
Modifiable on Resume	Yes

F.175 SOURCEDATABASE_CONNECTIONDETAILS_PORT

Specifies the source database listener port number.

Parameter Relationships

The `SOURCEDATABASE_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_PORT = listener port number</code>
Default value	There is no default value

Property	Description
Required	Yes* *Not required for Autonomous Database.
Modifiable on Resume	Yes

F.176

SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME

Specifies the proxy host name to connect to the source database through an HTTPS proxy.

Parameter Relationships

The SOURCEDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the source database.

Property	Description
Syntax	SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME = <i>proxy host name</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.177

SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT

Specifies the HTTP proxy port number to connect to the source database through an HTTPS proxy.

Parameter Relationships

The SOURCEDATABASE_CONNECTIONDETAILS parameters specify connection details for the source database.

Property	Description
Syntax	SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT = <i>proxy port number</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.178

SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL

Specifies the proxy protocol to connect to the source database through a proxy.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL = HTTP or HTTPS</code>
Default value	HTTP
Required	No
Modifiable on Resume	Yes

F.179

SOURCEDATABASE_CONNECTIONDETAILS_SERVICENAME

Specifies the source database fully qualified service name.

Parameter Relationships

The `SOURCEDATABASE_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_SERVICENAME = <i>service name</i></code>
Default value	There is no default value
Required	Yes* *Not required for Autonomous Database
Modifiable on Resume	No

F.180

SOURCEDATABASE_CONNECTIONDETAILS_TLSDetails_CREDENTIALSLOCATION

Specifies the directory containing client credentials (wallet, keystore, trustfile, etc.) for a TLS connection to the database.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_TLSDetails_CREDENTIALSLOCATION = <i>directory</i></code>
Default value	There is no default value
Required	Not mandatory for migration jobs Not required if using TCP Not required for Autonomous Database
Modifiable on Resume	Yes

F.181

SOURCEDATABASE_CONNECTIONDETAILS_TLSDetails_DISTINGUISHEDNAME

Specifies the distinguished name (DN) of the database server (`SSL_SERVER_CERT_DN`) for a TLS connection to the database.

Parameter Relationships

The `SOURCEDATABASE_*` parameters specify connection details for the source database.

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_TLSDetails_DISTINGUISHEDNAME = <i>distinguished_name</i></code>
Default value	There is no default value
Required	Not mandatory for migration jobs Not required if using TCP Not required for Autonomous Database
Modifiable on Resume	Yes

F.182 SOURCEDATABASE_ENVIRONMENT_DBTYPE

Indicates the type of database to migrate from the specified environment.

If you specify that the source database environment is Amazon Web Services RDS by setting `SOURCEDATABASE_ENVIRONMENT_NAME=AMAZON`, then you must also set `SOURCEDATABASE_ENVIRONMENT_DBTYPE=RDS_ORACLE`.

See Migrating from Amazon Web Services RDS to Oracle Autonomous AI Database.

Parameter Relationships

The `SOURCEDATABASE_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_ENVIRONMENT_DBTYPE = RDS_ORACLE</code>
Default value	ORACLE
Required	No
Modifiable on Resume	No

F.183 SOURCEDATABASE_ENVIRONMENT_NAME

Specifies the environment of the source database.

You can specify whether the source database environment is Oracle (`ORACLE`) or Amazon Web Services RDS (`AMAZON`).

If you set `SOURCEDATABASE_ENVIRONMENT_NAME=AMAZON` you must also set `SOURCEDATABASE_ENVIRONMENT_DBTYPE=RDS_ORACLE`. See Migrating from Amazon Web Services RDS to Oracle Autonomous Database.

Parameter Relationships

The `SOURCEDATABASE_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_ENVIRONMENT_NAME = [ORACLE AMAZON]</code>
Default value	ORACLE
Required	No
Modifiable on Resume	No

F.184 SOURCEDATABASE_GGADMINUSERNAME

Specifies the GoldenGate administrator user name for online logical migrations.

Parameter Relationships

The `SOURCEDATABASE_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_GGADMINUSERNAME = gg_admin_username</code>
Default value	There is no default value
Required	No
Modifiable on Resume	No

F.185 SOURCEDATABASE_OCID

Specifies the OCID of the source Autonomous Database.

Note

Using the `SOURCEDATABASE_OCID` parameter, you can migrate from an Autonomous database to an Autonomous database within same tenancy and region. However, to migrate an Autonomous database to an Autonomous database across tenancy and regions use the `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters. Also, ensure to provide the `OCIAUTHENTICATIONDETAILS_*` of target region or tenancy. For logical online migration, ensure to provision GoldenGate hub in the target region or tenancy.

Parameter Relationships

The `SOURCEDATABASE_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_OCID = ocid of source adb</code>
Default value	There is no default value
Required	No
Modifiable on Resume	No

F.186 SOURCESTANDBYDATABASE_CONNECTIONDETAILS_HOST

Specifies the listener host name or IP address of the source standby database.

Parameter Relationships

The `SOURCESTANDBYDATABASE_*` parameters specify connection details for the source standby database.

Property	Description
Syntax	<code>SOURCESTANDBYDATABASE_CONNECTIONDETAILS _HOST = ocid of source adb</code>
Default value	There is no default value

Property	Description
Required	Yes Not required for Oracle Autonomous AI Database.
Modifiable on Resume	No

F.187

SOURCESTANDBYDATABASE_CONNECTIONDETAILS_PORT

Specifies the listener port number of the source standby database.

Parameter Relationships

The SOURCESTANDBYDATABASE_* parameters specify connection details for the source standby database.

Property	Description
Syntax	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_PORT = <i>listener port number</i>
Default value	There is no default value
Required	Yes Not required for Oracle Autonomous AI Database.
Modifiable on Resume	No

F.188

SOURCESTANDBYDATABASE_CONNECTIONDETAILS_SERVICENAME

Specifies the fully qualified service name of the source standby database.

Parameter Relationships

The SOURCESTANDBYDATABASE_* parameters specify connection details for the source standby database.

Property	Description
Syntax	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_SERVICENAME = <i>service name</i>
Default value	There is no default value
Required	Yes Not required for Oracle Autonomous AI Database.
Modifiable on Resume	No

F.189

SOURCESTANDBYDATABASE_CONNECTIONDETAILS_TLSDetails_DISTINGUISHEDNAME

Specifies the distinguished name (DN) of the database server (SSL_SERVER_CERT_DN) for a TLS connection to the database.

Parameter Relationships

The SOURCESTANDBYDATABASE_* parameters specify connection details for the source standby database.

The SOURCESTANDBYDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the source standby database.

Property	Description
Syntax	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_TLSDetails_DISTINGUISHEDNAME = <i>distinguished_name</i>
Default value	There is no default value
Required	Yes Not required for Oracle Autonomous AI Database. Not mandatory for migration jobs Not required if using TCP
Modifiable on Resume	Yes

F.190

SOURCESTANDBYDATABASE_CONNECTIONDETAILS_TLSDetails_CREDENTIALSLOCATION

Specifies the directory containing client credentials such as wallet, keystore, trustfile, and so on for a TLS connection to the database.

Parameter Relationships

The SOURCESTANDBYDATABASE_* parameters specify connection details for the source standby database.

The SOURCESTANDBYDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the source standby database.

Property	Description
Syntax	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_TLSDetails_CREDENTIALSLOCATION = <i>directory</i>
Default value	There is no default value

Property	Description
Required	Yes Not required for Oracle Autonomous AI Database. Not mandatory for migration jobs Not required if using TCP
Modifiable on Resume	Yes

F.191

SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP

Specifies the IP address of the bastion host for bastion-based access to the database.

Parameter Relationships

The SOURCESTANDBYDATABASE_* parameters specify connection details for the source standby database.

The SOURCESTANDBYDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the source standby database.

Property	Description
Syntax	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP = <i>ip address</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.192

SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT

Specifies the port number of the bastion host for bastion-based access to the database.

Parameter Relationships

The SOURCESTANDBYDATABASE_* parameters specify connection details for the source standby database.

The SOURCESTANDBYDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the source standby database.

Property	Description
Syntax	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT = <i>port_number</i>

Property	Description
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.193

SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE

Specifies the identity file to access the bastion for bastion-based access to the database.

Parameter Relationships

The `SOURCESTANDBYDATABASE_*` parameters specify connection details for the source standby database.

The `SOURCESTANDBYDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source standby database.

Property	Description
Syntax	<code>SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE = identity file</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.194

SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME

Specifies the user name to access the bastion for bastion-based access to the database.

Parameter Relationships

The `SOURCESTANDBYDATABASE_*` parameters specify connection details for the source standby database.

The `SOURCESTANDBYDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source standby database.

Property	Description
Syntax	<code>SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME = username</code>
Default value	There is no default value

Property	Description
Required	No
Modifiable on Resume	Yes

F.195

SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP

Specifies the remote host IP address to access from the bastion for bastion-based access to the database.

Parameter Relationships

The `SOURCESTANDBYDATABASE_*` parameters specify connection details for the source standby database.

The `SOURCESTANDBYDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source standby database.

Property	Description
Syntax	<code>SOURCESTANDBYDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP = ip address</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.196

SOURCESTANDBYDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL

Specifies the proxy protocol to connect to the source standby database through a proxy.

Parameter Relationships

The `SOURCESTANDBYDATABASE_*` parameters specify connection details for the source standby database.

The `SOURCESTANDBYDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source standby database.

Property	Description
Syntax	<code>SOURCESTANDBYDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL = HTTP or HTTPS</code>
Default value	HTTP

Property	Description
Required	No
Modifiable on Resume	Yes

F.197

SOURCESTANDBYDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME

Specifies the proxy host name to connect to the source standby database through an HTTPS proxy.

Parameter Relationships

The SOURCESTANDBYDATABASE_* parameters specify connection details for the source standby database.

The SOURCESTANDBYDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the source standby database.

Property	Description
Syntax	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME = <i>proxy host name</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.198

SOURCESTANDBYDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT

Specifies the HTTP proxy port number to connect to the source standby database through an HTTPS proxy.

Parameter Relationships

The SOURCESTANDBYDATABASE_* parameters specify connection details for the source standby database.

The SOURCESTANDBYDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the source standby database.

Property	Description
Syntax	SOURCESTANDBYDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT = <i>proxy port number</i>

Property	Description
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.199 STS_SCHEMANAME

Specifies the schema under which the staging table is created. Specify the schema name where you want to create the STS staging table.

Note

If you do not specify STS_SCHEMANAME, then the staging table is created under the exporting schema.

Parameter Relationships

Property	Description
Syntax	STS_SCHEMANAME = <i>schema_name</i>
Default value	There is no default value
Required	No
Modifiable on Resume	No

F.200 STS_SQLSETNAME

Specifies the name of the SQL tuning set to be packed. Specify the name of the SQL tuning set to be packed.

Parameter Relationships

Property	Description
Syntax	STS_SQLSETNAME = <i>schema_name</i>
Default value	There is no default value
Required	No
Modifiable on Resume	No

F.201 STS_SQLSETREPLACE

Determines if an existing SQL tuning set has to be replaced while unpacking the STS data.

If you set the parameter to `TRUE`, then while unpacking the STS staging table, if the SQL tuning set already exists then the existing SQL tuning set is replaced.

Parameter Relationships

Property	Description
Syntax	STS_SQLSETREPLACE = <i><TRUE FALSE></i>
Default value	FALSE
Required	No
Modifiable on Resume	No

F.202 STS_SQLSETOWNER

Specifies the owner of the SQL Tuning Set. By default, this parameter is null.

If you do not provide the value in the parameter, then ZDM assumes SYS as the SQL set owner.

Parameter Relationships

Property	Description
Syntax	STS_SQLSETOWNER = <i><sqlset_owner></i>
Default value	null
Required	No
Modifiable on Resume	No

F.203 TABLESPACEDETAILS_AUTOCREATE

Specifies whether Zero Downtime Migration automatically creates DATA, TEMPORARY, and UNDO tablespaces at the target database necessary to allocate space in the database to contain schema objects.

This option is prohibited for Autonomous Database Shared targets.

See Automatic Tablespace Creation for more information.

Parameter Relationships

In a logical migration, the TABLESPACEDETAILS_* parameters specify details that allow Zero Downtime Migration to automatically create the required tablespaces at target database.

Property	Description
Syntax	TABLESPACEDETAILS_AUTOCREATE={TRUE FALSE}
Default value	TRUE

Property	Description
Range of values	<p>TRUE - Zero Downtime Migration automatically creates tablespaces</p> <p>FALSE - Zero Downtime Migration does not create tablespaces</p>
Required	<p>No</p> <p>This option is prohibited for Autonomous Database Shared targets.</p>
Modifiable on Resume	<p>Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED</p>

Note

The value of TABLESPACEDETAILS_AUTOCREATE is set to TRUE by default for ADBS target and for all the other targets it is set to FALSE by default.

F.204 TABLESPACEDETAILS_AUTOREMAP

Specifies whether Zero Downtime Migration automatically remaps a tablespace at the target database.

See Automatic Tablespace Remap for more information.

Parameter Relationships

In a logical migration, the TABLESPACEDETAILS_* parameters specify details that allow Zero Downtime Migration to automatically create the required tablespaces at target database.

Property	Description
Syntax	TABLESPACEDETAILS_AUTOREMAP={ TRUE FALSE }
Default value	FALSE
Range of values	<p>TRUE - Zero Downtime Migration automatically remaps tablespaces</p> <p>FALSE - Zero Downtime Migration does not remap tablespaces</p>
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_IMPORT_TGT phase is COMPLETED

F.205 TABLESPACEDETAILS_EXCLUDE

Specifies tablespaces to be excluded from automatic creation at the target database.

See Automatic Tablespace Creation for more information.

Example

```
TABLESPACEDETAILS_EXCLUDE=B2B_LOB_TS,B2B_HR_TS
```

Parameter Relationships

In a logical migration, the `TABLESPACEDETAILS_*` parameters specify details that allow Zero Downtime Migration to automatically create the required tablespaces at target database.

Property	Description
Syntax	<code>TABLESPACEDETAILS_EXCLUDE=tablespace_names</code>
Default value	By default SYSTEM, SYSAUX, and USERS tablespaces are excluded.
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED

F.206 TABLESPACEDETAILS_EXTENDSIZE MB

Specifies an extend size for `AUTOEXTEND` in support of automatic tablespace creation.

Properly setting `TABLESPACEDETAILS_EXTENDSIZE MB` enables `AUTOEXTEND` to avoid extend errors when automatic tablespace creation is enabled.

See Automatic Tablespace Creation for more information.

Parameter Relationships

In a logical migration, the `TABLESPACEDETAILS_*` parameters specify details that allow Zero Downtime Migration to automatically create the required tablespaces at target database.

Property	Description
Syntax	<code>TABLESPACEDETAILS_EXTENDSIZE MB=MB</code>
Default value	512
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED

F.207 TABLESPACEDETAILS_REMAPTARGET

Specifies tablespaces to be remapped.

For a tablespace to be used as `REMAP` target, the user performing the import operation, for example `SYSTEM`, should have some quota on the chosen tablespace.

See Automatic Tablespace Remap for more information.

Parameter Relationships

In a logical migration, the `TABLESPACEDETAILS_*` parameters specify details that allow Zero Downtime Migration to automatically create the required tablespaces at target database.

Property	Description
Syntax	<code>TABLESPACEDETAILS_REMAPTARGET=target_tablespaces_names</code>
Default value	By default the DATA tablespace is remapped.
Required	No
Modifiable on Resume	Until <code>ZDM_DATAPUMP_IMPORT_TGT</code> phase is COMPLETED

F.208 TABLESPACEDETAILS_REMAPTEMPTARGET

Specifies the TEMP tablespace at the target database to which the temporary tablespace of the source database needs to be remapped.

Name of TEMP tablespace at target to which the source database temporary tablespace need to be remapped. Setting `TABLESPACEDETAILS_AUTOREMAP` to TRUE and setting this parameter enables remap of temporary tablespaces.

Parameter Relationships

In a logical migration, the `TABLESPACEDETAILS_*` parameters specify details that allow Zero Downtime Migration to automatically create the required tablespaces at target database.

Property	Description
Syntax	<code>TABLESPACEDETAILS_REMAPTEMPTARGET={TRUE FALSE}</code>
Default value	<ul style="list-style-type: none"> Remap by default to temporary tablespace TEMP for migrating to Autonomous Database. No default for migrating to non Autonomous targets
Range of values	<p>TRUE - Zero Downtime Migration automatically remaps TEMP tablespaces.</p> <p>FALSE - Zero Downtime Migration does not remap TEMP tablespaces.</p>
Required	No
Modifiable on Resume	Until <code>ZDM_DATAPUMP_IMPORT_TGT</code> phase is COMPLETED .

F.209 TABLESPACEDETAILS_USEBIGFILE

Specifies whether to use bigfile tablespaces, if Zero Downtime Migration is configured to create tablespaces automatically.

Using bigfile tablespaces, which can be up to 128 TB, significantly reduces the number of data files for your database. Combined with Oracle Managed Files (OMF), bigfile tablespaces simplify data file management.

See Automatic Tablespace Creation for more information.

Parameter Relationships

In a logical migration, the `TABLESPACEDETAILS_*` parameters specify details that allow Zero Downtime Migration to automatically create the required tablespaces at target database.

Property	Description
Syntax	<code>TABLESPACEDETAILS_USEBIGFILE={TRUE FALSE}</code>
Default value	FALSE
Range of values	TRUE - Zero Downtime Migration automatically creates bigfile tablespaces FALSE - Zero Downtime Migration does not create bigfile tablespaces
Required	No
Modifiable on Resume	Until <code>ZDM_PREPARE_DATAPUMP_SRC</code> phase is COMPLETED

F.210 TABLESPACEDETAILS_BLOCKSIZE

Specifies the size of Oracle database blocks in kilobytes (KB).

If you do not specify any value for `TABLESPACEDETAILS_BLOCKSIZE`, then the source tablespace blocksize is considered. You can query the source blocksize using the following SQL command:

```
select block_size from dba_tablespaces;
```

Parameter Relationships

In a logical migration, the `TABLESPACEDETAILS_*` parameters specify details that allow Zero Downtime Migration to automatically create the required tablespaces at target database.

Note

Ensure that the target database has `db_block_size` set to 16k or set `db_16k_cache_size` if `db_block_size` is 8k. See [DB_nK_CACHE_SIZE](#) for the appropriate value to be specified for `db_16k_cache_size`.

Property	Description
Syntax	TABLESPACEDetails_BLOCKSIZE= 12 or 32
Default value	There is no default value
Range of values	8 12 16 32
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED

F.211 TARGETDATABASE_ADMINUSERNAME

Specifies the target database administrator user name.

Parameter Relationships

The TARGETDATABASE_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_ADMINUSERNAME = <i>username</i>
Default value	There is no default value
Required	Yes
Modifiable on Resume	No

F.212

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE

Specifies the identity file to access the bastion for bastion-based access to the target database.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

These are optional for Autonomous Database; however if an HTTP proxy is required to connect, specify them.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE = <i>bastion_id_file</i>
Default value	There is no default value
Required	Not mandatory for migration jobs

Property	Description
Modifiable on Resume	Yes

F.213

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP

Specifies the IP address of the bastion host for bastion-based access to database.

Parameter Relationships

The `TARGETDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the target OCI database.

These are optional for Autonomous Database; however if an HTTP proxy is required to connect, specify them.

Property	Description
Syntax	<code>TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP = ip address</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.214

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT

Specifies the port number of the bastion host for bastion-based access to database.

Parameter Relationships

The `TARGETDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the target OCI database.

These are optional for Autonomous Database; however if an HTTP proxy is required to connect, specify them.

Property	Description
Syntax	<code>TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT = port_number</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.215

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP

Specifies the remote host IP address to access from the bastion for bastion-based access to database.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

These are optional for Autonomous Database; however if an HTTP proxy is required to connect, specify them.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP = <i>ip_address</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.216

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME

Specifies the user name to access the bastion for bastion-based access to database.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

These are optional for Autonomous Database; however if an HTTP proxy is required to connect, specify them.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME = <i>username</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.217 TARGETDATABASE_CONNECTIONDETAILS_HOST

Specifies the listener host name or IP address.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS parameters specify connection details for the target OCI database.

These properties are optional for Autonomous Database; however if an HTTP proxy is required to connect, specify them.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_HOST = <i>hostname_or_ip</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.218 TARGETDATABASE_CONNECTIONDETAILS_PORT

Specifies the listener port number.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

These are optional for Autonomous Database; however if an HTTP proxy is required to connect, specify them.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_PORT = <i>listener port number</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.219 TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME

Specifies the proxy host name for connecting to the target database through an HTTPS proxy.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME = <i>proxy host name</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.220

TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT

Specifies the HTTP proxy port number for connecting to the source database through an HTTPS proxy.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT = <i>proxy port number</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

F.221

TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL

Specifies the proxy protocol to connect to the target database through a proxy.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL = HTTP or HTTPS
Default value	HTTP
Required	No
Modifiable on Resume	Yes

F.222

TARGETDATABASE_CONNECTIONDETAILS_SERVICENAME

Specifies the fully qualified service name.

This parameter is optional for Oracle Autonomous AI Database targets; however if an HTTP proxy is required to connect, specify it.

In addition, for Oracle Autonomous AI Database on Dedicated Exadata Infrastructure and Oracle Autonomous Database on Exadata Cloud@Customer with **fractional OCPU** service you must specify the appropriate service alias in the parameter.

You can specify any predefined fractional service alias available; however, for Autonomous Transaction Processing workloads TP* services are preferred over LOW* services because LOW* is meant for low priority batch jobs.

- TP_TLS, TP, LOW_TLS or LOW (for Autonomous Transaction Processing workloads)
- LOW_TLS or LOW (for Autonomous Data Warehouse workloads)

See also [Connecting to a DB System](#) and [About Connecting to a Dedicated Autonomous Database](#)

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_SERVICENAME = <i>service_name_or_alias</i>
Default value	There is no default value
Valid values	<p>For non-Autonomous, specify the fully qualified service name.</p> <p>For Autonomous, you can specify the service alias for fractional OCPU service as:</p> <ul style="list-style-type: none">• TP_TLS, TP, LOW_TLS or LOW (for Autonomous Transaction Processing workloads)• LOW_TLS or LOW (for Autonomous Data Warehouse workloads)
Required	No
Modifiable on Resume	No

F.223

TARGETDATABASE_CONNECTIONDETAILS_TLSDetails_CREDENTIALSLOCATION

Specifies the directory containing client credentials (wallet, keystore, trustfile, etc.) for a TLS connection.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

These are optional for Autonomous Database; however if an HTTP proxy is required to connect, specify them.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_TLSDetails_CREDENTIALSLOCATION = <i>directory</i>
Default value	There is no default value
Required	Not mandatory for migrations Not required if using TCP
Modifiable on Resume	Yes

F.224

TARGETDATABASE_CONNECTIONDETAILS_TLSDetails_DISTINGUISHEDNAME

Specifies the distinguished name (DN) of the database server (SSL_SERVER_CERT_DN) for a TLS connection.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

These are optional for Autonomous Database; however if an HTTP proxy is required to connect, specify them.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_TLSDetails_DISTINGUISHEDNAME = <i>distinguished_name</i>
Default value	There is no default value
Required	Required if the DB connection is over TLS.
Modifiable on Resume	Yes

F.225 TARGETDATABASE_GGADMINUSERNAME

Specifies the GoldenGate administrator user name for online logical migrations.

Parameter Relationships

The TARGETDATABASE_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_GGADMINUSERNAME = <i>gg_admin_username</i>
Default value	There is no default value
Required	No
Modifiable on Resume	No

F.226 TARGETDATABASE_OCID

Specifies the Oracle Cloud resource identifier.

Parameter Relationships

The TARGETDATABASE_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_OCID = <i>ocid</i>
Default value	There is no default value
Required	Yes This is an optional parameter if TARGETDATABASE_DBTYPE is set to valid a value.
Modifiable on Resume	No

F.227 TARGETDATABASE_DBTYPE

Specifies the target database type if OCID of the target database is not provided.

You can migrate database to Oracle Autonomous AI Database on Exadata Cloud@Customer without needing an OCID if value of TARGETDATABASE_DBTYPE = ADBCC.

Parameter Relationships

The TARGETDATABASE_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_DBTYPE = <i>dbtypeValue</i>

Property	Description
Default value	There is no default value The following values are supported: <ul style="list-style-type: none"> • <i>ORACLE</i> • <i>ADBD</i> • <i>ADBS</i> • <i>ADBCC</i> • <i>EXADATA</i>
Required	No
Modifiable on Resume	No

F.228 WALLET_USERACTION

Allows you to provide the auto login wallet path, which contains the username and its password.

Note

This parameter is supported only for logical migration.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The WALLET_* parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_USERACTION = wallet_path</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED.

F.229 WALLET_AMAZONS3SECRET

Specifies the Amazon S3 Secret Key wallet path.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The WALLET_* parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_AMAZONS3SECRET = wallet_path</code>

Property	Description
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED.

F.230 WALLET_OCIAUTHTOKEN

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, which is used to get the OCI Auth Token password.

Note

This parameter is applicable only when the source database is Oracle Autonomous Database on Shared Exadata Infrastructure or Oracle Autonomous Database on Dedicated Exadata Infrastructure.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_OCIAUTHTOKEN = wallet_path</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED.

F.231 WALLET_DATAPUMPENCRYPTION

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, which is used to get the Data Pump encryption password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_DATAPUMPENCRYPTION = wallet_path</code>
Default value	There is no default value
Required	No

Property	Description
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED.

F.232 WALLET_OGGADMIN

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, which is used to get the Oracle GoldenGate hub administrative password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_OGGADMIN = wallet_path</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED.

F.233 WALLET_SOURCECONTAINER

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, which is used to get the source database administrative user password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_SOURCECONTAINER = wallet_path</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED.

F.234 WALLET_SOURCECGGADMIN

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, which is used to get the source database administrative `c##ggadmin` user password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_SOURCEGGADMIN = wallet_path</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until <code>ZDM_PREPARE_DATAPUMP_SRC</code> phase is COMPLETED.

F.235 WALLET_SOURCEGGADMIN

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, which is used to get the source database administrative user `ggadmin` password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_SOURCEGGADMIN = wallet_path</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until <code>ZDM_PREPARE_DATAPUMP_SRC</code> phase is COMPLETED.

F.236 WALLET_TARGETADMIN

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, which is used to get the target database administrative admin password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_TARGETADMIN = wallet_path</code>
Default value	There is no default value
Required	No

Property	Description
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED.

F.237 WALLET_TARGETGGADMIN

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, which is used to get the target database administrative user `ggadmin` password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_TARGETGGADMIN = wallet_path</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED.

F.238 WALLET_OGGSERVICEADMIN

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, for specifying the Oracle Cloud Infrastructure GoldenGate administrative password.

The path should be accessible from the Zero Downtime Migration node.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_OGGSERVICEADMIN = Absolute path to wallet on ZDM host</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED.

G

Zero Downtime Migration Hybrid Migration Response File Parameters Reference

The following topics describe the Zero Downtime Migration response file parameters used in hybrid migrations.

G.1 MIGRATION_METHOD

Specifies the method of migration.

Property	Description
Syntax	<code>MIGRATION_METHOD = {OFFLINE_XTTS}</code>
Default value	<code>OFFLINE_XTTS</code>
Range of values	<code>OFFLINE_XTTS</code>
Required	Yes
Modifiable on Resume	No

G.2 DATA_TRANSFER_MEDIUM

Specifies how data will be transferred from the source database system to the target database system.

See also [Configuring the Transfer Medium and Specifying Transfer Nodes](#)

Property	Description
Syntax	<code>DATA_TRANSFER_MEDIUM = { NFS }</code>
Default value	<code>NFS</code>
Range of values	<code>NFS - Network File System</code>
Required	Yes
Modifiable on Resume	No

G.3 TARGETDATABASE_ADMINUSERNAME

Specifies the target database administrator user name.

Parameter Relationships

For example, for a co-managed database, the migration user name can be `system`. The `TARGETDATABASE_*` parameters specify connection details for the target OCI database.

Property	Description
Syntax	<code>TARGETDATABASE_ADMINUSERNAME = <i>username</i></code>
Default value	There is no default value
Required	Yes
Modifiable on Resume	No

G.4 SOURCEDATABASE_ADMINUSERNAME

Specifies the source database administrator user name.

Parameter Relationships

The `SOURCEDATABASE_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_ADMINUSERNAME = <i>source administrator username</i></code>
Default value	There is no default value
Required	Yes
Modifiable on Resume	No

G.5

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_IMPORTPARALLELISMDEGREE

Specifies the maximum number of worker processes that can be used for a Data Pump Import job.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

`DATAPUMPSETTINGS_DATAPUMPPARAMETERS_*` are optional parameters for Data Pump Export and Import. See `SET_PARAMETER` Procedures for more information.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_IMPORTPARALLELISMDEGREE = <i>integer</i></code>
Default value	There is no default value
Valid values	An integer value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_DATAPUMP_IMPORT_TGT</code> phase is COMPLETED.

G.6

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXPORTPARALLELISMDEGREE

Specifies the maximum number of worker processes that can be used for a Data Pump Import job.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

`DATAPUMPSETTINGS_DATAPUMPPARAMETERS_*` are optional parameters for Data Pump Export and Import. See `SET_PARAMETER` Procedures for more information.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_EXPORTPARALLELISMDEGREE = integer</code>
Default value	There is no default value
Valid values	An integer value is expected
Required	No
Modifiable on Resume	Until <code>ZDM_DATAPUMP_EXPORT_SRC</code> phase is COMPLETED.

G.7

DATAPUMPSETTINGS_DATAPUMPPARAMETERS_NOCLUSTER

Specifies whether all Data Pump workers are started on the current instance or on instances usable by the job.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

`DATAPUMPSETTINGS_DATAPUMPPARAMETERS_*` are optional parameters for Data Pump Export and Import. See `SET_PARAMETER` Procedures for more information.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_DATAPUMPPARAMETERS_NOCLUSTER = [TRUE FALSE]</code>
Default value	FALSE

Property	Description
Valid values	TRUE all Data Pump workers are started on the current instance FALSE Data Pump workers are started on instances usable by the job
Required	No
Modifiable on Resume	No

G.8 DATAPUMPSETTINGS_EXPORTVERSION

Specifies the Data Pump job export version.

See Oracle Data Pump documentation for Data Pump Export Version.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_EXPORTVERSION = ["COMPATIBLE" , "12" , "LATEST"]
Default value	COMPATIBLE, if the target database is of same or higher version than that of source database, and specific version, if the target database is a lower version than that of source database.
Required	No

G.9 DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_NAME

Specifies the object name of a directory on server file system of an on-premises database.

In lieu of a network database link, a directory on the server file system of an on-premises database, specified with the `DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_*` properties is used to store Data Pump Export dump files.

Zero Downtime Migration creates this object if it does not already exist

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_NAME = <i>Name</i>
Default value	There is no default value
Range of values	Name of directory object in the database.

Property	Description
Required	No
Modifiable on Resume	Until ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC phase is COMPLETED.

G.10

DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_PATH

Specifies the absolute object path of a directory on server file system of an on-premises database.

In lieu of a network database link, a directory on the server file system of an on-premises database, specified with the `DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_*` properties is used to store Data Pump Export dump files.

Zero Downtime Migration creates this object if it does not already exist

Note

For Oracle Database 19c and later releases, the `UTL_FILE_DIR` initialization parameter is desupported, which means symbolic links for Data Pump directories are not supported.

If you attempt to use an affected feature configured with symbolic links, then you encounter ORA-29283: invalid file operation: path traverses a symlink. Oracle recommends that you instead use directory objects in place of symbolic links.

See [How Does Oracle Data Pump Move Data?](#) for more information.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_EXPORTDIRECTORYOBJECT_PATH = Path</code>
Default value	There is no default value
Range of values	Absolute path of directory on database server
Required	No
Modifiable on Resume	Until ZDM_VALIDATE_DATAPUMP_SETTINGS_SRC phase is COMPLETED.

G.11

DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_NAME

Specifies the name of an import directory object.

In lieu of a network database link, a directory on the server file system of OCI database is used to store Data Pump dump files.

Zero Downtime Migration creates this object if it does not already exist.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_NAME</code> = <i>Name of the directory object</i>
Default value	There is no default value
Range of values	Name of directory object in database
Required	No
Modifiable on Resume	Until <code>ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT</code> phase is <code>COMPLETED</code> .

G.12

DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_PATH

Specifies the absolute path of an import directory object.

In lieu of a network database link, a directory on the server file system of OCI database is used to store Data Pump dump files.

Zero Downtime Migration creates this object if it does not already exist.

Note

For Oracle Database 19c and later releases, the `UTL_FILE_DIR` initialization parameter is desupported, which means symbolic links for Data Pump directories are not supported.

If you attempt to use an affected feature configured with symbolic links, then you encounter `ORA-29283: invalid file operation: path traverses a symlink`. Oracle recommends that you instead use directory objects in place of symbolic links.

See *How Does Oracle Data Pump Move Data?* for more information.

Parameter Relationships

The optional `DATAPUMPSETTINGS_*` parameters let you customize Oracle Data Pump Export and Import jobs.

Property	Description
Syntax	<code>DATAPUMPSETTINGS_IMPORTDIRECTORYOBJECT_PATH = Path of the directory object</code>
Default value	There is no default value
Range of values	Absolute path of directory on database server
Required	No
Modifiable on Resume	Until <code>ZDM_VALIDATE_DATAPUMP_SETTINGS_TGT</code> phase is <code>COMPLETED</code> .

G.13 DUMPTRANSFERDETAILS_PUBLICREAD

Specifies if the dump files on NFS are readable for others.

Parameter Relationships

This option allows target database user to read the dumps on the shared path when the dump files are allowed to be read by public.

This helps when the user accessing source database server is not allowed to change the group ownership on dumps on the shared path.

The `DUMPTRANSFERDETAILS_*` parameters specify details to transfer dumps from the source node to the target node.

Supported modes of transfer are OSS and secure copy. Upload of dumps to OSS can be either through OCI CLI or Curl.

Property	Description
Syntax	<code>DUMPTRANSFERDETAILS_PUBLICREAD = {TRUE FALSE}</code>
Default value	FALSE
Range of values	TRUE: Dump files on NFS are readable by public. FALSE: Dump files on NFS are not readable by public.
Required	No
Modifiable on Resume	Until <code>ZDM_TRANSFER_DUMPS_SRC</code> phase is <code>COMPLETED</code>

G.14 IGNOREEXPORTERRORS

Specifies comma separated list of ORA errors to be ignored for Oracle Data Pump export. For any new error to be ignored, suffix the new error to the list of default errors to be ignored.

Property	Description
Syntax	IGNOREEXPORTERRORS = ORA_error_list
Default value	ORA-31684,ORA-39111,ORA-39082
Range of values	ORA-31684,ORA-39111,ORA-39082
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_EXPORT_SRC phase is COMPLETED.

G.15 IGNOREIMPORTERRORS

Specifies comma separated list of ORA errors to be ignored for Oracle Data Pump import. For any new error to be ignored, suffix the new error to the list of default errors to be ignored.

Property	Description
Syntax	IGNOREIMPORTERRORS = ORA_error_list
Default value	ORA-31684,ORA-39111,ORA-39082
Range of values	ORA-31684,ORA-39111,ORA-39082
Required	No
Modifiable on Resume	Until ZDM_DATAPUMP_IMPORT_TGT phase is COMPLETED.

G.16 RMANSETTINGS_SRCCHANNELS

Specifies the number of RMAN channels to be allocated at the source for performing RMAN backups.

Property	Description
Syntax	RMANSETTINGS_SRCCHANNELS = integer
Default value	10
Range of values	0 to 10
Required	No
Modifiable on Resume	Until ZDM_XTTS_BACKUP_INCR_RO_SRC phase is COMPLETED.

G.17 RMANSETTINGS_TGTCHANNELS

Specifies the number of RMAN channels to be allocated at the source for performing RMAN backups.

Property	Description
Syntax	RMANSETTINGS_TGTCHANNELS = integer
Default value	10

Property	Description
Range of values	0 to 10
Required	No
Modifiable on Resume	Until ZDM_XTTS_RESTORE_INCR_TGT phase is COMPLETED.

G.18 RMANSETTINGS_RETENTIONWINDOW

Specifies the number of days after which backups created by ZDM become obsolete.

Property	Description
Syntax	RMANSETTINGS_RETENTIONWINDOW = integer
Default value	
Range of values	
Required	No
Modifiable on Resume	Until ZDM_XTTS_BACKUP_INCR_RO_SRC phase is COMPLETED.

G.19 RMANSETTINGS_BACKUPTAG

Specifies the backup tag to create or use backup. By default ZDM will generate a job# specific backup tag.

Property	Description
Syntax	RMANSETTINGS_BACKUPTAG = integer
Default value	
Range of values	
Required	No
Modifiable on Resume	Until ZDM_XTTS_BACKUP_FULL_SRC phase is COMPLETED.

G.20 RMANSETTINGS_SECTIONSIZE

Specifies the backup tag RMAN section size to use for backups. Specify the value as 0 to skip using section size.

Property	Description
Syntax	RMANSETTINGS_SECTIONSIZE = <integer>{K M G T}>
Default value	64G
Range of values	
Required	No

Property	Description
Modifiable on Resume	Until ZDM_XTTS_BACKUP_INCR_RO_SRC phase is COMPLETED.

G.21 RMANSETTINGS_COMPRESSIONALGORITHM

Specifies the RMAN Compression algorithm to use for backups.

Property	Description
Syntax	RMANSETTINGS_COMPRESSIONALGORITHM = BASIC LOW HIGH MEDIUM NONE
Default value	MEDIUM
Range of values	<ul style="list-style-type: none"> BASIC: Basic Compression Algorithm LOW: Least impact on backup throughput and suited for environments where CPU resources are the limiting factor. HIGH: Best suited for backups over slower networks where the limiting factor is network speed. MEDIUM: Recommended for most environments. Good combination of compression ratios and speed. NONE: Do not use compression.
Required	No
Modifiable on Resume	Until ZDM_XTTS_BACKUP_INCR_RO_SRC phase is COMPLETED.

G.22 RMANSETTINGS_PUBLICREAD

Specifies the backup files on shared storage to be made readable for others. This option allows target database user to read backups on shared path as the backup file directory is allowed to be read by public. This helps if the user accessing source database server is not allowed to change the group ownership on backups on shared path.

Property	Description
Syntax	RMANSETTINGS_PUBLICREAD = TRUE FALSE
Default value	FALSE
Range of values	TRUE or FALSE
Required	No
Modifiable on Resume	Until ZDM_XTTS_BACKUP_INCR_RO_SRC phase is COMPLETED.

G.23

SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE

Specifies the identity file to access the bastion for bastion-based access to the database.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE = <i>identity file</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.24

SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP

Specifies the IP address of the bastion host for bastion-based access to the database.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP = <i>ip address</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.25

SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT

Specifies the port number of the bastion host for bastion-based access to the database.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT = <i>port_number</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.26

SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP

Specifies the remote host IP address to access from the bastion for bastion-based access to the database.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP = <i>ip_address</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.27

SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME

Specifies the user name to access the bastion for bastion-based access to the database.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME = <i>username</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.28

SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME

Specifies the proxy host name to connect to the source database through an HTTPS proxy.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME = <i>proxy host name</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.29

SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT

Specifies the HTTP proxy port number to connect to the source database through an HTTPS proxy.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT = <i>proxy port number</i></code>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.30

SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL

Specifies the proxy protocol to connect to the source database through a proxy.

Parameter Relationships

The `SOURCEDATABASE_CONNECTIONDETAILS` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL = HTTP or HTTPS</code>
Default value	HTTP
Required	No
Modifiable on Resume	Yes

G.31 SOURCEDATABASE_ENVIRONMENT_DBTYPE

Indicates the type of database to migrate from the specified environment.

Parameter Relationships

The `SOURCEDATABASE_*` parameters specify connection details for the source database.

Property	Description
Syntax	SOURCEDATABASE_ENVIRONMENT_DBTYPE = <i>dbtypeValue</i>
Default value	ORACLE
Required	No
Modifiable on Resume	No

G.32 SOURCEDATABASE_ENVIRONMENT_NAME

Specifies the environment of the source database.

You can specify whether the source database environment is Oracle (ORACLE).

Parameter Relationships

The SOURCEDATABASE_* parameters specify connection details for the source database.

Property	Description
Syntax	SOURCEDATABASE_ENVIRONMENT_NAME = <i>nameValue</i>
Default value	ORACLE
Required	No
Modifiable on Resume	No

G.33 TARGETDATABASE_CONNECTIONDETAILS_HOST

Specifies the listener host name or IP address.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_HOST = <i>hostname_or_ip</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.34 TARGETDATABASE_CONNECTIONDETAILS_PORT

Specifies the listener port number.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_PORT = <i>listener port number</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.35

TARGETDATABASE_CONNECTIONDETAILS_SERVICENAME

Specifies the fully qualified service name.

You can specify any predefined fractional service alias available.

See also [Connecting to a DB System](#).

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_SERVICENAME = <i>service_name_or_alias</i>
Default value	There is no default value
Valid values	For non-Autonomous , specify the fully qualified service name.
Required	No
Modifiable on Resume	No

G.36 SOURCEDATABASE_CONNECTIONDETAILS_HOST

Specifies the source database listener host name or IP address. Required for all except `environment.name = ORACLE`. In case of Oracle RAC database, the scan name can be specified.

Parameter Relationships

The SOURCEDATABASE_* parameters specify connection details for the source database.

Property	Description
Syntax	SOURCEDATABASE_CONNECTIONDETAILS_HOST = <i>hostname_or_ip</i>
Default value	There is no default value
Required	Yes*
Modifiable on Resume	Yes

G.37 SOURCEDATABASE_CONNECTIONDETAILS_PORT

Specifies the source database listener port number. Required for all except `environment.name = ORACLE`.

Parameter Relationships

The `SOURCEDATABASE_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_PORT = listener port number</code>
Default value	There is no default value
Required	Yes*
Modifiable on Resume	Yes

G.38

SOURCEDATABASE_CONNECTIONDETAILS_SERVICENAME

Specifies the source database fully qualified service name. Required for all except `environment.name = ORACLE`.

Parameter Relationships

The `SOURCEDATABASE_*` parameters specify connection details for the source database.

Property	Description
Syntax	<code>SOURCEDATABASE_CONNECTIONDETAILS_SERVICENAME = service name</code>
Default value	There is no default value
Required	Yes*
Modifiable on Resume	No

G.39 TABLESPACEDETAILS_EXCLUDE

Specifies tablespaces to be excluded for automatic remap or automatic creation of tablespaces at target database during import of user schemas.

See Automatic Tablespace Creation for more information.

Example

```
TABLESPACEDETAILS_EXCLUDE=B2B_LOB_TS,B2B_HR_TS
```

Parameter Relationships

In a logical migration, the `TABLESPACEDETAILS_*` parameters specify details that allow Zero Downtime Migration to automatically create the required tablespaces at target database.

Property	Description
Syntax	TABLESPACEDETAILS_EXCLUDE= <i>tablespace_names</i>
Default value	By default SYSTEM, SYSAUX, and USERS tablespaces are excluded.
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED

G.40

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE

Specifies the identity file to access the bastion for bastion-based access to the target database.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IDENTITYFILE = <i>bastion_id_file</i>
Default value	There is no default value
Required	Not mandatory for migration jobs
Modifiable on Resume	Yes

G.41

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP

Specifies the IP address of the bastion host for bastion-based access to database.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_IP = <i>ip address</i>
Default value	There is no default value
Required	No

Property	Description
Modifiable on Resume	Yes

G.42

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT

Specifies the port number of the bastion host for bastion-based access to database.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_PORT = <i>port_number</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.43

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP

Specifies the remote host IP address to access from the bastion for bastion-based access to database.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_REMOTEHOSTIP = <i>ip_address</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.44

TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME

Specifies the user name to access the bastion for bastion-based access to database.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_BASTIONDETAILS_USERNAME = <i>username</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.45

TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME

Specifies the proxy host name for connecting to the target database through an HTTPS proxy.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_HOSTNAME = <i>proxy host name</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.46

TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT

Specifies the HTTP proxy port number for connecting to the source database through an HTTPS proxy.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PORT = <i>proxy port number</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Yes

G.47

TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL

Specifies the proxy protocol to connect to the target database through a proxy.

Parameter Relationships

The TARGETDATABASE_CONNECTIONDETAILS parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_CONNECTIONDETAILS_PROXYDETAILS_PROTOCOL = HTTP or HTTPS
Default value	HTTP
Required	No
Modifiable on Resume	Yes

G.48 TARGETDATABASE_DBTYPE

Specifies the target database type if OCID of the target database is not provided.

Parameter Relationships

The TARGETDATABASE_* parameters specify connection details for the target OCI database.

Property	Description
Syntax	TARGETDATABASE_DBTYPE = <i>dbtypeValue</i>
Default value	There is no default value The following values are supported: <ul style="list-style-type: none"> • <i>ORACLE</i> • <i>EXADATA</i> • <i>ODA</i>
Required	No
Modifiable on Resume	No

G.49 WALLET_DATAPUMPENCRYPTION

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, which is used to get the Data Pump encryption password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	WALLET_DATAPUMPENCRYPTION = <i>wallet_path</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED.

G.50 WALLET_SOURCEADMIN

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, which is used to get the source database administrative admin password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	WALLET_SOURCEADMIN = <i>wallet_path</i>
Default value	There is no default value
Range of value	Full path to the wallet.
Required	No
Modifiable on Resume	No

G.51 WALLET_TARGETADMIN

Specifies the absolute path to the directory that contains the auto login wallet file `cwallet.sso`, which is used to get the target database administrative admin password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_TARGETADMIN = wallet_path</code>
Default value	There is no default value
Required	No
Modifiable on Resume	Until <code>ZDM_PREPARE_DATAPUMP_SRC</code> phase is COMPLETED.

G.52 WALLET_TDEKEYSTORE

Specifies the absolute path location for wallet to be used for TDE keystore that contains the auto login wallet file `cwallet.sso` for specifying the source database TDE keystore password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	<code>WALLET_TDEKEYSTORE = wallet_path</code>
Default value	There is no default value
Range of value	Full path to the wallet.
Required	No
Modifiable on Resume	No

G.53 WALLET_TGTTDEKEYSTORE

Specifies the absolute path location for wallet to be used for the target TDE keystore that contains the auto login wallet file `cwallet.sso` for specifying the target database TDE keystore password.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The `WALLET_*` parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	WALLET_TGTTDEKEYSTORE = <i>wallet_path</i>
Default value	There is no default value
Range of value	Full path to the wallet.
Required	No
Modifiable on Resume	No

G.54 WALLET_USERACTION

Allows you to provide the auto login wallet path, which contains the username and its password which should run the useraction.

The path should be resolvable from the Zero Downtime Migration service host.

About the WALLET_* Parameters

The WALLET_* parameters specify the full path for the auto login wallet file on the Zero Downtime Migration service host.

Property	Description
Syntax	WALLET_USERACTION = <i>wallet_path</i>
Default value	There is no default value
Required	No
Modifiable on Resume	Until ZDM_PREPARE_DATAPUMP_SRC phase is COMPLETED.

H

Zero Downtime Migration ZDMCLI Command Reference

ZDMCLI is the command line interface for Zero Downtime Migration migration operations.

To run ZDMCLI commands, go to the `/bin` directory in the Zero Downtime Migration software home and enter one of the commands listed in the topics below. For example:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database
```

To list help pages for any ZDMCLI command use the `-help` option. The following command lists the help for all of the ZDMCLI commands.

```
zdmuser> $ZDM_HOME/bin/zdmcli -help
```

To get the current release information for your Zero Downtime Migration software, run ZDMCLI with the `-build` option.

```
zdmuser> $ZDM_HOME/bin/zdmcli -build
```

The following topics describe the Zero Downtime Migration ZDMCLI command usage and options.

H.1 ZDMCLI Options

You can run options on ZDMCLI without specifying a command.

Syntax

```
$ZDM_HOME/bin/zdmcli -option
```

Options

Table H-1 ZDMCLI Options

Option	Description
-build	Returns Zero Downtime Migration version information, including Cloud Premigration Advisor version.

H.2 abort job

Terminates the specified job, if running.

Syntax

```
$ZDM_HOME/bin/zdmcli abort job  
-jobid job_id
```

Options

Table H-2 ZDMCLI abort job Options

Option	Description
-jobid <i>job_id</i>	Unique job ID value (integer) for the scheduled job. The job ID is assigned when the job is scheduled.

H.3 add imagetype

Configures a new image type of the specified name and its associated user actions.

Syntax

```
$ZDM_HOME/bin/zdmcli add imagetype  
-imagetype image_type  
-basetype CUSTOM_PLUGIN  
[-useractions user_action_list]
```

Options

Table H-3 ZDMCLI add imagetype Options

Option	Description
-imagetype <i>image_type</i>	Name of the image type to be created
-basetype CUSTOM_PLUGIN	The base image type for which the image type is created. Note that CUSTOM_PLUGIN is the only valid value for this mandatory argument.
-useractions <i>user_action_list</i>	Comma-separated list of user action names

H.4 add useraction

Configures a new user action of the specified name with its associated script and action file.

Syntax

```
$ZDM_HOME/bin/zdmcli add useraction  
-useraction user_action_name  
-actions script script_name  
[-actionfile file_name]  
{-pre | -post}  
-optype MIGRATE_DATABASE  
[-phase operation_phase]
```

```

[-onerror {ABORT | CONTINUE}]
[-runscope
  {ONENODE |
   ALLNODES |
   AUTO}]
[-outputfrom useraction_names]
-asuser db_user

```

Options

Table H-4 ZDMCLI add useraction Options

Option	Description
-useraction <i>user_action_name</i>	Name of the user action
-actionscript <i>script_name</i>	Script file to be run
-actionfile <i>file_name</i>	File associated with and needed by the user action
-pre	Runs the user action before the operation
-post	Runs the user action after the operation
-optype MIGRATE_DATABASE	Defines the operation for which the user action is configured as MIGRATE_DATABASE.
-phase <i>phase_of_operation</i>	Migration operation phase for which the user action is configured
-onerror {ABORT CONTINUE}	The response if the user action encounters an error during execution
-runscope {ONENODE ALLNODES AUTO}	The servers on which the user action is run. Specify <i>AUTO</i> to choose the run scope based on the other command options.
-outputfrom <i>useraction_names</i>	Comma-separated list of user action names whose output is to be supplied to the current user action.
-asuser <i>db_user</i>	Specify the database user to run SQL commands in the user action. See WALLET_USERACTION for specifying the password required for processing user action as the specified user.

Examples

For more examples, see Registering User Actions.

H.5 migrate database

Performs a migration of a database to the Oracle Cloud.

Syntax

```

$ZDM_HOME/bin/zdmcli migrate database
[-sourcedb source_db_unique_name_value |
 -sourcesid source_oracle_sid]
-rsp zdm_template_path
-sourcenode source_host_name
-targetnode target_host_name
[-targethome target_home]

```

```

[-eval]
[-tdekeystorepasswd
    [-tgttdekeystorepasswd]]
[-tdemasterkey]
[-useractiondata user_action_data]
[-imagetype]
[-backupuser user_name
    [-restoreuser user_name]]
[-backuppasswd]
[-dvowner database_vault_owner]
[-tdewallet wallet_path
    [-tgttdewallet wallet_path]]
[-tdekeystorewallet tde_wallet_path
    [-tgttdekeystorewallet tde_wallet_path]]
[-sourcesyswallet sys_wallet_path]
[-osswallet oss_wallet_path
    [-ossrestorewallet oss_restore_wallet_path]]
[-dvwallet dv_wallet_path]
[-backupwallet backup_wallet_path]
[{-srcroot |
    -srccred cred_name |
    -srcuser user_name |
    {-srcsudouser sudo_user_name -srcsudopath sudo_binary_path} |
    {-srcauth plugin_name
        [-srcarg1 user:source_database_server_login_user_name
            -srcarg2
identity_file:ZDM_installed_user_private_key_file_location
            -srcarg3 sudo_location:sudo_location]}}}
    {-tgtroot |
        -tgtcred cred_name |
        -tgtuser user_name |
        {-tgtsudouser sudo_user_name -tgtsudopath sudo_binary_path} |
        {-tgtauth plugin_name
            [-tgtarg1 user:target_database_server_login_user_name
                -tgtarg2
identity_file:ZDM_installed_user_private_key_file_location
                -tgtarg3 sudo_location:sudo_location]}}}
    [-schedule {timer_value | NOW}]
    [-pauseafter phase]
    [-stopafter phase]
    [-listphases]
    [-ignoremissingpatches patch_name
        [,patch_name...]]
[-ignore
    [ALL]
    [,WARNING]
    [,PATCH_CHECK]
    [,NLS_CHECK]
    [,NLS_NCHAR_CHECK]
    [,ENDIAN_CHECK]
    [,VAULT_CHECK]
    [,DB_NK_CACHE_SIZE_CHECK]]]
[-incrementalinterval timer_minutes]
[-advisor |
    -ignoreadvisor |
    -skipadvisor]

```

```
[-genfixup {YES | NO}
[-srccred src_dbuser_wallet
[-tgtcred tgt_db_user_wallet]
```

Options

Table H-5 ZDMCLI migrate database Options

Option	Description
-advisor	Similar to -eval, migrate database will run the minimum phases required for exclusively running Cloud Premigration Advisor Tool (CPAT) on the migration job, without actually running the migration job against the source and target
-ignoreadvisor	Runs Cloud Premigration Advisor Tool (CPAT), but ignores errors generated by CPAT.
-skipadvisor	Skips the CPAT phase of the migration job
-backuppasswd <i>password</i>	In a physical migration, allows you to <ol style="list-style-type: none"> 1. Create an RMAN backup with provided backup password 2. Use an existing RMAN backup with backup password authentication
-backupuser <i>user_name</i>	Name of the user allowed to back up or restore the database
-restoreuser <i>user_name</i>	Name of the user allowed to restore the database
-backupwallet <i>backup_wallet_path</i>	Full path for the auto-login wallet file on the Zero Downtime Migration host containing the RMAN backup password
-dvwallet <i>dv_wallet_path</i>	Full path for the auto-login wallet file on the Zero Downtime Migration host, containing the credential for the Oracle Database Vault owner
-osswallet <i>oss_wallet_path</i>	Full path for the auto-login wallet file on the Zero Downtime Migration host containing the credential for the Object Storage Service (OSS) backup user
-ossrestorewallet <i>oss_restore_wallet_path</i>	Full path for the auto-login wallet file on the Zero Downtime Migration host containing the credential for the Object Storage Service (OSS) restore backup user
-sourcesyswallet <i>sys_wallet_path</i>	Full path for the auto-login wallet file on the Zero Downtime Migration host containing the SYS password of the source database
-tdewallet <i>wallet_path</i>	Full path for the auto-login wallet file on the Zero Downtime Migration host containing the Transparent Data Encryption (TDE) keystore password

Table H-5 (Cont.) ZDMCLI migrate database Options

Option	Description
<code>-tgttdewallet wallet_path</code>	Full path for the auto-login wallet file on the Zero Downtime Migration host containing target container database Transparent Data Encryption (TDE) keystore password If you are converting a non-multitenant source database to a multitenant architecture on the target, that is a pluggable database (PDB), then you can also create an auto-login wallet for the target container database (CDB) TDE keystore password.
<code>-dvowner database_vault_owner</code>	Name of the Oracle Database Vault owner allowed to grant or revoke SYS privileges
<code>-eval</code>	Evaluates the migration job without actually running the migration job against the source and target
<code>-genfixup {YES NO}</code>	Displays remedial scripts for failing checks when a migration is run with Cloud Premigration Advisor Tool (CPAT) enabled. Any remedies that can be run automatically on the source database are run. See Cloud Premigration Advisor Tool Support for CPAT use cases supported by Zero Downtime Migration.
<code>-ignore [ALL][,WARNING][,PATCH_CHECK][,NLS_CHECK][,NLS_NCHAR_CHECK][,ENDIAN_CHECK][,VAULT_CHECK][,DB_NK_CACHE_SIZE_CHECK]</code>	Ignore all checks or specific type of checks: ALL - ignore all checks WARNING - ignore checks with warning status PATCH_CHECK - patch level should be the same NLS_CHECK - source and target database NLS should be same NLS_NCHAR_CHECK - source and target database NLS NCHAR should be same NLS_NCHAR - source and target database NLS should be same ENDIAN_CHECK - source and target database Endian should be same VAULT_CHECK - vault enabled should be consistent for source and target DB_NK_CACHE_SIZE_CHECK - set DB_NK_CACHE_SIZE in the target database if it is set in the source database.
<code>-ignoremissingpatches</code>	Proceeds with the migration even though the specified patches, which are present in the source path or working copy, might be missing from the destination path or working copy
<code>-imagetype image_type</code>	Name of the user action imagetype
<code>-incrementalinterval timer_minutes</code>	Run periodic incremental RMAN backup every interval (in minutes)
<code>-listphases</code>	Lists the phases for the migration job
<code>-pauseafter phase</code>	Pause the job after running the specified phase

Table H-5 (Cont.) ZDMCLI migrate database Options

Option	Description
<code>-rsp zdm_template_path</code>	Location of the Zero Downtime Migration response file
<code>-schedule timer_value</code>	Scheduled time to run the migration, in ISO-8601 format. For example, 2016-12-21T19:13:17+05
<code>-sourcedb source_db_unique_name_value</code>	The <code>-sourcedb</code> parameter in Oracle Zero Downtime Migration (ZDM) specifies the unique database name that is used to manage the Clusterware configuration for the source database. Important: Use this unique name to identify the database in the Clusterware environment. Do not use the <code>db_unique_name</code> which is set in the database's initialization parameters (<code>init.ora</code> file).
<code>-sourcenode source_host_name</code>	Host on which the source database is running.
<code>-sourcesid source_oracle_sid</code>	ORACLE_SID of the source single instance database without Grid Infrastructure

Note

This must be a primary database.

Table H-5 (Cont.) ZDMCLI migrate database Options

Option	Description
<code>-srcauth plug-in_name [plug-in_args]-srcauth sudoasuser</code>	<p>Use the <code>zdmauth</code> or <code>dbuser</code> authentication plug-in to access the source database server, and enter the following arguments:</p> <pre> -srcarg1 user:source_database_server_login_use r_name -srcarg2 identity_file:ZDM_installed_user_priv ate_key_file_location -srcarg3 sudo_location:sudo_location </pre> <p>If you do not specify the <code>sudo</code> location, the default (<code>/usr/bin/sudo</code>) is used by Zero Downtime Migration.</p> <p><code>zdmauth</code> plugin can receive the parameter: <code>-srcarg14 ssh_port=<port_number></code> to use a different port number instead of the default SSH port number specified in the <code>rhpf.pref</code> file.</p> <p>The <code>sudoasuser</code> plugin can receive the parameter: <code>-srcarg15 ssh_port=<port_number></code> to use a different port number instead of the default SSH port number specified in the <code>rhpf.pref</code> file.</p> <p>See <i>Migrating with Database User Privileges</i> for more information about <code>dbuser</code> authentication.</p> <p>Perform super user operations as <code>sudoasuser</code> user name on the source database server.</p>
<code>-srccred cred_name</code>	Credential name with which to associate the user name and password credentials to access the source database server
<code>-srcroot</code>	Directs Zero Downtime Migration to use <code>root</code> credentials to access the source database server
<code>-srcsudopath sudo_binary_path</code>	Location of <code>sudo</code> binary on the source database server
<code>-srcsudouser user_name</code>	Perform super user operations as <code>sudo</code> user name on the source database server
<code>-srcuser user_name</code>	Name of the privileged user performing operations on the source database server

Table H-5 (Cont.) ZDMCLI migrate database Options

Option	Description
<code>-stopafter phase</code>	<p>Truncates the work flow by the specified phase, and upon completion of the specified phase, the migration job is marked with status completed.</p> <p>There is no option to resume the job beyond this phase.</p> <p>For example, if you intend to stop the work flow after Data Guard setup, then specifying <code>-stopafter ZDM_CONFIGURE_DG_SRC</code> stops the job at this phase and the job is marked completed once the <code>ZDM_CONFIGURE_DG_SRC</code> is completed successfully.</p>
<code>-targethome target_home</code>	Location of the target database <code>ORACLE_HOME</code>
<code>-targetnode target_host_name</code>	Target server to which the source database is migrated
<code>-tdekeystorepasswd</code>	Transparent Data Encryption (TDE) keystore password, required for password-based keystore or wallet
<code>-tdekeystorewallet tde_wallet_path</code>	Full path for the auto-login wallet file on the Zero Downtime Migration host containing the Transparent Data Encryption (TDE) keystore password
<code>-tdemasterkey</code>	Transparent Data Encryption (TDE) master encryption key
<code>-tgtauth plugin_name [plugin_args]-tgtauth sudoasuser</code>	<p>Use the <code>zdmauth</code> authentication plug-in to access the target database server, and enter the following arguments:</p> <pre> -tgtarg1 user:target_database_server_login_use r_name -tgtarg2 identity_file:ZDM_installed_user_priv ate_key_file_location -tgtarg3 sudo_location:sudo_location </pre> <p>If you do not specify the sudo location the default (<code>/usr/bin/sudo</code>) is used by Zero Downtime Migration.</p> <p><code>zdmauth</code> plugin can receive the parameter: <code>-tgtarg14 ssh_port=<port_number></code> to use a different port number instead of the default SSH port number specified in the <code>rhpf.pref</code> file.</p> <p>The <code>sudoasuser</code> plugin can receive the parameter: <code>-tgtarg15 ssh_port=<port_number></code> to use a different port number instead of the default SSH port number specified in the <code>rhpf.pref</code> file.</p> <p>Name of the <code>sudoasuser</code> performing operations on the target database server.</p>

Table H-5 (Cont.) ZDMCLI migrate database Options

Option	Description
<code>-tgtcred cred_name</code>	Credential name with which to associate the user name and password credentials to access the target database server
<code>-tgtroot</code>	Use root credentials to access the target database server
<code>-tgtsudopath sudo_binary_path</code>	Location of the sudo binary on the target database server
<code>-tgtsudouser user_name</code>	Perform super user operations as sudo user name on the target database server
<code>-tgttdekeystorepasswd</code>	Target container database TDE keystore password
<code>-tgttdekeystorewallet tde_wallet_path</code>	Full path for the auto-login wallet file on the Zero Downtime Migration host that contains the target TDE keystore password
<code>-tgtuser user_name</code>	Name of the user performing operations on the target database server
<code>-useractiondata user_action_data</code>	Value to be passed to <i>useractiondata</i> parameter of the user action script
<code>-srccred <src_dbuser_wallet></code>	Used for root user and sudo user to make connections to the source node.
<code>-tgtcred <tgt_db_user_wallet></code>	Used for root user and sudo user to make connections to the target node.

Examples

ZDMCLI migrate database options for an Autonomous Database migration:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database -rsp file_path -sourcenode host
-srcauth zdmauth -srcarg1 user:username -srcarg2 identity_file:ssh_key_path
-srcarg3 sudo_location:sudo_path -eval [-advisor [-ignoreadvisor] | -
skipadvisor]]
```

ZDMCLI migrate database options for a co-managed database migration:

```
zdmuser> $ZDM_HOME/bin/zdmcli migrate database -rsp file_path -sourcenode host
-srcauth zdmauth -srcarg1 user:username -srcarg2 identity_file:ssh_key_path
-srcarg3 sudo_location:sudo_path -targetnode host -tgtauth zdmauth
-tgtarg1 user:username -tgtarg2 identity_file:ssh_key_path
-tgtarg3 sudo_location:sudo_path -eval [-advisor [-ignoreadvisor] | -
skipadvisor]]
```

H.6 modify imagetype

Modifies the list of user actions associated with the specified image type.

Syntax

```
$ZDM_HOME/bin/zdmcli modify imagetype
  -imagetype image_type_name
  -useractions user_action_list
```

Options

Table H-6 ZDMCLI modify imagetype Options

Option	Description
<code>-imagetype <i>image_type</i></code>	Name of the image type to be modified
<code>-useractions <i>user_action_list</i></code>	Comma-separated list of user actions that you want to associate with the image type, for example: <code>-useractions userAction1, userAction2</code>

H.7 modify job

Allows you to modify the Oracle GoldenGate Extract and Replicat parameters of a running migration job.

Syntax

```
zdmuser> $ZDM_HOME/bin/zdmcli modify job
  -jobid job_id
  -rsp response_file_path
```

Options

Table H-7 ZDMCLI modify job Options

Option	Description
<code>-jobid <i>job_id</i></code>	Unique job ID value (integer) for the scheduled migration job The job ID is assigned when the migration job is scheduled.
<code>-rsp <i>response_file_path</i></code>	Location of the Zero Downtime Migration response file

H.8 modify useraction

Modifies the configuration of the user action with the specified name.

Syntax

```
$ZDM_HOME/bin/zdmcli modify useraction
  -useraction user_action_name
  [-actionsript script_name]
  [-actionfile file_name]
```

```

[-pre | -post]
[-optype MIGRATE_DATABASE]
[-phase phase]
[-onerror {ABORT | CONTINUE}]
[-runscope
    {ONENODE |
     ALLNODES |
     AUTO}]
[-outputfrom useraction_names]

```

Options

Table H-8 ZDMCLI modify useraction Options

Option	Description
-useraction <i>user_action_name</i>	Name of the user action
-actionscript <i>script_name</i>	Script file to be run
-actionfile <i>file_name</i>	Accompanying file needed by the user action
-pre	Runs the user action before the operation
-post	Runs the user action after the operation
-optype MIGRATE_DATABASE	Defines the operation for which the user action is configured as MIGRATE_DATABASE
-onerror {ABORT CONTINUE}	Defines whether to stop or continue running if an error occurs while the user action is running
-runscope {ONENODE ALLNODES AUTO}	The servers where the user action will be run. Specify <i>AUTO</i> to choose the run scope based on the other command options.
-outputfrom <i>useraction_names</i>	Comma-separated list of user action names whose output is to be supplied to the current user action.

H.9 query audit

Displays the migration job audit records.

Syntax

```

$ZDM_HOME/bin/zdmcli query audit
[[ [-operation
    { add |
      abort |
      modify |
      migrate |
      grant |
      revoke |
      query |
      resume |
      suspend }]]
  [-entity
    { client |
      role |
      database |

```

```

        user |
        audit |
        imagetype |
        useraction}} |
        [-user user_name]
[-client client_name] |
        [-from timestamp -to timestamp] |
-before timestamp |
-since timestamp |
-first number |
-last number] |
-record record_id |
-config]

```

Options

Table H-9 ZDMCLI query audit Options

Option	Description
-operation { add abort modify migrate grant revoke query resume suspend }	The operation type for which to display audit records
-entity { client role database user audit imagetype useraction }	The entity for which to display audit records
-user user_name	Name of the user who ran the migration operations
-client client_name	Client cluster name where migration operations were executed
-from timestamp	Date for getting a range of audit records, in the format YYYY-MM-DD.
-to timestamp	Date for getting a range of audit records, in the format YYYY-MM-DD
-since timestamp	Date to get audit records since the date provided, in the format YYYY-MM-DD
-before timestamp	Date to get audit records before the date provided, in the format YYYY-MM-DD
-first number	First number of audit records to get from the query
-last number	Last number of audit records to get from the query
-record record_ID	Audit record ID
-config	Show maximum record configuration

H.10 query job

Gets the current status of scheduled migration jobs.

Syntax

```

$ZDM_HOME/bin/zdmcli query job
  [-jobid job_id]
  [-jobtype]]
  [-sourcenode source_host_name]

```

```

        [-sourcedb db_name |
        -sourcesid sid]]
[-targetnode target_host_name]
[-latest]
[-eval |
-migrate]
[-status
    {SCHEDULED |
    EXECUTING |
    UNKNOWN |
    TERMINATED |
    FAILED |
    SUCCEEDED |
    PAUSED |
    ABORTED}]
[-phase]
[-dbname database_name]
[-since timer_value]
[-upto timer_value]
[-brief]
[-statusonly]

```

Options

Table H-10 ZDMCLI query job Options

Option	Description
-jobid <i>job_id</i>	Unique job ID value (integer) for the scheduled migration job The job ID is assigned when the migration job is scheduled.
-job_type	Returns the type of the scheduled job
-sourcenode <i>source_host_name</i>	Server on which the source database is running
-sourcedb <i>db_name</i>	Name of the source database to be migrated
-sourcesid <i>sid</i>	The ORACLE_SID of the source single instance database without Grid Infrastructure
-targetnode <i>target_host_name</i>	Target server to which the database is migrated
-latest	Returns the most recent job that matches the given criteria
-eval	Returns evaluation jobs only
-migrate	Returns migration jobs only
-status {SCHEDULED EXECUTING UNKNOWN TERMINATED FAILED SUCCEEDED PAUSED ABORTED}	Returns jobs that match the specified job status

Table H-10 (Cont.) ZDMCLI query job Options

Option	Description
-phase	Returns the status of the given phase. If the phase supplied by the user is invalid, the query returns an error. <pre>./zdmcli query job -jobid 33 -phase ZDM_PREUSERACTIONS_TGT -statusonly # exmaple.com: Audit ID: 153 # Job ID: 33 # ZDM_PREUSERACTIONS_TGT:PENDING</pre>
-dbname <i>unique_db_name</i>	Specifies the database DB_UNIQUE_NAME value
-since <i>timer_value</i>	Date from which to get the jobs, in ISO-8601 format. For example: 2016-12-21T19:13:17+05
-upto <i>timer_value</i>	Upper limit time to which to get the jobs, in ISO-8601 format. For example: 2016-12-21T19:13:17+05
-brief	Returns job details summary only
-statusonly	Returns only the job status and current phase name

Usage Notes

To identify if the current run is a resumption of a PAUSED migration job, a restart of a FAILED migration job, or a fresh start for a migration job, use the following options:

- `zdmcli query job -latest` gets the latest job without considering the `job_type`
- `zdmcli query job -latest -migrate` gets the latest non-evaluation migration job
- `zdmcli query job -latest -eval` get the latest evaluation migration job

The `zdmcli query job` reports Oracle GoldenGate replication metrics for online logical migration. If a job has completed the phase `ZDM_CREATE_GG_EXTRACT_SRC` but not the phase `ZDM_START_GG_REPLICAT_TGT`, then `zdmcli query job` reports only the following metrics: -

- Extract status (Running, Abended, and so on.)
- Extract write checkpoint (number of trail files generated)

If a job has completed both `ZDM_CREATE_GG_EXTRACT_SRC` and `ZDM_START_GG_REPLICAT_TGT` phases, then `zdmcli query job` reports the following metrics: -

- Extract status (Running, Abended, and so on).
- Extract write checkpoint (number of trail files generated)
- Replicat status (Running, Abended, and so on).
- Replicat read checkpoint (number of trail files applied)
- End-to-end heartbeat lag (in seconds)

- Replication throughput (in GBph)

```
Oracle GoldenGate replication metrics:
Extract "EXTABC" status: Running
Extract "EXTABC" trail files generated: 2
Replicat "REPDE" status: Running
Replicat "REPDE" trail files applied: 1
End-to-end heartbeat lag: 600 seconds
Replication throughput: 1.0 GBph
```

H.11 query useraction

Displays the configuration of a user action.

Syntax

```
$ZDM_HOME/bin/zdmcli query useraction
    [-useraction user_action_name | -imagetype image_type
    [-optype MIGRATE_DATABASE]]
```

Options

Table H-11 ZDMCLI query useraction Options

Option	Description
-useraction <i>user_action_name</i>	Name of the user action
-imagetype <i>image_type</i>	Specify the image type name
-optype MIGRATE_DATABASE	Operation for which the user action is configured

H.12 resume job

Resumes a specified job that was paused.

Syntax

```
$ZDM_HOME/bin/zdmcli resume job
    -jobid job_id
    [-pauseafter pause_phase |
    -rsp zdm_logical_template_path]
    [-rerun {BACKUP|RESTORE}]
    [ -ignore
    {IMPORT_ERRORS | EXPORT_ERRORS}]
    [ -skip
    {SWITCHOVER |
    UPGRADE |
    DG_CONFIG |
    DG_CONFIG_STBY} ]
```

Options

Table H-12 ZDMCLI resume job Options

Option	Description
<code>-jobid job_id</code>	Unique job ID value (integer) for the scheduled job The job ID is assigned when the migration job is scheduled.
<code>-pauseafter pause_phase</code>	Pauses the migration job after running the specified phase
<code>-rerun {BACKUP RESTORE}</code>	In a physical migration, you can choose to rerun RMAN backup or restore operations on resume. BACKUP causes Zero Downtime Migration to re-run phases starting from the ZDM_BACKUP_INCREMENTAL_SRC phase. As part of the re-run of the backup phase, an RMAN crosscheck is first run to ensure that the source controlfile is consistent with any backups present on the backup media. RESTORE triggers rerun of the restore-related phases which includes dropping the existing target database, restoring spfile, restoring controlfile and datafiles. See the Usage Notes below for more information.
<code>-rsp zdm_logical_template_path</code>	Specify the migration response file if you modified any parameters to be picked up by Zero Downtime Migration on resume. This option can only be used with logical migration jobs.
<code>-ignore {IMPORT_ERRORS EXPORT_ERRORS}</code>	Ignores the Data Pump errors in the latest phase executed. Specifying this on resume of FAILED job lets the job to proceed to next action in the respective phase and further proceed to follow-on phases in the job without re-executing Data Pump action. The phase status that FAILED is marked with status IGNORED_ON_FAILURE. <code>-ignore EXPORT_ERRORS</code> ignores all error seen in Data Pump export and ZDM job proceeds to the next workflow actions. <code>-ignore IMPORT_ERRORS</code> ignores all error seen in Data Pump import and ZDM job proceeds to the next workflow actions.

Table H-12 (Cont.) ZDMCLI resume job Options

Option	Description
<code>-skip {SWITCHOVER UPGRADE DG_CONFIG DG_CONFIG_STBY}</code>	<p>Resumes the job after the switchover has been performed from outside of ZDM.</p> <p>When ZDM resume job is started with this option, ZDM does not throw an error when the role of the source database is not PRIMARY and/or the role of the target database is not STANDBY.</p> <div data-bbox="1148 552 1271 585" data-label="Section-Header"> <p>Note</p> </div> <p>If the role switchover of the source and target database is successful, the job continues.</p>
	<p>Resumes the job after the UPGRADE has been performed from outside of ZDM or when you want to skip the UPGRADE operation. When the ZDM resumes, job is started with this option. ZDM does not perform UPGRADE operation on resume. Following values are available:</p> <ul style="list-style-type: none"> • <code>-skip DG_CONFIG</code>: Skips Data Guard configuration between the source and target databases. • <code>-skip DG_CONFIG_STBY</code>: Skips Data Guard configuration for target standby database (Disaster Recovery case).

Usage Notes

See Resume a Migration Job

The `-rerun {BACKUP|RESTORE}` option which enables the phase rerun provides you an option to retry backup or restore procedures on failure. You might use this option if

- Backups are accidentally deleted before the restore is attempted/completed.
- The TDE wallet is changed after Zero Downtime Migration has already copied the wallet to the target, so the differential backup source would encrypt the backup with the new wallet but the incremental restore will fail because the target will not have the latest wallet. In this case using `-rerun` will trigger a re-copy of the wallet and subsequently rerun of restore including dropping and recreating the target.

H.13 suspend job

Suspends the specified job if running. Executing `suspend job` stops the ongoing job at the current work flow phase and allows jobs to be resumed later.

Syntax

```
$ZDM_HOME/bin/zdmcli suspend job
  -jobid job_id
```

Options

Table H-13 ZDMCLI suspend job Options

Option	Description
-jobid <i>job_id</i>	Unique job ID value (integer) The job ID number is assigned when the migration job is scheduled.

H.14 delete job

Deletes the specified job or jobs from the repository.

Syntax

```
$ZDM_HOME/bin/zdmcli delete job -help
{ -jobids <job_ids>
  -status
    {SCHEDULED |
     EXECUTING |
     UNKNOWN |
     TERMINATED |
     FAILED |
     SUCCEEDED |
     PAUSED |
     ABORTED} }
  [-force]
  [-verbose]

  -jobids <jobs_ids> Comma separated list of one or more jobs to be deleted
  -status {SCHEDULED | EXECUTING | UNKNOWN | TERMINATED | FAILED | SUCCEEDED |
  PAUSED | ABORTED}
                                     Job status for which to get the jobs.
  -force Forcibly delete the parent job and make all its child jobs independent
  -verbose Include additional information
```

Options

Table H-14 ZDMCLI delete job Options

Option	Description
-jobids <i>job_ids</i>	Comma separated list of one or more jobs to be deleted.

H.15 delete useraction

Deletes the specified user action.

Syntax

```
$ZDM_HOME/bin/zdmcli delete useraction  
-useraction user_action_name
```

Options

Table H-15 ZDMCLI delete useraction Options

Option	Description
-useraction <i>user_action_name</i>	Name of the user action.

H.16 delete imagetype

Deletes an existing image type.

Syntax

```
$ZDM_HOME/bin/zdmcli delete imagetype  
-imagetype image_type
```

Options

Table H-16 ZDMCLI delete useraction Options

Option	Description
-imagetype <i>image_type</i>	<p>Name of the image type to be deleted. For a custom image type, use the image type name.</p> <p>The following options are available:</p> <ul style="list-style-type: none">• ORACLEDBSOFTWARE (default) for Oracle Database software• ORACLEGISoftware for Oracle Grid Infrastructure software• ORACLEGGSoftware for Oracle GoldenGate software• LINUXOS for Oracle Linux Operating System• SOFTWARE for all other software

Setting Up SSH Key Based Authentication

① Note

These steps are applicable for physical, logical, and hybrid migrations where either the source and/or target are accessed using SSH keys (co-managed databases). These steps are **not applicable** for logical migration where the target is Autonomous Database.

Complete the following procedure to ensure the required connectivity between the Zero Downtime Migration service host and the source and target database servers.

1. On the Zero Downtime Migration service host, verify that the RSA authentication key pairs are available without a passphrase for the Zero Downtime Migration software installed user.

If a new key pair must be generated without the passphrase, then, as a Zero Downtime Migration software installed user, generate new key pairs as described in [Generate SSH Keys Without a Passphrase](#).

2. Rename the private key file.

Rename the `zdm_installed_user_home/.ssh/id_rsa` file name to `zdm_installed_user_home/.ssh/zdm_service_host.ppk`.

3. Add the contents of the `zdm_installed_user_home/.ssh/id_rsa.pub` file to the `opc_user_home/.ssh/authorized_keys` file, with the following dependencies:

For the source database server:

- If the source database server is accessed with the root user, then no action is required.
- If the source database server is accessed through SSH, then add the contents of the `zdm_installed_user_home/.ssh/id_rsa.pub` file into the `opc_user_home/.ssh/authorized_keys` file on all of the source database servers.

For the target database server:

- Because the target database server is on cloud only and access is through SSH, add the contents of the `zdm_installed_user_home/.ssh/id_rsa.pub` file into the `opc_user_home/.ssh/authorized_keys` file on *all* of the target database servers.

Note that the `opc` user is a standard Oracle cloud user that is used to access database servers, but you can use any privileged user that has `sudo` privileges. You can also use different users for the source and target databases.

4. Make sure that the source and target database server names are resolvable from the Zero Downtime Migration service host through either resolving name servers or alternate ways approved by your IT infrastructure.

One method of resolving source and target database server names is to add the source and target database server names and IP address details to the Zero Downtime Migration service host `/etc/hosts` file.

In the following example, the IP address entries are shown as 192.x.x.x, but you must add your actual public IP addresses.

```
#OCI public IP two node RAC server details
192.0.2.1 ocidb1
192.0.2.2 ocidb2
#OCIC public IP two node RAC server details
192.0.2.3 ocicdb1
192.0.2.4 ocicdb2
```

Optionally, Zero Downtime Migration allows connectivity through bastion hosts for both logical and physical migrations.

5. Make certain that port 22 in the source and target database servers accept incoming connections from the Zero Downtime Migration service host.
6. Test the connectivity from the Zero Downtime Migration service host to all source and target database servers.

```
zdmuser> ssh -i zdm_service_host_private_key_file_location user@source/
target_database_server_name
```

For example,

```
zdmuser> ssh -i /home/zdmuser/.ssh/zdm_service_host.ppk opc@ocidb1
zdmuser> ssh -i /home/zdmuser/.ssh/zdm_service_host.ppk opc@ocicdb1
```

Note

SSH connectivity during Zero Downtime Migration operations requires direct, non-interactive access between the Zero Downtime Migration service host and the source and target database servers without the need to enter a passphrase.

7. Disable TTY and verify that it is disabled for the SSH privileged user.

TTY needs to be turned off so that Zero Downtime Migration can run commands on the remote hosts non-interactively.

Because there are many ways to set sudo privileges, there are many ways to disable TTY for the `zdmuser`. As an example, you could set the following default in `/etc/sudoers` file.

```
Defaults:zdmuser !requiretty
```

Run the following command to verify that TTY is disabled:

```
ssh -i zdm_service_host_private_key_file_location
user@source_database/target_database_server_name
"sudo_location_source/target_database /bin/sh -c date"
```

If TTY is disabled, the command above returns the date from the remote host without any errors.

Optionally, if SSH is configured to require TTY, the output shows an error, such as the following:

```
[opc@zdm-server ~]$ ssh -i /home/zdmuser/.ssh/zdm_service_host.ppk  
opc@ocidbl  
    "/usr/bin/sudo /bin/sh -c date"  
  
sudo: sorry, you must have a tty to run sudo
```

Note

Usage of `sudo` is optional here.

Zero Downtime Migration Port Requirements

I.1 Generate SSH Keys Without a Passphrase

You can generate a new SSH key without a passphrase if on the Zero Downtime Migration service host the authentication key pairs are not available without a passphrase for the Zero Downtime Migration software installed user.

Note

Currently, only the RSA key format is supported for configuring SSH connectivity, so use the `ssh-keygen` command, which generates both of the authentication key pairs (public and private).

The following example shows you how to generate an SSH key pair for the Zero Downtime Migration software installed user. You can also use this command to generate the SSH key pair for the `opc` user.

Run the following command on the Zero Downtime Migration service host.

```
zdmuser> ssh-keygen -m PEM -b 2048 -t rsa
Generating public/private rsa key pair.
Enter file in which to save the key (/home/zdmuser/.ssh/id_rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in /home/zdmuser/.ssh/id_rsa.
Your public key has been saved in /home/zdmuser/.ssh/id_rsa.pub.
The key fingerprint is:
c7:ed:fa:2c:5b:bb:91:4b:73:93:c1:33:3f:23:3b:30 zdmuser@zdm_service_host
The key's randomart image is:
+--[ RSA 2048 ]-----+
|
|
|
|
|
|
|
|
|
|
|
|
|
|
|
|
```



```

      S o . = |
      . E . * |
      X.+o. |
      . = B o . o |
      o+*o. |
+-----+

```

This command generates the `id_rsa` and `id_rsa.pub` files in the `zdmuser` home, for example, `/home/zdmuser/.ssh`.

I.2 Set up an SSH Tunnel for Online Physical Migration

If connectivity using SCAN and the SCAN port is not possible between the source and target database servers, set up an SSH tunnel from the source database server to the target database server.

The following procedure sets up an SSH tunnel on the source database servers for the root user. Note that this procedure amounts to setting up what may be considered a temporary channel. Using this connectivity option, you will not be able to synchronize between the target database and source database after switchover, and with this configuration you cannot fall back to the original source database.

Note

The following steps refer to Oracle Cloud Infrastructure, but are also applicable to Oracle Exadata Database Service on Cloud@Customer and Oracle Exadata Database Service on Dedicated Infrastructure.

1. Generate an SSH key file without a passphrase for the `opc` user on the target Oracle Cloud Infrastructure server, using the information in [Generate SSH Keys Without a Passphrase](#). If the target is an Oracle RAC database, then generate an SSH key file without a passphrase from the target Oracle RAC server specified in `-targetnode` argument.
2. Add the contents of the Oracle Cloud Infrastructure server `opc_user_home/.ssh/id_rsa.pub` file into the Oracle Cloud Infrastructure server `opc_user_home/.ssh/authorized_keys` file.
3. Copy the target Oracle Cloud Infrastructure server private SSH key file onto the source server in the `/root/.ssh/` directory. If the source is an Oracle RAC database, copy the file into all of the source servers.

For better manageability, keep the private SSH key file name the same as the target server name, and keep the `.ppk` extension. For example, `ocidb1.ppk` (where `ocidb1` is the target server name).

The file permissions should be similar to the following.

```

/root/.ssh>ls -l ocidb1.ppk
-rw----- 1 root root 1679 Oct 16 10:05 ocidb1.ppk

```

4. Put the following entries in the source server `/root/.ssh/config` file.

```

Host *
    ServerAliveInterval 10
    ServerAliveCountMax 2

Host OCI_server_name

```

```

HostName OCI_server_IP_address
IdentityFile Private_key_file_location
User OCI_user_login
ProxyCommand /usr/bin/nc -X connect -x proxy_name:proxy_port %h %p

```

Where

- *OCI_server_name* is the Oracle Cloud Infrastructure target database server name without the domain name. For an Oracle RAC database use the node specified for `-targetnode` without the domain name.
- *OCI_server_IP_address* is the Oracle Cloud Infrastructure target database server IP address. For an Oracle RAC database use the node specified for `-targetnode`.
- *Private_key_file_location* is the location of the private key file on the source database server, which you copied from the target database server in step 3 above.
- *OCI_user_login* is the OS user used to access the target database servers.
- *proxy_name* is the host name of the proxy server.
- *proxy_port* is the port of the proxy server.

Note

The ProxyCommand option is specified when using a proxy server for connectivity.

For example, after specifying the relevant values, the `/root/.ssh/config` file should be similar to the following.

```

Host *
    ServerAliveInterval 10
    ServerAliveCountMax 2

Host ocidb1
    HostName 192.0.2.1
    IdentityFile /root/.ssh/ocidb1.ppk
    User opc
    ProxyCommand /usr/bin/nc -X connect -x www-proxy.example.com:80 %h %p

```

The file permissions should be similar to the following.

```

/root/.ssh>ls -l config
-rw----- 1 root root 1679 Oct 16 10:05 config

```

In the above example, the Oracle Cloud Infrastructure server name is `ocidb1`, and the Oracle Cloud Infrastructure server public IP address is `192.0.2.1`.

If the source is an Oracle Cloud Infrastructure Classic server, the *proxy_name* is not required, so you can remove or comment the line starting with `ProxyCommand`.

If the source is an Oracle RAC database, then copy the same `/root/.ssh/config` file onto all of the source Oracle RAC database servers. This file will have the Oracle Cloud Infrastructure server name, Oracle Cloud Infrastructure server public IP address, and private key file location of first Oracle Cloud Infrastructure Oracle RAC server information configured.

5. Make sure that you can SSH to the first target Oracle Cloud Infrastructure server from the source server before you enable the SSH tunnel.

For an Oracle RAC database, test the connection from all of the source servers to the first target Oracle Cloud Interface server.

Using the private key:

```
[root@ocicdb1 ~] ssh -i /root/.ssh/ocidb1.ppk opc@ocidb1
Last login: Fri Dec 7 14:53:09 2018 from 192.0.2.3

[opc@ocidb1 ~]$
```

Note

SSH connectivity requires direct, non-interactive access between the source and target database servers, without the need to enter a passphrase.

6. Run the following command on the source server to enable the SSH tunnel.

```
ssh -f OCI_hostname_without_domain_name -L
ssh_tunnel_port_number:OCI_server_IP_address:OCI_server_listener_port -N
```

Where

- *OCI_hostname_without_domain_name* is the Oracle Cloud Infrastructure target database server name without a domain name. For an Oracle RAC database use the node specified for *-targetnode* without the domain name.
- *ssh_tunnel_port_number* is any available ephemeral port in the range (1024-65545). Make sure that the SSH tunnel port is not used by any other process in the server before using it.
- *OCI_server_listener_port* is the target database listener port number. The listener port must be open between the source database servers and Oracle Cloud Infrastructure target servers.
- *OCI_server_IP_address* is the IP address of the target database server. For a single instance database, specify the Oracle Cloud Infrastructure server IP address. For an Oracle RAC database, specify the Oracle Cloud Infrastructure scan name with the domain name. If the scan name with domain name is not resolvable or not working, then specify the IP address obtained using the `lsnrctl status` command output. For example,

```
Listening Endpoints Summary...
  (DESCRIPTION=(ADDRESS=(PROTOCOL=ipc)(KEY=LISTENER)))
  (DESCRIPTION=(ADDRESS=(PROTOCOL=tcp)(HOST=192.0.2.9)(PORT=1521)))
  (DESCRIPTION=(ADDRESS=(PROTOCOL=tcp)(HOST=192.0.2.10)(PORT=1521)))
```

The following is an example of the command run to enable the SSH tunnel.

```
[root@ocicdb1~]ssh -f ocidb1 -L 9000:192.0.2.9:1521 -N
```

For an Oracle RAC database, this step must be repeated on all of the source servers.

7. Test the SSH tunnel.

Log in to source server, switch to the `oracle` user and source the database environment, and run the following command.

```
tnsping localhost:ssh_tunnel_port
```

For example,

```
[oracle@ocicdb1 ~] tnsping localhost:9000
```

The command output is similar to the following.

```
TNS Ping Utility for Linux: Version 12.1.0.2.0 - Production on 22-JAN-2019  
05:41:57  
Copyright (c) 1997, 2014, Oracle. All rights reserved.  
Used parameter files:  
Used HOSTNAME adapter to resolve the alias  
Attempting to contact (DESCRIPTION=(CONNECT_DATA=(SERVICE_NAME=))  
(ADDRESS=(PROTOCOL=TCP)(HOST=127.0.0.1)(PORT=9000)))  
OK (50 msec)
```

If `tnsping` does not work, then the SSH tunnel is not enabled.

For Oracle RAC, this step must be repeated on all of the source servers.

Index

A

abort job command, [H-1](#)
action template, [9](#)
add imagetype command, [H-2](#)

B

BACKUP_PATH, [E-1](#)

D

DATAPATCH_WITH_ONE_INSTANCE_RUNNIN
G, [E-2](#)
deinstall, [3](#)

E

encryption requirements, [B-1](#)

H

HOST, [E-3](#)

K

key pair without passphrase, [I-3](#)

L

list phases in a migration job, [11](#)

M

MAX_DATAPATCH_DURATION_MINS, [E-3](#)
migration job
 list phases, [11](#)
 rerun, [17](#)
 status, [11](#)

O

OPC_CONTAINER, [E-4](#)

R

requiremenmts, encryption, [B-1](#)
rerun a migration job, [17](#)
response file parameters
 BACKUP_PATH, [E-1](#)
 DATAPATCH_WITH_ONE_INSTANCE_RUNNING,
 [E-2](#)
 HOST, [E-3](#)
 MAX_DATAPATCH_DURATION_MINS, [E-3](#)
 OPC_CONTAINER, [E-4](#)
 SHUTDOWN_SRC, [E-5](#)
 SKIP_FALLBACK, [E-6](#)
 SKIP_SRC_SERVICE_RETENTION, [E-6](#)
 SRC_BASTION_HOST_IP, [E-6](#)
 SRC_BASTION_IDENTITY_FILE, [E-7](#)
 SRC_BASTION_PORT, [E-7](#)
 SRC_BASTION_USER, [E-8](#)
 SRC_CONFIG_LOCATION, [E-9](#)
 SRC_HOST_IP, [E-10](#)
 SRC_HTTP_PROXY_PORT, [E-11](#)
 SRC_HTTP_PROXY_URL, [E-11](#)
 SRC_OSS_PROXY_HOST, [E-11](#)
 SRC_OSS_PROXY_PORT, [E-11](#)
 SRC_RMAN_CHANNELS, [E-12](#)
 SRC_SSH_RETRY_TIMEOUT, [E-12](#)
 SRC_TIMEZONE, [E-12](#)
 SRC_ZDLRA_WALLET_LOC, [E-12](#)
 TGT_BASTION_HOST_IP, [E-13](#)
 TGT_BASTION_IDENTITY_FILE, [E-13](#)
 TGT_BASTION_PORT, [E-14](#)
 TGT_BASTION_USER, [E-15](#)
 TGT_CONFIG_LOCATION, [E-15](#)
 TGT_DATAACFS, [E-15](#)
 TGT_DATADG, [E-16](#)
 TGT_DB_UNIQUE_NAME, [E-17](#)
 TGT_HOST_IP, [E-18](#)
 TGT_HTTP_PROXY_PORT, [E-18](#)
 TGT_HTTP_PROXY_URL, [E-18](#)
 TGT_OSS_PROXY_HOST, [E-19](#)
 TGT_OSS_PROXY_PORT, [E-19](#)
 TGT_RECOACFS, [E-19](#)
 TGT_RECODG, [E-20](#)
 TGT_REDOACFS, [E-21](#)
 TGT_REDODG, [E-21](#)
 TGT_RMAN_CHANNELS, [E-22](#)

response file parameters (*continued*)

TGT_SKIP_DATAPATCH, [E-22](#)
 TGT_SSH_RETRY_TIMEOUT, [E-23](#)
 TGT_SSH_TUNNEL_PORT, [E-23](#)
 TGT_ZDLRA_WALLET_LOC, [E-23](#)
 ZDLRA_CRED_ALIAS, [E-28](#)
 ZDM_APPLY_LAG_MONITORING_INTERVAL, [E-47](#)
 ZDM_BACKUP_RETENTION_WINDOW, [E-30](#)
 ZDM_CURL_LOCATION, [E-31](#)
 ZDM_LOG_OSS_PAR_URL, [E-31](#)
 ZDM_OPC_RETRY_COUNT, [E-33](#)
 ZDM_OPC_RETRY_WAIT_TIME, [E-33](#)
 ZDM_SRC_TNS_ADMIN, [E-39](#)
 ZDM_TGT_UPGRADE_TIMEZONE, [E-46](#)
 ZDM_USE_EXISTING_UNDO_SIZE, [E-46](#)

S

SHUTDOWN_SRC, [E-5](#)
 SKIP_FALLBACK, [E-6](#)
 SKIP_SRC_SERVICE_RETENTION, [E-6](#)
 SRC_BASTION_HOST_IP, [E-6](#)
 SRC_BASTION_IDENTITY_FILE, [E-7](#)
 SRC_BASTION_PORT, [E-7](#)
 SRC_BASTION_USER, [E-8](#)
 SRC_CONFIG_LOCATION, [E-9](#)
 SRC_HOST_IP, [E-10](#)
 SRC_HTTP_PROXY_PORT, [E-11](#)
 SRC_HTTP_PROXY_URL, [E-11](#)
 SRC_OSS_PROXY_HOST, [E-11](#)
 SRC_OSS_PROXY_PORT, [E-11](#)
 SRC_RMAN_CHANNELS, [E-12](#)
 SRC_SSH_RETRY_TIMEOUT, [E-12](#)
 SRC_TIMEZONE, [E-12](#)
 SRC_ZDLRA_WALLET_LOC, [E-12](#)
 SSH key without passphrase, [I-3](#)
 status of migration job, [11](#)

T

TGT_BASTION_HOST_IP, [E-13](#)

TGT_BASTION_IDENTITY_FILE, [E-13](#)
 TGT_BASTION_PORT, [E-14](#)
 TGT_BASTION_USER, [E-15](#)
 TGT_CONFIG_LOCATION, [E-15](#)
 TGT_DATAACFS, [E-15](#)
 TGT_DATADG, [E-16](#)
 TGT_DB_UNIQUE_NAME, [E-17](#)
 TGT_HOST_IP, [E-18](#)
 TGT_HTTP_PROXY_PORT, [E-18](#)
 TGT_HTTP_PROXY_URL, [E-18](#)
 TGT_OSS_PROXY_HOST, [E-19](#)
 TGT_OSS_PROXY_PORT, [E-19](#)
 TGT_RECOACFS, [E-19](#)
 TGT_RECODG, [E-20](#)
 TGT_REDOACFS, [E-21](#)
 TGT_REDODG, [E-21](#)
 TGT_RMAN_CHANNELS, [E-22](#)
 TGT_SKIP_DATAPATCH, [E-22](#)
 TGT_SSH_RETRY_TIMEOUT, [E-23](#)
 TGT_SSH_TUNNEL_PORT, [E-23](#)
 TGT_ZDLRA_WALLET_LOC, [E-23](#)

U

uninstall, [3](#)

Z

ZDLRA_CRED_ALIAS, [E-28](#)
 ZDM_APPLY_LAG_MONITORING_INTERVAL, [E-47](#)
 ZDM_BACKUP_RETENTION_WINDOW, [E-30](#)
 ZDM_CURL_LOCATION, [E-31](#)
 ZDM_LOG_OSS_PAR_URL, [E-31](#)
 ZDM_OPC_RETRY_COUNT, [E-33](#)
 ZDM_OPC_RETRY_WAIT_TIME, [E-33](#)
 ZDM_SRC_TNS_ADMIN, [E-39](#)
 ZDM_TGT_UPGRADE_TIMEZONE, [E-46](#)
 ZDM_USE_EXISTING_UNDO_SIZE, [E-46](#)
 zdmcli
 abort job, [H-1](#)
 add imagetype, [H-2](#)